

Grid Computing in SAS® 9.4 Third Edition



The correct bibliographic citation for this manual is as follows: SAS Institute Inc. 2014. *Grid Computing in SAS® 9.4, Third Edition.* Cary, NC: SAS Institute Inc.

Grid Computing in SAS® 9.4, Third Edition

Copyright © 2014, SAS Institute Inc., Cary, NC, USA

All rights reserved. Produced in the United States of America.

For a hard-copy book: No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, or otherwise, without the prior written permission of the publisher, SAS Institute Inc.

For a web download or e-book: Your use of this publication shall be governed by the terms established by the vendor at the time you acquire this publication.

The scanning, uploading, and distribution of this book via the Internet or any other means without the permission of the publisher is illegal and punishable by law. Please purchase only authorized electronic editions and do not participate in or encourage electronic piracy of copyrighted materials. Your support of others' rights is appreciated.

U.S. Government License Rights; Restricted Rights: The Software and its documentation is commercial computer software developed at private expense and is provided with RESTRICTED RIGHTS to the United States Government. Use, duplication or disclosure of the Software by the United States Government is subject to the license terms of this Agreement pursuant to, as applicable, FAR 12.212, DFAR 227.7202-1(a), DFAR 227.7202-3(a) and DFAR 227.7202-4 and, to the extent required under U.S. federal law, the minimum restricted rights as set out in FAR 52.227-19 (DEC 2007). If FAR 52.227-19 is applicable, this provision serves as notice under clause (c) thereof and no other notice is required to be affixed to the Software or documentation. The Government's rights in Software and documentation shall be only those set forth in this Agreement.

SAS Institute Inc., SAS Campus Drive, Cary, North Carolina 27513-2414.

August 2014

SAS provides a complete selection of books and electronic products to help customers use SAS® software to its fullest potential. For more information about our offerings, visit **support.sas.com/bookstore** or call 1-800-727-3228.

SAS® and all other SAS Institute Inc. product or service names are registered trademarks or trademarks of SAS Institute Inc. in the USA and other countries. ® indicates USA registration.

Other brand and product names are trademarks of their respective companies.



Gain Greater Insight into Your SAS® Software with SAS Books.

Discover all that you need on your journey to knowledge and empowerment.





Contents

	What's New in SAS Grid Manager 9.4	
	PART 1 Grid Computing for SAS 1	
Chapter 1 • What Is	s SAS Grid Computing?	. 3
	SAS Grid Computing Basics	
	SAS Grid Topology	
	What Types of Processing Does a Grid Support? What Business Problems Can a Grid Solve?	
	what Business Problems Can a Grid Solve?	. 8
Chapter 2 • Plannii	ng and Configuring a Grid Environment	
	Installation and Configuration Overview	
	Configuring the File Server	
	Installing Platform Suite for SAS	
	Configuring the Grid Control Server	
	Configuring the Grid Nodes	
	Configuring Client Applications	
	Modifying SAS Logical Grid Server Definitions	
	Modifying Grid Monitoring Server Definitions	
	Installing and Configuring SAS Grid Manager Client Utility	
	instanting and Configuring SAS Environment Manager in a Grid Environment	24
Chapter 3 • Manag	ing the Grid	25
onaptor o manag	Overview of Grid Management	
	Modifying Configuration Files with Platform RTM for SAS	
	Specifying Job Slots for Machines	
	Using Queues	
	Working with Grid Options Sets	
	Defining and Specifying Resources	
Chantar 1 - Enabli	ng SAS Applications to Burn on a Crid	20
Chapter 4 • Enabili	ng SAS Applications to Run on a Grid	
	Overview of Grid Enabling	
	Submitting Batch SAS Jobs to the Grid	
	Comparing Grid Submission Methods	
	Enabling Distributed Parallel Execution of SAS Jobs	
	Using SAS Studio with a SAS Grid	
	Using SAS Studio with a SAS Orid	
	Using SAS Stored Processes with a SAS Grid	
	Using SAS Data Integration Studio with a SAS Grid	
	Using SAS Enterprise Miner with a SAS Grid	
	Using SAS Risk Dimensions with a SAS Grid	
	Using SAS Grid Manager for Server Load Balancing	
	Come Data Ond Manager for Server Load Datalients	JJ
Chanter 5 • High A	vailability	65

	High Availability and SAS Grid Manager	65
	Setting Up High Availability for Critical Applications	
	Restarting Jobs	
Chapter 6 • Using	Grid Management Applications	73
J 1,111 1 1 1 3	Using Platform RTM for SAS	
	Using the Grid Manager Plug-in for SAS Environment Manager	
	Using the Grid Manager Plug-in for SAS Management Console	
Chapter 7 • Troubl	eshooting	89
•	Overview of the Troubleshooting Process	
	Verifying the Network Setup	90
	Verifying the Platform Suite for SAS Environment	. 91
	Verifying the SAS Environment	. 93
	Debugging Grid Jobs	96
	Fixing Issues with the Grid Manager Plug-in for SAS Environment Manager	96
Chapter 8 • SAS Fo	unctions for SAS Grid	
Chapter 9 • SASGS	SUB Command	115
•	SASGSUB Overview	
	Disabling SASGSUB Actions	116
	Dictionary	116
	PART 3 Appendix 129	
Appendix 1 • Supp	ported Job Options	131

What's New in SAS Grid Manager 9.4

Overview

SAS Grid Manager has the following new features and enhancements:

- Support for grid options sets has been added.
- Support for grid-launched workspace servers has been added.
- New options have been added to the SAS Grid Manager Client Utility, including support for grid options sets, support for interactive SAS sessions and command processing, and support for waiting for results from grid jobs.
- New job options for Platform Suite for SAS have been added.
- A Grid Manager plug-in has been added to SAS Environment Manager.

Support for Grid Options Sets

A grid options set is a collection of grid options, SAS options, and required resources that are associated with a particular SAS client application. The purpose of a grid options set is to enable a SAS grid administrator to define a collection of options in SAS metadata. These options map to one or more SAS client applications and are automatically applied to workloads submitted to the grid based on the identity of the user accessing the client application. Some of the client applications that support grid options sets include the following:

- SAS Data Integration Studio
- · SAS Grid Manager Client Utility
- SAS sessions that use the grdsvc enable statement to submit jobs to the grid
- · Grid-launched servers

Support for Grid-Launched Servers

With grid-launched servers, when an application requests a SAS workspace server from the object spawner, the spawner passes the request on to SAS Grid Manager. SAS Grid Manager checks the machines on the grid, using the grid's policy management to determine which host is the least busy, and starts the server. Because the load-balanced servers are started by SAS Grid Manager, jobs on these servers appear as LSF jobs.

In the first maintenance release after SAS 9.4, stored process servers and pooled workspace servers can also be grid-launched.

New Options for the SAS Grid Manager Client Utility

The following new options have been added to the SAS Grid Manager Client Utility (SASGSUB):

-GRIDOPTSET

specifies the name of a grid options set.

-GRIDWAITTIMEOUT

specifies that the SAS Grid Manager Client Utility waits until either the job has completed running or a specified time-out value is reached.

-GRIDWAITRESULTS

specifies that the SAS Grid Manager Client Utility waits until the job has completed running (either successfully or with an error) and then returns the results of the processing.

_PROMPT

when used as a value for the METAUSER or GRIDUSER parameters, specifies that the SAS Grid Manager Client Utility prompts the user for a user ID.

In the first maintenance release after SAS 9.4, support has been added to the SAS Grid Manager Client Utility to support interactive mode. These options enable you to start an interactive SAS session on the grid, using either SAS Display Manager mode or UNIX line mode, or to run an arbitrary command. It also enables you to monitor the output from SAS or a command running in batch mode.

-GRIDRUNSASLM

specifies that the SASGSUB command runs a SAS session in line mode and that standard output and standard error are displayed by SASGSUB. SASGSUB also redirects standard input to the SAS session running on the grid. The grid must be on UNIX.

-GRIDRUNSASDMS

specifies that the SASGSUB command runs a SAS session in SAS Display Manager mode. Standard output and standard error are displayed by SASGSUB, and the X Windows session is directed to the host and port specified on the -GRIDRUNSASDMS argument. The grid must be on UNIX.

-GRIDRUNCMDINT

specifies that an arbitrary command is run on the grid in interactive mode. Standard output and standard error are displayed by SASGSUB. Standard input is directed to the program running on the grid.

-GRIDWATCHOUTPUT

when SASGSUB is used for batch processing, specifies that the log output and the list output of the batch job are displayed on the user's machine.

New Job Options

The following job options that are supported by Platform Suite for SAS have been added:

app

specifies the LSF application name to use.

maxpendingtime

specifies how long a job waits in the pending state before being terminated.

specifies a job name to be used for all jobs.

Grid Manager Plug-in for SAS Environment Manager

In the second maintenance release after SAS 9.4, a Grid Manager plug-in has been added to SAS Environment Manager. This plug-in enables you to perform these tasks:

- View information about LSF clusters
- View information about and manage grid jobs
- View information about and manage hosts on the grid
- View information about and manage queues
- View information about and manage high availability applications
- View audit records

Recommended Reading

- SAS/CONNECT User's Guide
- SAS Deployment Wizard User's Guide
- SAS Intelligence Platform: Installation and Configuration Guide
- SAS Language Reference: Dictionary
- SAS Macro Language: Reference
- Scheduling in SAS

For a complete list of SAS books, go to support.sas.com/bookstore. If you have questions about which titles you need, please contact a SAS Book Sales Representative:

SAS Books SAS Campus Drive Cary, NC 27513-2414 Phone: 1-800-727-3228

Fax: 1-919-677-8166 E-mail: sasbook@sas.com

Web address: support.sas.com/bookstore

Grid Computing for SAS

Chapter 1 What Is SAS Grid Computing?	3
Chapter 2 Planning and Configuring a Grid Environment	11
Chapter 3 Managing the Grid	25
Chapter 4 Enabling SAS Applications to Run on a Grid	39
Chapter 5 High Availability	65
Chapter 6 Using Grid Management Applications	73
Chapter 7 Troubleshooting	80

Chapter 1

What Is SAS Grid Computing?

SAS Grid Computing Basics	3
SAS Grid Topology	5
What Types of Processing Does a Grid Support?	6
Multi-User Workload Balancing	6
Parallel Workload Balancing	
Distributed Enterprise Scheduling	
SAS Applications That Support Grid Processing	
What Business Problems Can a Grid Solve?	8
Many Users on Single Resource	8
High Availability	9
Increased Data Growth	
Running Larger and More Complex Analysis	9
Need for a Flexible IT Infrastructure	

SAS Grid Computing Basics

A SAS grid computing environment is one in which SAS computing tasks are distributed among multiple computers on a network, all under the control of SAS Grid Manager. In this environment, workloads are distributed across a grid cluster of computers. This workload distribution enables the following functionality:

Workload balancing

enabling multiple users in a SAS environment to distribute workloads to a shared pool of resources.

Accelerated processing

allowing users to distribute subtasks of individual SAS jobs to a shared pool of resources. The grid enables the subtasks to run in parallel on different parts of the grid, which completes the job much faster.

Scheduling jobs

allowing users to schedule jobs, which are automatically routed to the shared resource pool at an appropriate time.

SAS Grid Manager provides load balancing, policy enforcement, efficient resource allocation, prioritization, and a highly available analytic environment for SAS products and solutions running in a shared grid environment. It also separates the SAS applications from the infrastructure used to execute the applications. This enables you to transparently add or remove hardware resources as needed and also provides tolerance of

hardware failures within the grid infrastructure. SAS Grid Manager integrates the resource management and scheduling capabilities of the Platform Suite for SAS with the SAS 4GL syntax and subsequently with several SAS products and solutions.

SAS Grid Manager includes these components, as illustrated in Figure 1.1 on page 5.:

Grid Manager plug-in

a plug-in for SAS Management Console that provides a monitoring and management interface for the jobs and resources in your grid

grid syntax

the SAS syntax necessary to grid-enable the SAS workload

SAS Grid Manager Client Utility

a command-line utility that enables you to submit SAS programs, operating system commands, or command files to a grid for processing. This utility allows a grid client to submit SAS programs to a grid without requiring that SAS be installed on the machine performing the submission. It also enables jobs to be processed on the grid without requiring that the client remain active.

Platform Suite for SAS

components provided by Platform Computing to provide efficient resource allocation, policy management, and load balancing of SAS workload requests.

The Platform Suite for SAS includes these components:

Load Sharing Facility (LSF)

this facility dispatches all jobs submitted to it, either by Process Manager or directly by SAS, and returns the status of each job. LSF also manages any resource requirements and performs load balancing across machines in a grid environment.

Process Manager (PM)

this is the interface used by the SAS scheduling framework to control the submission of scheduled jobs to LSF and manage any dependencies between the jobs. Process Manager includes two optional components, Calendar Editor and Flow Manager.

Calendar Editor is a scheduling client for a Process Manager server. It enables you to create new calendar entries for time dependencies.

Flow Manager provides a visual representation of flows that are created and scheduled through the Schedule Manager plug-in as well as reports scheduled through SAS Web Report Studio. Flow Manager enables you to view and update the status of jobs in a flow and rerun jobs.

Grid Management Services (GMS)

this is the interface to the Grid Manager plug-in in SAS Management Console. It provides the run-time information about jobs, hosts, and queues for display in SAS Management Console.

Enterprise Grid Orchestrator (EGO)

provides support for critical service failover in a a highly available (HA) environment. EGO provides functions for monitoring critical services, restarting services if they stop, and starting services on a failover host when needed.

Platform RTM for SAS


a web-based tool that enables you to graphically view the status of devices and services in a SAS grid environment as well as manage the policies and configuration of the grid. This application is not part of Platform Suite for SAS but can be

downloaded separately from http://support.sas.com/demosdownloads/ setupcat.jsp?cat=SAS+Grid+Manager

SAS Grid Topology

As illustrated below, a grid configuration consists of these main components:

Figure 1.1 Grid Topology



Grid control server

this machine controls distribution of jobs to the grid. Any machine in the grid can be designated as the grid control server. Also, you can choose whether to configure the grid control server as a grid resource capable of receiving work. This machine must contain Base SAS, SAS/CONNECT, and Platform LSF. It typically also contains Platform PM and Platform GMS. The grid control server might also configure a SAS workspace server so that SAS applications (SAS Data Integration Studio, SAS Enterprise Miner, SAS Enterprise Guide, and SAS Add-In for Microsoft Office) can run programs that take advantage of the grid.

Grid node

these machines are grid computing resources that are capable of receiving the work that is being distributed to the grid. The number of nodes in a grid depends on the size, complexity, and volume of the jobs that are run by the grid. You can add or remove nodes as specified by your business needs. Each grid node must contain Base SAS, SAS/CONNECT, Platform LSF, and any applications and solutions needed to run grid-enabled jobs.

Central file server

this machine is used to store data for jobs that run on the grid. In order to simplify installation and ease maintenance, you can also install the SAS binaries on the central file server.

Metadata server

this machine contains the metadata repository that stores the metadata definitions needed by SAS Grid Manager and other SAS applications and solutions that are running on the grid. Although it is recommended that the SAS Metadata Server be on a dedicated machine, it can be run on the grid control server.

SAS Management Console

this application is used to manage the definitions in the metadata repository, to submit jobs to the grid through the Schedule Manager plug-in, and to monitor and manage the grid through the Grid Manager plug-in.

Grid clients

submits jobs to the grid for processing, but is not part of the grid resources available to execute work.

Examples of grid clients are:

- a SAS Data Integration Studio client, a SAS Enterprise Miner client, or a SAS Enterprise Guide client that uses a workspace server in the grid. Platform LSF is not required on this client machine.
- a SAS Management Console client, that uses the Schedule Manager plug-in or another application to schedule SAS workflows. Platform LSF is not required on this client machine.
- a SAS Foundation install that is used to run a program that submits work to the
 grid. The submitted work can be entire programs or programs broken into
 parallel chunks. This client must have Base SAS, SAS/CONNECT, and the client
 components of Platform LSF installed. Platform LSF client is required to submit
 the SAS workload to the grid.
- a SAS Grid Manager Client Utility. SAS is not required to be installed on this
 client, but Platform LSF client is required to submit the SAS workload to the
 grid.

What Types of Processing Does a Grid Support?

Multi-User Workload Balancing

Most organizations have many SAS users performing a variety of query, reporting, and modeling tasks and competing for the same resources. SAS Grid Manager can help bring order to this environment by providing capabilities such as the following:

- specifying which jobs get priority
- deciding the share of computing resources used by each job
- controlling the number of jobs that are executing at any one time

In practice, SAS Grid Manager acts as a gatekeeper for the jobs submitted to the grid. As jobs are submitted, SAS Grid Manager dispatches the job to grid nodes, preventing any one machine from being overloaded. If more jobs are submitted than can be run at once, SAS Grid Manager submits as many jobs as can be run. The rest of the jobs are held in a queue until resources are free, and then the jobs are dispatched to be run. SAS Grid Manager can also use job priority to determine whether a job is run immediately or held in a queue.

The application user notices little or no difference when working with a grid. For example, users can define a key sequence to submit a job to a grid rather than running it on their local workstation. Batch jobs can be run using the SAS Grid Manager Client Utility.

Parallel Workload Balancing

Some SAS programs consist of subtasks that are independent units of work and can be distributed across a grid and executed in parallel. You can use SAS syntax to identify the parallel units of work in these programs, and then use SAS Grid Manager to distribute the programs across the grid. Using parallel workload balancing can substantially accelerate the entire application.

Applications such as SAS Data Integration Studio, SAS Risk Dimensions, and SAS Enterprise Miner are often used for iterative processing. In this type of processing, the same analysis is applied to different subsets of data or different analysis is applied to a single subset of data. Using SAS Grid Manager can improve the efficiency of these processes, because the iterations can be assigned to different grid nodes. Because the jobs run in parallel, the analysis completes more quickly and with less strain on computing resources.

Distributed Enterprise Scheduling

The Schedule Manager plug-in for SAS Management Console provides the ability to schedule user-written SAS programs as well as jobs from numerous SAS applications. You can schedule the jobs and programs to run when specified time or file events occur. The jobs are then run on the grid using the resource and prioritization policies established by SAS Grid Manager.

SAS Applications That Support Grid Processing

The following table lists the SAS applications that currently support grid processing and the type of processing that each supports.

Table 1.1 Grid Support in SAS Applications

SAS Application	Multi-User Workload Balancing	Parallel Workload Balancing	Distributed Enterprise Scheduling
Any SAS program	yes	yes, with modifications	yes
SAS Grid Manager Client Utility (SASGSUB)	yes	yes	
SAS Enterprise Guide	yes	yes	
SAS Add-In for Microsoft Office	yes	yes	

SAS Application	Multi-User Workload Balancing	Parallel Workload Balancing	Distributed Enterprise Scheduling
SAS Data Integration Studio	yes	yes	yes
SAS Enterprise Miner	yes	yes	
SAS Risk Dimensions	yes	yes, with modifications	
SAS Web Report Studio			yes
SAS Marketing Automation			yes
SAS Marketing Optimization			yes
SAS JMP Genomics		yes	
SAS Demand Forecasting for Retail		yes	
SAS products or solutions that use workspace server load balancing	yes		
SAS stored processes	yes, with limitations	yes, with limitations	

For a current list of SAS applications that support grid processing, see http:// support.sas.com/rnd/scalability/grid/index.html.

What Business Problems Can a Grid Solve?

Many Users on Single Resource

An organization might have multiple users submitting jobs to run on one server. When the environment is first configured, the server might have been sufficient to handle the number of users and jobs. However, as the number of users submitting jobs grows, the load on the server grows. The increased load might lead to slower processing times and system crashes. In a SAS grid environment, jobs are automatically routed to any one of the servers on the grid. This spreads the computing load over multiple servers, and diminishes the chances of a server becoming overloaded. If the number of jobs exceeds the resources available, the jobs are queued until resources become available. If the number of users continues to increase, you can increase capacity by adding servers to the grid.

High Availability

Your organization might have services and long-running SAS programs that are critical to your operations. The services must be available at all times, even if the servers that are running them become unavailable. The SAS programs must complete in a timely manner, even if something happens to cause them to fail. For a SAS program that takes a long time to run, this means that the program cannot be required to restart from the beginning if it ends prematurely.

You can configure the critical services within your SAS grid environment to be highly available. SAS Grid Manager can monitor the critical services, detect if they fail or if the machine on which they are running fails, and automatically start the services on a failover host. Either a hardware load balancer or DNS name resolution is used to redirect clients to the service running on the failover host. This ensures that critical services remain available to clients without any manual intervention.

By using options on the SAS Grid Manager Client Utility, you can specify that SAS programs submitted to the grid are automatically restarted from the point where they stopped if they end before completion. The job restarts from the last completed procedure, DATA step, or labeled section. Jobs that take a long time to run do not have to start over at the beginning. You can also use the restart capability with queue options that automatically requeue jobs that end prematurely to provide a complete highavailability environment for SAS programs.

Increased Data Growth

Your organization might have a process running to analyze a certain volume of data. Although the server that is processing the job is sufficient to handle the current volume of data, the situation might change if the volume of data increases. As the amount of data increases, the load on the server increases, which can lead to longer processing times or other problems. Changing to a larger-capacity server can involve considerable expense and service interruption.

A SAS grid environment can grow to meet increases in the amount of data processed. If the volume of data exceeds the capacity of a server on the grid, the processing load can be shared by other grid servers. If the volume continues to increase, you can add servers to the grid without having to make configuration changes to your processes. Adding servers to the grid is also more cost-effective than replacing a single large server, because you can add smaller servers to handle incremental increases in data volume.

Running Larger and More Complex Analysis

Your organization might have a process running to perform a certain level of analysis on data. If you want to increase the complexity of the analysis being performed, the increased workload puts a greater strain on the processing server. Changing the computing power of the server involves considerable expense and interrupts network availability.

Using a SAS grid environment enables you to add computing power by adding additional computers on the grid. The analysis job can be divided up among the grid nodes, which enables you to perform more complex analysis without increasing the load on any single machine.

Need for a Flexible IT Infrastructure

Your organization's ability to perform the data analysis that you need depends on a flexible computing infrastructure. You must be able to add needed resources quickly and in a cost-effective manner as the load increases. You must also be able to handle maintenance issues (such as adding or replacing resources) without disrupting your work. A SAS grid environment enables you to maintain a flexible infrastructure without disrupting your operations.

As your data-processing needs grow, you can incrementally add computing resources to your grid by adding smaller, less-expensive servers as new server nodes. This ability prevents you from having to make large additions to your environment by adding large and expensive servers.

When you need to perform maintenance on machines in the grid, the grid can still operate without disruption. When you take the servers offline for maintenance or upgrades, SAS Grid Manager routes to work to the machines that are still online. Users who send work to the grid for processing do not have to change their way of working. Work that is sent to the grid is processed just as before.

Likewise, the SAS grid environment adapts if a computer fails on the grid. Because SAS Grid Manager automatically avoids sending work to the failed machine, the rest of the grid is still available for processing and users do not see any disruption.

Chapter 2

Planning and Configuring a Grid Environment

Installation and Configuration Overview	. 11
Configuring the File Server	12
Installing Platform Suite for SAS	12
Configuring the Grid Control Server	12
Configuring the Grid Nodes	17
Configuring Client Applications	17
Modifying SAS Logical Grid Server Definitions	17
Modifying Grid Monitoring Server Definitions	. 20
Installing and Configuring SAS Grid Manager Client Utility	21
Installation Overview	
Installation Prerequisites	
Configuring the SAS Grid Manager Client Utility	
Using the SASGSUB Configuration File	
$ In stalling \ and \ Configuring \ SAS \ Environment \ Manager \ in \ a \ Grid \ Environment \ . $	24

Installation and Configuration Overview

The process of configuring a grid consists of two main tasks:

- 1. Installing and configuring Platform Suite for SAS. Instructions for installing and configuring Platform Suite for SAS are found on the SAS website at http://support.sas.com/rnd/scalability/grid/gridinstall.html.
- 2. Installing and configuring SAS products and metadata definitions on the grid. You can either install all SAS products on all machines in the grid or install different sets of SAS applications on sets of machines in the grid. However, Base SAS, SAS/CONNECT, and SAS Grid Manager must be installed on all grid machines. Using a grid plan file with the SAS Deployment Wizard guides you through the process of installing and configuring the SAS applications and metadata definitions on each machine in the grid. You must specify the same directory structure on all machines in the grid.

For information about performing a planned installation, see SAS Intelligence Platform: Installation and Configuration Guide.

Configuring the File Server

The central file server is a critical component of a grid environment. It is essential for each application on a grid node to be able to efficiently access data. Slowdowns caused by the performance of the file storage system could reduce the effectiveness and benefit of using a grid. The amount of storage required and the type of I/O transactions help determine the type of file storage system that best meets your needs.

Assuming that the SAS jobs running on the grid perform an equal number of reads and writes, it is recommended that the file system be able to sustain 50–70 MB per second per core. This level can be adjusted up or down, depending on the level of I/O activity of your SAS jobs. For information about choosing and configuring a file system, see *Best Practices for Data Sharing in a Grid Distributed SAS Environment*, which is available at http://support.sas.com/rnd/scalability/grid/gridpapers.html.

Installing Platform Suite for SAS

SAS Grid Manager includes Platform Suite for SAS from Platform Computing. The SAS website provides step-by-step instructions on installing and configuring the Platform Suite for SAS. These instructions are available from http://support.sas.com/rnd/scalability/grid/gridinstall.html.

Information for installing Platform Suite for SAS is available for both Windows and UNIX platforms.

The installation process for Platform Suite for SAS installs these components:

- Platform Process Manager
- · Platform LSF
- · Platform Grid Management Service

Configuring the Grid Control Server

After you install and configure Platform Suite for SAS, you can use the SAS Deployment Wizard to configure the grid control server. The SAS Deployment Wizard installs and configures these components:

Table 2.1 SAS Deployment Wizard Grid Control Server Components

Installed SAS Software Components	Configured SAS Software Components
 SAS Foundation (including Base SAS and SAS/CONNECT) SAS Management Console Grid Manager Plug-in for SAS Management Console 	 Platform Process Manager Server Grid Monitoring Server SAS Application Server (SAS Logical DATA Step Batch Server, SAS Logical Grid Server, SAS Logical Workspace Server)
	Object SpawnerGrid script file

If you are installing Platform Suite for SAS on a UNIX machine, you might need to source the profile.lsf file before you start the SAS Deployment Wizard. The hostsetup command in the installation procedure for Platform LSF version 7 includes the ability to source the LSF profile to the default profile for all users. If this option was not used in the installation process or did not work correctly, you must use the following procedure. This procedure enables the SAS Deployment Wizard to find the addresource utility. To source the file, follow these steps:

- 1. Start the LSF daemons. The easiest method for doing this is to reboot the computer on which Platform Suite for SAS is installed.
- 2. Using the default profile for the machine, issue this command:
 - . LSF TOP/conf/profile.lsf


Replace LSF TOP with the directory in which Platform LSF is installed. Note that the command starts with a period.

The amount of user input that is required during the installation and configuration process depends on whether you choose an Express, Typical, or Custom install. For information about running the SAS Deployment Wizard, see SAS Deployment Wizard User's Guide.

An Express installation does not request any grid-specific information. Default values are used in all cases, so you must verify that these values match the values needed for your environment.

During an Express install, the Platform Process Manager information page enables you to specify the host name and port of the machine on which Platform Process Manager installed.


Figure 2.1 Platform Process Manager Page for Express Install



During the installation and configuration process for a Custom install, the SAS Deployment Wizard displays these pages that request grid-specific information:


1. The SAS Grid Control Server page enables you to specify the name of the Logical SAS Grid Server and the SAS Grid Server. Specify the grid control server machine.

Figure 2.2 SAS Grid Control Server Page




2. The Grid Control Server: Job Information page enables you to specify how jobs run on the grid. Specify the command used to start the server session on the grid, workload values, and additional options for the grid. The directory in the Grid Shared Directory Path field is used by grid programs (such as the SAS Grid Manager Client Utility) to store information. The location must be accessible by all grid nodes, and all grid users must have Read and Write access to the directory. For information about the values used in these fields, see "Modifying SAS Logical Grid Server Definitions" on page 17.

Figure 2.3 Grid Control Server: Job Information Page




3. The SAS Grid Monitoring Server page enables you to specify the name, machine, and port for the grid monitoring server.

Figure 2.4 SAS Grid Monitoring Server Page



4. The Platform Process Manager page enables you to specify the server on which you installed Platform Suite for SAS and the port that is used to connect to the server.

Figure 2.5 Platform Process Manager Page for Custom Install



Configuring the Grid Nodes

After you have installed and configured the grid control server, you can use the SAS Deployment Wizard to configure the grid nodes. The SAS Deployment Wizard installs and configures these components:

Table 2.2 Required Software Components for Grid Nodes

Installed SAS Software Components	Configured SAS Software Components
SAS Foundation (Base SAS, SAS/CONNECT)	SAS Grid Node, script file

If more than one application server contains a logical grid server, you must choose which application server to use.

For information about the values required during a planned installation, see SAS Intelligence Platform: Installation and Configuration Guide.

Note: The configuration directory structure for each grid node must be the same as that of the grid control server.

Configuring Client Applications

After the grid nodes have been installed and configured, you can install and configure the software required for the client applications that will use the grid. The software required depends on the type of client application. Applications such as SAS Data Integration Studio that can submit jobs through a workspace server do not need to install anything other than the client application. Applications such as Base SAS that submit jobs to the grid must also install Platform Suite for SAS in order to send jobs to the grid. When you install SAS Management Console, you must also install the SAS Grid Manager plug-in. SAS Management Console is used to monitor and control the grid.

Modifying SAS Logical Grid Server Definitions


The initial configuration of the logical grid servers is performed by the SAS Deployment Wizard. However, a SAS grid administrator might need to modify the existing grid metadata or add new grid metadata definitions.

A SAS administrator performs these steps to specify or modify the required and optional properties as metadata for the SAS Grid Server:

- 1. In SAS Management Console, open the metadata repository that contains the metadata for the Logical Grid Server.
- 2. In the navigation tree, select **Server Manager**.

- 3. Expand the folders under **Server Manager** until you see the metadata objects for the SAS application server, such as **SASApp**, and its Logical Grid Server component.
- 4. Expand the Logical Grid Server component so that you see the metadata object for the Grid Server.
- 5. Right-click the metadata object for the Grid Server, and select **Properties**.
- 6. In the Grid Server Properties window, click the **Options** tab.

Figure 2.6 Grid Server Properties



7. The fields on the **Options** tab are:

Provider

the grid middleware provider. The current default value is Platform. This value is used to communicate with the grid control server.

Grid Command

the script, application, or service that Platform Suite for SAS uses to start server sessions on the grid nodes. Any SAS options that are included in this command are passed to the grid jobs. You can specify any additional SAS options in the SAS Options field.

This value is the path to the sasgrid.cmd file (Windows) or sasgrid script file (UNIX). Because this same command is used to start the servers on all grid nodes, the path to the directory on each grid node must be the same. For example: C:\SAS\Grid\Lev1\SASApp\GridServer\sasgrid.

SAS Options

specifies the SAS options that are applied by default to jobs that are sent to the grid. Separate multiple options with a space. Any SAS options that are specified for a specific application mapping override this value.

Required Resources

specifies the name of the resources that are applied by default to jobs that are sent to the grid. Any resources that are specified for a specific application mapping are added to this value. The application server name is displayed in this field by default, but it can be removed if needed.

Grid Options

specifies the grid command options that are applied by default to jobs that are sent to the grid. Examples include the job priority, the job queue, or the user group that is associated with the job. Any grid options that are specified by a grid options set and mapped to a specific application override this value. Job options are specified as name/value pairs in this format. Multiple pairs are separated by semicolons:

```
option-1=value-1; option-2="value-2 with spaces";
... option-n='value-n with spaces';
```

Here is an example of additional options that specify that all jobs that use this logical grid server go to the priority queue in the project "payroll":

```
queue=priority; project='payroll'
```

For a complete list of job options, see Appendix 1, "Supported Job Options," on page 131.

Grid Options Set Mappings

lists the grid server's mappings of grid options sets to applications for a specified user or group. Each grid option set associates a set of SAS options, required resources, and grid options to a SAS application and user identities that use the grid. To change or remove an entry, click on the entry and select Edit or Delete from the pop-up menu. Click New to create a new application mapping. See "Working with Grid Options Sets" on page 31 for more information about grid options sets.

Advanced Options

enables you to specify the workload and module name. The workload specifies the optional resources that can be processed on the node. The module name specifies the shared library name or Java class name of the grid middleware provider's support plug-in.

- 8. After you complete the field entries, click **OK** to save the changes and close the Grid Server Properties window.
- 9. In the display area (right-hand side) on SAS Management Console, right-click the **Connection** object for the Grid Server, and then select **Properties**.
- 10. In the Properties window for the Grid Server Connection, click the **Options** tab. Here are the fields on this tab:

Authentication Domain

the authentication domain that is used for connections to the server. Set this value to <none> for Platform LSF

Grid Server Address

the host name or network address of the grid control server.

Grid Server Port

the port that is used to connect to the grid control server. This value should always be set to 0 (zero) for Platform LSF.

Modifying Grid Monitoring Server Definitions

The initial configuration of the grid monitoring server is performed by the SAS Deployment Wizard. However, a SAS grid administrator might need to modify the existing grid metadata or add new grid metadata definitions.

A SAS administrator performs these steps to specify or modify the required and optional properties as metadata for the Grid Monitoring Server:

- 1. In SAS Management Console, open the metadata repository that contains the metadata for the SAS Grid Server.
- 2. In the navigation tree, select Server Manager.
- 3. Find the metadata object for the Grid Monitoring Server.
- 4. Right-click the metadata object for the Grid Monitoring Server, and then select **Properties**.
- 5. In the Properties window for the Grid Monitoring Server, click the **Options** tab.
- 6. Here are the fields on the **Options** tab:

Provider

the grid middleware provider. This value is Platform. This value is used to communicate with the grid control server.

Module Name

specifies the shared library name or the class name of the support plug-in for Platform Suite for SAS. Leave this field blank unless directed otherwise by SAS Technical Support.

Options

the options needed by the grid monitoring server to connect to the grid server.

RTM Host Name

specifies the URL for the RTM host.

- 7. After you complete the field entries, click **OK** to save the changes and close the Grid Monitoring Server Properties window.
- 8. In the display area (right side) on SAS Management Console, right-click the **Connection** object for the Grid Monitoring Server, and then select **Properties**.
- 9. In the Properties window for the Grid Monitoring Server Connection, click the **Options** tab. Here are the fields on this tab:

Authentication Domain

the authentication domain that is used for connections to the server. This value is the authentication domain of the machine that Grid Management Services (GMS) is running on.

Host Name

the network address of the grid control server.

Port

the port that is used to connect to the grid control server. The default value is 1976 for Platform Grid Management Service.

10. After you complete the entries, click **OK** to save the changes and close the Grid Monitoring Server Connection Properties window.

Installing and Configuring SAS Grid Manager Client Utility

Installation Overview

The SAS Grid Manager Client Utility enables users to submit SAS programs to a grid for processing without requiring SAS to be installed on the machine that is performing the submission. Platform LSF must be installed on any machine on which the SAS Grid Manager Client Utility runs.

The SAS Grid Manager Client Utility is automatically installed and configured using the SAS Deployment Wizard if the utility is in the plan file.

Installation Prerequisites

The configuration for the SAS Grid Manager Client Utility assumes that all of the following actions have been performed:


- The grid control server has already been installed. The configuration must retrieve the logical grid server definition from metadata.
- The user name under which jobs are submitted is defined in metadata. If not, jobs submitted to the grid fail.

Configuring the SAS Grid Manager Client Utility

The amount of user input that is required during the installation and configuration process depends on whether you choose an Express, Typical, or Custom install. For information about running the SAS Deployment Wizard, see SAS Deployment Wizard User's Guide.


1. The SAS Grid Manager Client Utility: Options page enables you to specify the user credentials that are used to connect to the SAS Metadata Server, the method for transferring files to and from the grid (either through a shared file system or remote copy), and the path to a SAS license file that contains a SAS Grid Manager license (only shown during a custom installation). By default, the metadata is searched for the SAS license file.

Figure 2.7 Grid Manager Client Utility: Options Page




2. If you choose to use remote copy (also known as staging) to transfer files to and from the grid, the SAS Grid Manager Client Utility: Staged File Options page is displayed. This page enables you to specify the path to the directory used to stage files moving into and out of the grid. If you are performing a custom installation, you can also specify the staging host and the path to the staging directory as seen by the staging host.

Figure 2.8 SAS Grid Manager Client Utility: Staged File Options Page



If you choose to use a shared directory to copy files to and from the grid, the SAS Grid Manager: Shared Directory Options page appears. This page enables you to specify the grid-shared directory on the grid control server.

Figure 2.9 SAS Grid Manager Client Utility: Shared Directory Options Page



Using the SASGSUB Configuration File

Most of the options that are used by the SAS Grid Manager Client Utility are contained in the sasgsub.cfg file. This file is automatically created by the SAS Deployment Wizard. These options specify the information that the SAS Grid Manager Client Utility uses every time it runs. The sasgsub.cfg file is located in the Applications/ SASGridManagerClientUtility/<version> directory of the configuration directory. The following information from the SAS Deployment Wizard is collected in the sasgsub.cfg file:

- information to connect to the SAS Metadata Server (SAS Metadata Server name, port, user ID, and password). By default, the metadata password value is set to PROMPT, and the user is prompted for a password.
- the path that is used to store files used by the grid. If you are using a shared file system, then this is the path to the shared file system. If you are staging files, then this is the location where grid clients store files that are retrieved by the grid.
- the name of the SAS Application Server that contains the logical grid server definition.

Installing and Configuring SAS Environment Manager in a Grid Environment

If you are installing SAS Environment Manager in a grid environment where more than one grid machine shares a configuration directory, you must perform additional configuration steps so that the SAS Environment Manager agents point to the correct machine. To run the configuration process, use the script deploy-ev-agents.sh, which you can download from http://support.sas.com/rnd/scalability/grid/HA/gridha.html.

If you are using the SAS Grid Manager plug-in for SAS Environment Manager, you must use the SAS Deployment Wizard to install and configure Platform Web Services. The SAS Deployment Wizard prompts you for the following information:

- Context root for Platform Web Services
- Platform LSF configuration directory
- The name of the Platform Web Services database, as well as a user ID and password for connections to the database

Chapter 3

Managing the Grid

Overview of Grid Management	25
Modifying Configuration Files with Platform RTM for SAS	26
Specifying Job Slots for Machines	27
Using Queues	28
Understanding Queues	
Configuring Queues	
Using the Normal Queue	
Example: A High-Priority Queue	
Example: A Night Queue	29
Example: A Queue for Short Jobs	
Specifying Job Slot Limits on a Queue	. 30
Working with Mismatches between Queues and Workspace Servers	31
Working with Grid Options Sets	31
Understanding Grid Options Sets	31
Merging Option Values	
Creating Grid Options Sets	32
Specifying That an Application Is Grid Capable	. 34
Defining and Specifying Resources	36
Overview	
Defining Resource Names Using Addresource	. 37
Specifying Resource Names Using GRDSVC_ENABLE	
Specifying Resource Names Using the SAS Grid Manager Client Utility	. 37
Specifying Resource Names in SAS Data Integration Studio	. 37

Overview of Grid Management

Most organizations that use SAS consist of a variety of user categories. Each user category has its own needs and expectations. For example, your organization might have these users:

SAS Enterprise Guide and SAS Add-In for Microsoft Office users

These users are usually running interactive programs, and expect immediate results.

SAS Enterprise Miner users

These users might be using multiple machines to train models.

SAS Web Report Studio users

These users might be scheduling reports to run at a specified time.

SAS Risk Dimensions users

These users might be running jobs at night.

Some users in your environment might be running jobs that have a high priority. Other users might be running jobs that require a large number of computing resources. A SAS grid environment must be able to account for all of these different needs, priorities, and workloads.

In order to manage this type of environment, you must be able to control when and where jobs can run in the grid. You can manage grid resources using these strategies:

- Job slots. They enable you to control how many jobs can run concurrently on each
 machine in the grid. This enables you to tune the load that each machine in the grid
 can accept. For example, you can assign a higher number of job slots to highercapacity machines, which specifies that those machines can process more jobs
 concurrently.
- Queues. They enable you to control when jobs can run and what computing resources are available to the jobs that are submitted to the queue. You can create queues based on factors such as job size or priority. You can also define job dispatch windows and run windows for each queue. When you submit a job to a particular queue, the queue settings determine when the job runs and what priority the job has compared to other jobs that have been submitted to the grid. You can also specify the number of job slots across the grid that a queue can use at any one time. By combining the job-slot specification on the hosts and queues, you can specify how work is distributed across the grid.
- Resources. They enable you to specify where jobs are run on the grid by specifying
 resource names on hosts and using matching resource names on jobs. The resource
 names are specified on machines in the grid to indicate what type of job each
 machine should run. When you submit jobs to the grid, you can specify resource
 names to specify which machines should be used to process the job.
- Grid options sets. They enable you to create sets of SAS options, required resources, and grid options. Each options set can then be mapped to a specified combination of a SAS application and a user or user group. For example, you might want to define policies for different applications running on the grid (such as SAS Data Integration Studio and batch SAS programs) as well as for different business units that are using those applications on the grid. After defining the grid, you can define grid options sets that contain the options needed for the different type of processing. Then, you can map the appropriate options sets to each of the user and application combinations that you need.

Modifying Configuration Files with Platform RTM for SAS

You can use Platform RTM for SAS to modify the configuration files that define queues and resources on the grid. The Platform RTM download package contains documentation about performing this task. However, if you use Platform RTM for SAS to change any configuration files, you cannot make any further changes to the files outside of Platform RTM for SAS. Changes in the configuration files are not synchronized with Platform RTM for SAS.

Download Platform RTM for SAS from http://www.sas.com/demosdownloads/setupcat.jsp?cat=SAS+Grid+Manager

Specifying Job Slots for Machines

Platform LSF uses job slots to specify the number of processes that are allowed to run concurrently on a machine. A machine cannot run more concurrent processes than it has job slots. The default number of job slots for a machine is the same as the number of processor cores in the machine.

However, you can configure hosts with fast processors to have more jobs slots than the number of cores by setting the MXJ value for the given host to a fixed number of job slots. This enables the more powerful host to execute more jobs concurrently to take advantage of the processor's speed.

To change the number of job slots on a grid node, follow these steps:

- 1. Log on to the grid control server as the LSF Administrator (Isfadmin).
- 2. Open the file lsb.hosts, which is located in the directory LSF-install-dir\conf \lsbatch\cluster-name\configdir. This is the LSF batch configuration file. Locate the Host section of the file, which contains an entry for a default grid node.

```
Begin
Host
                                      tmp DISPATCH WINDOW
HOST NAME MXJ
                 r1m
                                ls
                                                             #Keywords
                          pq
                  ()
                          ()
                                ()
                                       ()
default
                                               ()
                                                              #Example
End Host
```

- 3. Edit this file to specify the maximum number of job slots for all nodes or for each node. There are two ways you can do this.
 - To specify the total number of job slots per node, edit the line for the default node. Here is an example:

Begin Host						
HOST_NAME MXJ	r1m	pg	ls	tmp	DISPATCH_WINDOW	#Keywords
default !	()	()	()	()	()	#Example
End Host						

The value! represents one job slot per core for each node in the grid. You can replace this value with a number that specifies the maximum number of job slots on each node, regardless of the number of cores. For example, a value of ! on a machine with 16 cores results in 16 job slots, while a value of 2 on a machine with 16 cores results in just 2 job slots.

To specify the total number of jobs slots per node, add a line for each node in the grid. Here is an example:

Begin							
Host							
HOST_NAME	MXJ	r1m	pg	ls	tmp	DISPATCH_WINDOW	#Keywords
default	!	()	()	()	()	()	#Example
D1234	16	()	()	()	()	()	#Example
D1235	16	()	()	()	()	()	#Example
D1236	16	()	()	()	()	()	#Example
D1237	16	()	()	()	()	()	#Example
D1238	16	()	()	()	()	()	#Example
End Host							

Each line designates the concurrent execution of 16 jobs on each node.

- 4. Save and close the file.
- 5. Verify the LSF batch configuration file by entering this command at the command prompt: badmin reconfig
- 6. For details about using this command, see *Platform LSF Reference*.

Using Queues

Understanding Queues

When a job is submitted for processing on the grid, it is placed in a queue and is held until resources are available for the job. LSF processes the jobs in the queues based on parameters in the queue definitions that establish criteria such as which jobs are processed first, what hosts can process a job, and when a job can be processed. All jobs submitted to the same queue share the same scheduling and control policy. By using multiple queues, you can control the workflow of jobs that are processed on the grid.

By default, SAS uses a queue named NORMAL. To use another queue that is already defined in the lsb.queues file, specify the queue using a queue=queue_name option. You can specify this option in the metadata for the SAS logical grid server (in the **Grid Options** field), in the job options macro variable referenced in the GRDSVC_ENABLE statement, or in the **Grid Options** field of a grid options set. For information about specifying a queue in the logical grid server metadata, see "Modifying SAS Logical Grid Server Definitions" on page 17. For information about specifying a queue in a GRDSVC_ENABLE statement, see "GRDSVC_ENABLE Function" on page 101.

Configuring Queues

Queues are defined in the lsb.queues file, which is located in the directory LSF-install-dir\conf\lsbatch\cluster-name\configdir. The file contains an entry for each defined queue. Each entry names and describes the queue and contains parameters that specify the queue's priority and the attributes associated with the queue. For a complete list of parameters allowed in the lsb.queues file, refer to Platform LSF Reference.

Using the Normal Queue

As installed, SAS Grid Manager uses a default queue called NORMAL. If you do not specify the use of a different queue, all jobs are routed to this queue and are processed with the same priority. Other queues enable you to use priorities to control the work on the queues. The queue definition for a normal queue looks like the following:

```
Begin Queue
QUEUE_NAME = normal
PRIORITY = 30
DESCRIPTION = default queue
End Queue
```

Example: A High-Priority Queue

This example shows the existing queue for high priority jobs. Any jobs in the high-priority queue are sent to the grid for execution before jobs in the normal queue. The relative priorities are set by specifying a higher value for the PRIORITY attribute on the high-priority queue.

```
Begin Queue

QUEUE_NAME = normal

PRIORITY = 30

DESCRIPTION = default queue

End Queue

Begin Queue

QUEUE_NAME = priority

PRIORITY = 40

DESCRIPTION = high priority users

End Queue
```

Example: A Night Queue

This example shows the existing queue for processing jobs (such as batch jobs) at night. The queue uses these features:

- The DISPATCH_WINDOW parameter specifies that jobs are sent to the grid for processing only between the hours of 6:00 PM and 7:30 AM.
- The RUN_WINDOW parameter specifies that jobs from this queue can run only between 6:00 PM and 8:00 AM. Any job that has not completed by 8:00 AM is suspended and resumed the next day at 6:00 PM.
- The HOSTS parameter specifies that all hosts on the grid except for host1 can run jobs from this queue. Because the queue uses the same priority as the normal queue, jobs from the high-priority queue are still dispatched first. Excluding host1 from the hosts that are available for the night queue leaves one host always available for processing jobs from other queues:

```
Begin Queue
QUEUE NAME = normal
PRIORITY = 30
DESCRIPTION = default queue
End Queue
Begin Queue
QUEUE_NAME = priority
PRIORITY = 40
DESCRIPTION = high priority users
End Queue
Begin Queue
QUEUE NAME = night
PRIORITY = 30
DISPATCH_WINDOW = (18:00-07:30)
RUN WINDOW = (18:00-08:00)
HOSTS = all \sim host1
DESCRIPTION = night time batch jobs
```

End Oueue

Example: A Queue for Short Jobs

This example shows the existing queue for jobs that need to preempt longer-running jobs. The PREEMPTION parameter specifies which queues can be preempted as well as the queues that take precedence. Adding a value of PREEMPTABLE[short] to the normal queue specifies that jobs from the normal queue can be preempted by jobs from the short queue. Using a value of PREEMPTIVE[normal] to the short queue specifies that jobs from the short queue can preempt jobs from the normal queue. Using a value for PRIORITY on the short queue ensures that the jobs are dispatched before jobs from the normal queue. However, the jobs from the priority queue still take precedence.

```
Begin Queue
QUEUE_NAME = normal
PRIORITY = 30
PREEMPTION = PREEMPTABLE[short]
DESCRIPTION = default queue
End Queue
Begin Queue
QUEUE NAME = priority
PRIORITY = 40
DESCRIPTION = high priority users
End Queue
Begin Queue
QUEUE NAME = short
PRIORITY = 35
PREEMPTION = PREEMPTIVE[normal]
DESCRIPTION = short duration jobs
End Queue
```

Specifying Job Slot Limits on a Queue

A job slot is a position on a grid node that can accept a single unit of work or SAS process. Each host has a specified number of available job slots. By default, each host is configured with a single job slot for each core on the machine, so a multiple-core machine would have multiple job slots. For information about specifying job slots for a host, see *Platform LSF Reference*.

You can also use a queue definition to control the number of job slots on the grid or on an individual host that are used by the jobs from a queue. The QJOB_LIMIT parameter specifies the maximum number of job slots on the grid that can be used by jobs from the queue. The HJOB_LIMIT parameter specifies the maximum number of job slots on any one host that can be used by the queue. The following example sets a limit of 60 job slots across the grid that can be used concurrently by the *normal* queue and a limit of 2 job slots on any host that can be used.

```
Begin Queue
QUEUE_NAME = normal
PRIORITY = 30
DESCRIPTION = default queue
QJOB LIMIT = 60
```

 $HJOB_LIMIT = 2$ End Queue

Working with Mismatches between Queues and Workspace Servers

Defining a queue that specifies fewer hosts than are available for processing can cause an error. For example, you might want to have jobs in a certain queue only be processed by the machine host2, so the queue definition would contain the line **HOSTS** = **host2**. You might also have a grid-launched logical workspace server definition that includes workspace servers for host1, host2, and host3. When the object spawner receives a request to start a workspace server, it then submits a job to Platform LSF to start the workspace server. Because the logical workspace server definition includes more hosts (host1, host2, host3) than the queue (host2), an error message results.

To accommodate this type of environment, add the line **ENABLE HOST INTERSECTION=Y** to the lsb.params file.

Working with Grid Options Sets

Understanding Grid Options Sets

A grid options set is a collection of grid options, SAS options, and required resources. Grid options sets are then mapped to a particular SAS client application and one or more specific metadata identities. The purpose of a grid options set is to enable a SAS grid administrator to define a collection of options in SAS metadata that map to one or more SAS client applications. Those options and are automatically applied to the workload that is submitted to the grid based on the identity of the user accessing the client application. SAS client applications such as the SAS Grid Manager Client Utility have been enhanced to support grid options sets.

For example, consider a scenario where you have many SAS Data Integration Studio users. The users are classified as either "power users" or "ad hoc users." The power users should always submit their jobs to the POWERUSER queue and use the SAS options MEMSIZE=2048M and SORTSIZE=512M. The ad hoc users should always submit their jobs to the DIS queue and use the default SAS invocation options.

To support this scenario, define the workspace servers to be launched using the grid. You could define a grid options set called DISPOWERUSER that contains the grid option QUEUE=POWERUSER and SAS options MEMSIZE=2048M and SORTSIZE=512M. You would then map this grid options set to the SAS Data Integration Studio application and to the metadata identities that you identify as power users. You could then define a second grid options set called DISADHOCUSER that contains only the grid option QUEUE=DIS. You would also map this grid options set to the SAS Data Integration Studio application, but to the SASUSERS group. When a SAS Data Integration Studio user submits a job to the grid, the grid options set mapping identifies which grid options set to use, and applies the proper options for the job. This process is completely transparent to the user.

Merging Option Values

When you use a grid options set, its values are merged with the default option values for the logical grid server. The way the values are merged and evaluated differs according to the type of option:

SAS Options

values in the grid options set are appended to the values from the SAS Options field on the logical grid server's Properties window. Because the options are evaluated from left to right, the value from the grid options set is evaluated last and therefore overrides any similar default SAS option.

For example, you have a logical grid server with a SAS option set to "-memsize 256" and you create a grid options set with a SAS option value of "-memsize 0". When the job is executed on the grid, the SAS command line has the options "-memsize 256 memsize 0" at the end of the command line. The option "-memsize 0" is evaluated last, so that is the value used when processing the job.

Required resources

values in the grid options set are added to the values from the **Required Resources** field on the logical grid server's Properties window. When the job runs on the grid, all specified resources must be available.

For example, you might have a logical grid server with "SASApp" specified in the Required Resources field and a grid options set with a required resource specified as "MySQLDB". When the grid provider selects a host on which to run the job, it must select a host that has both "SASApp" and "MySQLDB" as resources associated with the host.

Grid options


values in the grid options set are appended to the values from the Grid Options field on the logical grid server's Properties window. Because the options are evaluated from left to right, the value from the grid options set is evaluated last and therefore overrides any similar default grid option.

For example, you might have a logical grid server with a **Grid Options** value of "queue=normal" and you create a grid options set with a value of "queue=priority". When the job is passed to the grid provider module, the option string that is passed include the options "queue=normal queue=priority". Because the option "queue=priority" appears after "queue=normal", the priority queue is used for the job.

Creating Grid Options Sets


Grid options sets are created in SAS Management Console as part of a Grid Server definition. You must be a member of the SAS Administrators group in order to create a grid options set. To create a grid options set, follow these steps:

- 1. In the Server Manager of SAS Management Console, select a Grid Logical Server and then the Grid Server component.
- 2. In the Properties window, select the **Options** tab. The Grid Application Mappings table lists any existing mappings.



3. Click New to display the Grid Options Set Mapping Wizard dialog box.

The New, Edit, and Delete buttons are available only if you are a member of the SAS Administrators group.



4. In this dialog box, specify these options:

SAS Application

Specify the SAS application that should be associated with this grid options set. The applications that are listed in this field are ones that have been identified as grid capable either during deployment or by specifying the isGridCapable keyword in the application's properties. If you select an application that launches a workspace server and you have specified that load balanced servers should be launched by the grid, rather than by the spawner, then the options in the grid options set can be used when the workspace server starts. The application name must also be matched with the isGridCapable keyword. See "Specifying That an Application Is Grid Capable" on page 34 for more information.

Grid Options Set

Specifies a named set of grid options, required resources, and SAS options. The grid options set mapping associates this group of options and resources with a SAS application and identities. Click **New** to define a new grid options set.

Identities

Select identities (users or groups) to associate with the grid options set. You must select at least one identity to associate with the mapping. If no identity is selected, the mapping is not saved.

Specifying That an Application Is Grid Capable

The only applications that you can associate with a grid options set are ones that have been identified as being grid capable. Applications are identified as grid capable either by the application's deployment process or by specifying the isGridCapable keyword through the application's property values.

To verify which applications have been identified as grid capable during deployment, you can define a grid options set mapping before you have set the isGridCapable keyword on any applications through the application properties. The applications that are listed as available for mapping are the ones that were identified as grid capable during deployment.

For all other applications that you want to map to a grid options set, you must manually identify each of them as grid capable. In order to apply the isGridCapable keyword to the correct application when running a job, SAS Grid Manager must be able to match the application name as identified on the application folder with the name that is sent by the application when the object spawner starts the workspace server. If they do not match, then you can use wildcards to help match the names. This situation might occur if the application sends a different name from one invocation to the next or if you have multiple versions of the same application that you want to map to the same grid options

These examples illustrate several scenarios:


- If the folder for an application is specified as "SAS Application A" and the application sends the name "SAS Application A", then the names match exactly and you can set the keyword to isGridCapable.
- If the folder for an application is specified as "SAS Application A" and the application sends the name "SAS Application A 4.6" some times and "SAS Application A 4.7" at other times, then you should specify the keyword in the form isGridCapable:SAS Application A*.
- If the folder for an application is specified as "SAS Application A" and the application sends the name "SAS Application A" some times and "Web Infrastructure - SAS Application A" at other times, then you should specify the keyword in the form is Grid Capable: *SAS Application A.
- If the folder for an application is specified as "SAS Application A" and the application sends the name "Web Infrascture - SAS Application A" some times and "SAS Application A 4.6" at other times, then you should specify the keyword in the form isGridCapable:*SAS Application A*.

For example, to make SAS Studio a grid-enabled application, you might specify the keyword as isGridCapable:*SAS Studio Mid-Tier*.

- The isGridCapable portion of the keyword enables SAS Studio Mid-Tier to be included in the list of grid-enabled applications.
- The *SAS Studio Mid-Tier* portion of the keyword enables the IOM application name as sent by SAS Studio to be matched to the SAS Studio Mid-Tier application folder so that grid options sets can be applied. The wildcards enable SAS Grid Manager to recognize the IOM name (Web Infra Platform Services 9.4 - SAS Studio Mid-Tier 3.1) and match it with the SAS Studio Mid-Tier options sets.

To set the isGridCapable keyword for an application, follow these steps:

- 1. In SAS Management Console, select the **Folders** tab.
- 2. Open the **System** \Rightarrow **Applications** folder.
- 3. Select the folder for the application whose property you want to change. Then, select File ⇒ Properties.
- 4. In the Properties window, click **Add** next to the **Keyword** area.
- 5. In the Add Keyword dialog box, type isGridCapable or isGridCapable:<application name> with wildcards as needed in the Name field.



6. Click **OK** to close the Add Keyword dialog box and then the Properties window.

After applications are identified as being grid capable and grid options sets are mapped to those applications, the options in the grid options set are used to start any grid-launched servers. See "Grid-Launched Servers" on page 60 for more information.

Defining and Specifying Resources

Overview

Defining resources enables you to specify where jobs are run on the grid. You can define resource names on grid nodes, and then specify those same resource names on jobs that are sent to the grid. The resource names that are specified on grid machines indicate a specific program or resource that the grid job might need (for example, a machine that has SAS/STAT installed on it or a machine that has access to a Teradata machine), so you can direct specific types of work to the nodes that are most appropriate for processing them.

By default, when a job is sent to the grid, the name of the SAS Application Server is sent as a resource name along with the job. You can further specify the type of machine used to run a job by specifying the WORKLOAD= parameter on the GRDSVC_ENABLE call.

For example, assume that you have installed and configured a grid that uses the application server name of SASApp. You now want to specify that SAS Data Integration Studio jobs should run on certain machines in the grid. To make this happen, follow these steps:

- 1. Create a resource name of DI for SAS Data Integration Studio jobs. (DI is only an example; you can use any user-defined string.)
- Assign the resource names DI and SASApp to the machines that you want to use for processing SAS Data Integration Studio jobs.
- 3. Add the value DI to the **Required Resources** field for a grid options set definition that also specifies SAS Data Integration Studio in the **SAS Application** field.
- 4. When you send a job to the grid using SAS Data Integration Studio, the job is automatically sent to the DI workload, which sends the job to one of the machines

with SASApp as a resource name and DI as a resource name. If there are no grid servers with resource names that match the value on the job, the job is not processed.

If you did not use a grid options set, you would have to manually choose the workload named DI in the Loop Properties window in SAS Data Integration Studio.

Defining Resource Names Using Addresource

SAS Grid Manager provides the addresource command to define hosts and resources. To use this command to specify resource names, follow these steps:

- 1. Log on to the grid control machine as the LSF administrator.
- 2. If you are on UNIX, source the LSF profile file and verify that the PATH is correct.
- 3. Issue the command addresource -r <resource_name> -m <machine name>. If the machine name contains spaces, you must change the spaces to underscores.
 - For example, the command addresource -r DI -m D1234 assigns the resource name DI to the machine D1234.
- 4. Run the LSF commands to reconfigure the grid to recognize the new resources.

Specifying Resource Names Using GRDSVC ENABLE

You can use the GRDSVC ENABLE function to specify resource names for jobs that run on the grid. Use the SERVER= option to specify a resource to use if the specified grid server has specified a required resource. For more information, see "GRDSVC ENABLE Function" on page 101.

Specifying Resource Names Using the SAS Grid Manager Client **Utility**

If you specify required resources in the metadata definition for a SAS Application Server, you can use the SAS Grid Manager Client Utility to specify that those resources are used. Specify the -GRIDAPPSERVER option to specify the SAS Application server to use. For more information, see "SASGSUB Syntax: Submitting a SAS Program in Batch Mode" on page 116.

Specifying Resource Names in SAS Data Integration Studio

In order to specify the resource name for SAS Data Integration Studio jobs, you must complete these tasks:

- Add the resource name as an allowed value for the logical grid server to which you send jobs.
- Specify the workload that corresponds to the resource name in the loop transformation properties.

To add the resource name to the logical grid server metadata's Workload values, see "Modifying SAS Logical Grid Server Definitions" on page 17.

To specify the workload value in SAS Data Integration Studio, follow these steps:

- 1. On the SAS Data Integration Studio menu bar, select **Tools** ⇒ **Options**, and then select the **SAS Server** tab on the Options dialog box.
- 2. Select the SAS grid server in the Server field.
- 3. Select the workload to use for the submitted jobs in the **Grid workload** specification field.

You can also specify the resource name through a grid options set, either on GRDSVC_ENABLE or by using the GRIDOPTSET parameter on the SAS Grid Manager Client Utility.

Chapter 4

Enabling SAS Applications to Run on a Grid

Overview of Grid Enabling	4(
Submitting SAS Programs to a Grid Interactively Overview Submitting Jobs from the Program Editor to the Grid Viewing LOG and OUTPUT Lines from Grid Jobs Using the SAS Explorer Window to Browse Libraries Running Interactive SAS Sessions Using the SAS Grid Manager Client Utility Running Interactive Commands Using the SAS Grid Manager Client Utility	. 40 . 41 . 42 . 42
Submitting Batch SAS Jobs to the Grid Overview Grid Manager Client Utility File Handling Submitting Jobs in Batch Using the SAS Grid Manager Client Utility Running Commands in Batch Using the SAS Grid Manager Client Utility Viewing Job Status Using the SAS Grid Manager Client Utility Ending Jobs Using the SAS Grid Manager Client Utility Retrieving Job Output Using the SAS Grid Manager Client Utility Retrieving a SAS Grid Manager Client Utility Log Monitoring Batch Processing Using the SAS Grid Manager Client Utility Using a Grid without a Shared Directory	43 43 44 44 45 45 46 46
Scheduling Jobs on a Grid	
Comparing Grid Submission Methods	. 48
Enabling Distributed Parallel Execution of SAS Jobs	48
Using SAS Studio with a SAS Grid	. 49
Using SAS Enterprise Guide and SAS Add-In for Microsoft Office with a SAS Grid Types of Grid Enablement Parallel Execution and Grid Enablement Using Extended Attributes to Specify Grid Usage Assigning Libraries in a Grid Developing SAS Programs Interactively Using a Grid	50 51 . 52 . 52
Using SAS Stored Processes with a SAS Grid	53
Using SAS Data Integration Studio with a SAS Grid Scheduling SAS Data Integration Studio Jobs on a Grid Multi-User Workload Balancing with SAS Data Integration Studio Parallel Workload Balancing with SAS Data Integration Studio Updating SAS Grid Server Definitions for Partitioning Specifying Workload for the Loop Transformation	. 54 . 54 . 55

Using SAS Enterprise Miner with a SAS Grid	57
Using SAS Risk Dimensions with a SAS Grid	5 9
Using SAS Grid Manager for Server Load Balancing	59
Overview	. 59
Load Balancing Methods	60
Converting Servers to Use Grid Load Balancing	61

Overview of Grid Enabling

After you have configured your grid, you can configure your SAS applications and programs to take advantage of the grid capabilities. Some SAS applications require you to change only an option to take advantage of the grid; other applications require more extensive changes.

Submitting SAS Programs to a Grid Interactively

Overview

You can use SAS Display Manager as a client to submit SAS programs to the grid for execution. The results of the execution are returned to the local workstation. When you submit a SAS program from a SAS Display Manager client to execute on a grid, the program runs on a grid machine in a separate session with its own unique work library. The SAS log and output of the grid execution are returned to the local workstation. You might need to perform additional actions in order to view data from the SAS Display Manager session that was created or modified by the program that ran on the grid. For example, modifications might be required in order to use the Explorer to browse SAS libraries that are modified by grid execution.

Starting with the first maintenance release after SAS 9.4, you can also use the SAS Grid Manager Client Utility to start an interactive session on the grid or watch the output from a batch session. An interactive session enables you to perform functions in interactive mode or batch monitor mode:

Interactive mode

- Run SAS in line mode.
- Run SAS in Display Manager mode.
- Run and interact with a command (watch the output and provide input).

Batch monitor mode

- Run SAS in batch mode and watch the output of the session.
- Run a command in batch mode and watch the output.

Using SAS line mode or SAS Display Manager mode requires that the grid nodes are UNIX machines. Also, SAS Display Manager mode requires that you have X Server on the client machine.

If you terminate the SAS Grid Manager Client Utility session while performing any interactive mode function, the remote job is also terminated. Terminating the session while running a batch monitor mode function does not terminate the batch job.

Submitting Jobs from the Program Editor to the Grid

The first step in integrating SAS processes with the grid is to get your SAS programs running on the grid.

In order to submit a SAS program to the grid, you must add a set of grid statements to the program. For programs submitted through the SAS Program Editor, you can save the statements to an external file and then specify a key definition that issues the statements. Submit the contents of the SAS Program Editor window to the grid, rather than to the local workstation.

Some of the examples in this topic use SAS/CONNECT statements (such as signon, rsubmit, and signoff). For detailed information about these statements, see SAS/CONNECT User's Guide.

Note: This procedure does not work if the Explorer window is open in your SAS session.

To add grid statements to a program and submit the program to the grid, follow these steps:

1. Save these statements to an external file, referred to as *grid-statement-file* (for example, c:\gpre.sas):

```
%global count;
%macro gencount;
%if %bquote(&count) eq %then %do; %let count=1;%end;%else %let
count=%eval(&count+1);
%mend;
%gencount;
options
metaserver='metadata-server-address';
options metaport=metadata-server-port;
options metauser=username;
options metapass="password";
%let rc=%sysfunc(grdsvc enable(grid&count, server=SASApp));
signon grid&count;
```

metadata-server-address is the machine name of the SAS Metadata Server, and metadata-server-port is the port used to communicate with the metadata server.

2. Open the Keys window and specify the following for an available key (for example, F12):

```
gsubmit "%include
'grid-statement file';";
rsubmit grid&count wait=no persist=no;
```

grid-statement-file is the path and filename of the file (for example, c:\gpre.sas) containing the grid statements.

3. Type or include a SAS program in the Program Editor window, and then press the key assigned to the grid statements. The program is automatically submitted to the grid for processing. Your local machine is busy only until the program is submitted to the grid.

Using the same key to submit multiple jobs causes multiple jobs to be executed in parallel on the grid. Anything specified in the WORK library is discarded when the grid session ends and is not available to later steps in the code.

Viewing LOG and OUTPUT Lines from Grid Jobs

The example in "Submitting Jobs from the Program Editor to the Grid" on page 41 uses asynchronous rsubmits. This causes the results of the execution to be returned to the local log and output windows only after the entire program finishes execution on the grid. To cause the log and output lines to be displayed while the program is executing, delete the options noconnectwait; line in the program.

The rsubmit executes synchronously, and the returned log and output lines are displayed while the job is executing. This also results in the Client SAS session being busy until the entire grid job has completed. You cannot submit more code until the job completes.

Using the SAS Explorer Window to Browse Libraries

The Client SAS session and the grid SAS session are two separate instances of SAS. Any code or products needed to access data must be submitted and available on both the client machine as well as the grid nodes. Use the following steps to browse libraries from the SAS Explorer Window that are accessed and modified by jobs executing in the grid:

- 1. Define all of your SAS libraries within SAS metadata under your server context (for example, under SASApp).
- 2. Ensure that the following option is in the SAS invocation in the sasgrid script file used to start SAS on the grid nodes. This option should have been added by the SAS Deployment Wizard.

metaautoresources SASApp

SASApp is the name of your application server context.

3. Include this option on the Client SAS session invocation on the workstation.

metaautoresources SASApp

SASApp is the name of your application server context.

Note: If you are accessing data through any SAS/ACCESS product, you must license the SAS/ACCESS products on the SAS Client machine in order to be able to browse those libraries from the SAS Explorer. The SAS/ACCESS products must also be licensed on the grid nodes in order to enable the job to access data during execution.

Each SAS session executing on the grid is a unique session with a unique WORK library. In order to view the work libraries that are created on each of the grid nodes, you must add the following line after the signon statement in the code provided in "Submitting Jobs from the Program Editor to the Grid" on page 41:

libname workgrid slibref=work server=grid&count;

grid&count is the label used as the remote session ID in the signon statement.

Running Interactive SAS Sessions Using the SAS Grid Manager Client Utility

To start an interactive SAS session on a UNIX grid using the SAS Grid Manager Client Utility and SAS Display Manager, issue the following command from an operating system command line:

<path/>SASGSUB -GRIDRUNSASDMS <hostName>:display number<.screen number>

To start an interactive SAS session in line mode on a UNIX grid using the SAS Grid Manager Client Utility, issue the following command from an operating system command line:

<path/>SASGSUB -GRIDRUNSASLM

The path option specifies the path for the SASGSUB program. By default, the location is <configuration directory>/Applications/SASGridManagerClientUtility/<version>.

The -GRIDRUNSASDMS or -GRIDRUNSASLM option starts the interactive SAS session on the grid. Once the session has started, you can submit SAS code or programs that will run on the machine in the grid. There are other arguments, some required and some optional, that you can include in the SASGSUB statement. These arguments are passed to the grid when the SAS session is started and include parameters such as the metadata connection information, grid application server name, and workload resource names. See "SASGSUB Syntax: Starting SAS in Interactive Mode" on page 117 for complete syntax information.

Running Interactive Commands Using the SAS Grid Manager Client **Utility**

To interactively run a command on a grid using the SAS Grid Manager Client Utility, issue the following command from a SAS command line:

<path/>SASGSUB -GRIDRUNCMDINT command

Standard input, standard output, and standard error are directed to your command prompt window.

Submitting Batch SAS Jobs to the Grid

Overview

The SAS Grid Manager Client Utility enables you to run SAS jobs on the grid in batch. You can also use the utility to check job status, end a job, and retrieve job output. Most of the options that are used by the SAS Grid Manager Client Utility are contained in the sasgsub.cfg file. This file is automatically created by the SAS Deployment Wizard. These options specify the information that the SAS Grid Manager Client Utility uses every time it runs.

The SAS Grid Manager Client Utility and Platform LSF must be installed on any machine on which the SAS Grid Manager Client Utility runs.

Grid Manager Client Utility File Handling

This is how files are handled by the SAS Grid Manager Client Utility when processing a job on the grid in batch mode:

1. SASGSUB creates a job directory in the GRIDWORK directory under the directory of the user who is submitting the job. For example, if GRIDWORK is /grid/ share and the submitting user is sasuser1, then a job directory is created in / grid/share/sasuser1 for the files.

- 2. SASGSUB copies the SAS program and any files specified by GRIDFILESIN into the new directory.
- 3. SASGSUB submits a job to the grid that includes information about the location of the job directory. It uses either GRIDWORK or GRIDWORKREM to specify the location of the job information to the grid. If you are staging files, SASGSUB also passes the stage file command specified by the GRIDSTAGECMD option to the grid.
- 4. If the grid job is using staging when the job starts, the grid copies the files in the job directory under GRIDWORK to a temporary job directory. The temporary directory is in the grid's shared directory location that is specified during the SAS Deployment Wizard installation process.
- 5. The grid runs the SAS program from the job directory and places the LOG and LST file back into the same job directory. For a shared file system, this directory is the one specified by the GRIDWORK option. This is also the directory that SASGSUB copied files into. If you are staging files, this directory is the job directory that is in the grid shared directory.
- 6. If you are staging files, after the job is complete, the files in the job directory in the grid shared location are copied to the job directory that is specified by the GRIDWORK option.
- At this point in processing, the job directory in GRIDWORK contains all of the files that are required and produced by SAS batch processing. You can then retrieve the files using the GRIDGETRESULTS command.

Submitting Jobs in Batch Using the SAS Grid Manager Client Utility

To submit a SAS job in batch mode to a grid using the SAS Grid Manager Client Utility, issue the following command from an operating system command line:

<path/>SASGSUB -GRIDSUBMITPGM sas-program-file

The *path* option specifies the path for the SASGSUB program. By default, the location is *<configuration_directory>*/Applications/SASGridManagerClientUtility/*<version>*.

The -GRIDSUBMITPGM option specifies the name and path of the SAS program that you want to submit to the grid.

In addition, you can specify other options that are passed to the grid or used when processing the job, including workload resource names. For a complete list of options, see "SASGSUB Syntax: Submitting a SAS Program in Batch Mode" on page 116.

Specifying the -GRIDWATCHOUTPUT argument displays the standard output and standard error of the submitted batch job on your machine.

Running Commands in Batch Using the SAS Grid Manager Client Utility

To submit a command to a grid in batch mode using the SAS Grid Manager Client Utility, issue the following command from an operating system command line:

<path/>SASGSUB -GRIDRUNCMDcommand

Viewing Job Status Using the SAS Grid Manager Client Utility

After you submit a job to the grid, you might want to check the status of the job. To check the status of a job, issue the following command from a command line:

```
<path/>SASGSUB -GRIDGETSTATUS [job-ID | ALL]
```

-GRIDGETSTATUS specifies the ID of the job that you want to check, or ALL to check the status of all jobs submitted by your user ID. For a complete list of options, see "SASGSUB Syntax: Viewing Job Status" on page 120.

The following is an example of the output produced by the SASGSUB -GRIDGETSTATUS command.

Output 4.1 Output Produced by SASGSUB -GRIDGETSTATUS Command

```
Current Job Information
 Job 1917 (testPgm) is Finished: Submitted: 08Dec2008:10:28:57, Started: 08Dec2008:10:28:57 on
Host host1, Ended: 08Dec2008:10:28:57
 Job 1918 (testPgm) is Finished: Submitted: 08Dec2008:10:28:57, Started: 08Dec2008:10:28:57 on
Host host1, Ended: 08Dec2008:10:28:57
 Job 1919 (testPgm) is Finished: Submitted: 08Dec2008:10:28:57, Started: 08Dec2008:10:28:57 on
Host host1, Ended: 08Dec2008:10:28:57
 Job information in directory U:\pp\GridSub\GridWork\user1\SASGSUB-2008-11-24 13.17.17.327 testPgm
is invalid.
  Job 1925 (testPgm) is Submitted: Submitted: 08Dec2008:10:28:57
```

Ending Jobs Using the SAS Grid Manager Client Utility

If a job that has been submitted to the grid is causing problems or otherwise needs to be terminated, use the SAS Grid Manager Client Utility to end the job. Issue the following command from a command line:

```
<path/>SASGSUB -GRIDKILLJOB [job-ID | ALL]
```

-GRIDKILLJOB specifies the ID of the job that you want to end, or ALL to end all jobs submitted by your user ID. For a complete list of options, see "SASGSUB Syntax: Ending a Job" on page 120.

Retrieving Job Output Using the SAS Grid Manager Client Utility

After a submitted job is complete, use the SAS Grid Manager Client Utility to retrieve the output produced by the job. Issue the following command from a command line:

```
<path/>SASGSUB -GRIDGETRESULTS [job-ID | ALL] -GRIDGETRESULTSDIR
```

-GRIDGETRESULTS specifies the ID of the job whose results you want to retrieve, or you can specify ALL to retrieve the results from all jobs submitted by your user ID.

-GRIDRESULTSDIR specifies the directory in which the jobs results should be moved. When the results are retrieved, they are removed from the GRIDWORK directory, which keeps this directory from filling up with completed jobs. If you do not specify this parameter, the results are copied to a job subdirectory in the current directory.

A file named job.info is created along with the job output. This file contains information about the execution of the job, including the submit time, start time, end time, the machine on which the job ran, the job ID, and the return code from the SAS program.

The following is an example of the output produced by the SASGSUB -GRIDGETRESULTS command.

Output 4.2 Output Produced by SASGSUB -GRIDGETRESULTS Command

```
Current Job Information
  Job 1917 (testPgm) is Finished: Submitted: 08Dec2008:10:53:33, Started: 08Dec2008:10:53:33 on
Host host1, Ended: 08Dec2008:10:53:33
   Moved job information to .\SASGSUB-2008-11-21 21.52.57.130 testPgm
  Job 1918 (testPgm) is Finished: Submitted: 08Dec2008:10:53:33, Started: 08Dec2008:10:53:33 on
Host host1, Ended: 08Dec2008:10:53:33
   Moved job information to .\SASGSUB-2008-11-24 13.13.39.167 testPgm
  Job 1919 (testPgm) is Finished: Submitted: 08Dec2008:10:53:34, Started: 08Dec2008:10:53:34 on
Host host1, Ended: 08Dec2008:10:53:34
   Moved job information to .\SASGSUB-2008-11-24_13.16.06.060_testPgm
  Job 1925 (testPgm) is Submitted: Submitted: 08Dec2008:10:53:34
```

Retrieving a SAS Grid Manager Client Utility Log

After a submitted job is complete, you can find the SAS program log file for the job in this location: GRIDWORK/user id/SASGSUB-YYYY-MM-DD HH:MM SS mmm job name/program name.log

The SAS Grid Manager Client Utility uses the standard SAS logging facility. Output from the SAS Grid Manager Client Utility is directed to the console unless you use the SAS logging facility to create a log. See the -LOGCONFIGLOC option in "SASGSUB Syntax: Submitting a SAS Program in Batch Mode" on page 116 for a list of the supported logging keys.

Monitoring Batch Processing Using the SAS Grid Manager Client Utility

When you use SASGSUB to submit a program or a command to the grid in batch mode, you can use the -GRIDWATCHOUTPUT argument to interactively monitor the processing on the grid. The option specifies that the output of what was submitted by the SASGSUB command is displayed on your machine. If you use this argument when submitting a SAS program using -GRIDSUBMITPGM, the SAS log and output are displayed. If you use the argument when submitting a command using -GRIDRUNCMD, the command's standard output and standard error are displayed. While the output is being displayed, entering the command prompt does not affect the processing in the grid.

If you terminate the SASGSUB session while in interactive monitoring mode, the batch job continues to run and does not terminate.

Using a Grid without a Shared Directory

If your grid configuration does not permit a directory structure to be shared between the grid client machines and the grid nodes, you can specify that the grid job move files into the grid before processing and move files out of the grid when the job is complete. The file movement (called file staging) is performed by the grid job using a remote copy program such as rcp, scp, or lsrcp. When using file staging, files are moved into and out of the grid using the GRIDWORK directory. The SAS Grid Manager Client Utility

passes information to the grid that indicates which files need to be sent to the grid and where the files are located. After the grid processes the job, the results are copied back to the GRIDWORK directory. If the user is offline, the results are held in the shared file system until they are retrieved.

During the installation process, the SAS Deployment Wizard enables you to specify whether you will use a shared directory or if you will be staging files. If you specify that you will be staging files, you must also specify the staging command that you want to use to move the files (rcp, lsrcp, scp, pscp, or smbclient). You can also specify the host that you will use to stage files to and from the grid, if you are not using the current host.

To submit jobs to a grid without a shared file system, follow these steps:

- 1. Use the GRIDSTAGECMD parameter on the SASGSUB command to specify the transfer method to use for moving the files from the staging directory to the grid.
- 2. If the machine that stages the files is not the current host, use the GRIDSTAGEHOST parameter on the SASGSUB command to specify the host that is used to stage the files. For example, use this parameter if you are using a laptop to submit jobs to the grid and then disconnecting or shutting down the laptop before the jobs are completed or submitted. The laptop must have a GRIDWORK directory on a file server that is always available to the grid. Use the GRIDSTAGEHOST command to specify the file server host name.

Scheduling Jobs on a Grid

Using the scheduling capabilities, you can specify that jobs are submitted to the grid when a certain time has been reached or after a specified file or job event has occurred (such as a specified file being created).

To schedule a job to run on a grid, follow these steps:

- 1. Deploy the job for scheduling.
 - Some SAS applications, such as SAS Data Integration Studio, include an option to deploy jobs for scheduling. If you want to schedule an existing SAS job, use the Deploy SAS DATA Step Program option in the Schedule Manager plug-in of SAS Management Console.
- 2. Use the Schedule Manager plug-in in SAS Management Console to add the job to a
 - A flow contains one or more deployed jobs as well as the schedule information and time, file, or job events that determine when the job runs.
- 3. Assign the flow to a scheduling server and submit the flow for scheduling.
 - You must assign the flow to a Platform Process Manager scheduling server in order for the scheduled job to run on the grid.

For detailed information about scheduling, see *Scheduling in SAS*.

Comparing Grid Submission Methods

You can use the SAS Grid Manager Client Utility, the Schedule Manager plug-in to SAS Management Console, and SAS language statements to submit jobs to the grid. The following table compares the methods.

Table 4.1 Comparison of Grid Submission Methods

Feature	SAS Grid Manager Client Utility	Schedule Manager Plug-in	SAS Language Statements
Interface	Command line	SAS Management Console interface	SAS language syntax
Duration of client connection	Duration of the submission	Duration of the submission	Duration of the execution
Minimum client installation requirements	SAS Grid Manager Client Utility and Platform LSF	SAS Management Console	Base SAS, SAS/CONNECT, Platform LSF
Support for checkpoint restart	Yes	Yes	No
Support for SAS options, grid options, and policies	Yes	Yes	Yes
Support for event-triggered workflow execution	No	Yes	No

Enabling Distributed Parallel Execution of SAS Jobs

Some SAS programs contain multiple independent subtasks that can be distributed across the grid and executed in parallel. This approach enables the application to run faster. To enable a SAS program to use distributed parallel processing, add RSUBMIT and ENDRSUBMIT statements around each subtask and add the GRDSVC_ENABLE function call. SAS Grid Manager automatically assigns each identified subtask to a grid node.

You can use the SAS Code Analyzer to automatically create a grid-enabled SAS job. To use the SAS Code Analyzer, add PROC SCAPROC statements to your SAS program, specifying the GRID parameter. When you run the program with the PROC SCAPROC statements, the grid-enabled job is saved to a file. You can then run the saved SAS job on the grid, and SAS Grid Manager automatically assigns the identified subtasks to a grid node.

This is an example of the syntax for the SAS Code Analyzer:

```
proc scaproc;
    record '1.txt' grid '1.grid':
run:
remainder of SAS program...
```

For complete information and syntax for the PROC SCAPROC statement, see Base SAS Procedures Guide.

This is an example of the syntax used for enabling distributed parallel processing:

```
% let rc=%sysfunc(grdsvc_enable(_all_,server=SASApp));
options autosignon;
rsubmit task1 wait=no;
    /* code for parallel task #1 */
endrsubmit;
rsubmit task2 wait=no;
    /* code for parallel task #2 */
endrsubmit;
. . .
rsubmit taskn wait=no;
     /* code for parallel task #n */
endrsubmit;
waitfor _all_ task1 task2 . . . taskn;
signoff all;
```

For more information, see "GRDSVC ENABLE Function" on page 101.

For detailed syntax information, see SAS/CONNECT User's Guide.

Using SAS Studio with a SAS Grid

SAS Studio can take advantage of the processing capabilities of a SAS Grid. The approach to take to add grid support depends on the edition of SAS Studio that you are using.

With all editions of SAS Studio, you can use the SAS/CONNECT GRDSVC_ENABLE, SIGNON, and RSUBMIT functions in your code to send the code to the grid. Use the GRDSVC ENABLE function to identify the SAS/CONNECT session that should be sent to the grid, specify that session name in the SIGNON statement, and then submit the code to the session in the RSUBMIT statement.

For example, you could use the following code to specify processing on the grid:

```
%let rc=%sysfunc(grdsvc enable(gridsess,server=SASApp));
options autosignon;
rsubmit gridsess wait=no;
    /* code to be processed on the grid */
endrsubmit;
waitfor gridsess;
signoff gridsess;
```

See Chapter 8, "SAS Functions for SAS Grid," on page 101 and the SAS/CONNECT 9.4 User's Guide for syntax information.

If you are using SAS Studio Enterprise Edition together with SAS Grid Manager, you can convert the SAS Studio workspace server to use grid load balancing. During the conversion process, you can choose to launch the workspace server either by the grid or by the object spawner on the least-used machine in the grid. After you convert the workspace server, the grid load-balanced server processes the SAS statements in SAS Studio. See "Using SAS Grid Manager for Server Load Balancing" on page 59 for more information.

In order to run code from any edition of SAS Studio on the grid, you must have SAS Grid Manager licensed and Platform Computing's LSF installed on the same machine as the SAS Studio workspace server.

You should modify the SAS Studio property metadata to specify that the application is grid capable. Identifying SAS Studio as grid capable enables you to associate grid options sets with the application. Grid options sets are collections of grid options, SAS options, and required resources that you can map to users and applications (in this case, SAS Studio). For more information, see "Understanding Grid Options Sets" on page 31.

To specify that SAS Studio is grid capable, use SAS Management Console to add the keyword <code>isGridCapable:*SAS</code> Studio Mid-Tier* to the metadata for the SAS Studio folder. See "Specifying That an Application Is Grid Capable" on page 34 for complete instructions.

Using SAS Enterprise Guide and SAS Add-In for Microsoft Office with a SAS Grid

Types of Grid Enablement

Jobs generated by SAS Enterprise Guide and SAS Add-In for Microsoft Office can take advantage of a SAS grid using one or a combination of these approaches:

- Using server-side load balancing through a grid-launched workspace server. When
 SAS Enterprise Guide or SAS Add-In for Microsoft Office request the use of a
 workspace server to run a job, the object spawner launches a new workspace server
 in the grid on a node that meets the criteria of the queue to which the job was
 submitted. The job then runs on the workspace server. See "Using SAS Grid Manager
 for Server Load Balancing" on page 59 for more information about specifying grid
 load balancing on a workspace server.
- Using server-side load balancing through a grid load-balanced workspace server. When SAS Enterprise Guide or SAS Add-In for Microsoft Office request the use of a workspace server to run a job, the object spawner uses SAS Grid Manager to automatically launch the server on the least busy node in the grid. The code from SAS Enterprise Guide or SAS Add-In for Microsoft Office is then run on the workspace server. See "Using SAS Grid Manager for Server Load Balancing" on page 59 for more information about specifying grid load balancing on a workspace server.
- Using SAS Enterprise Guide or SAS Add-In for Microsoft Office's ability to enable
 projects or tasks to run on the grid. If you are using SAS Enterprise Guide or SAS
 Add-In for Microsoft Office 5.1 or later, the code for the project or the task is
 wrapped in RSUBMIT/ENDRSUBMIT statements and automatically sent to the
 SAS grid for processing. To specify this type of processing, perform one of the
 following actions:
 - Specify Use grid if available in the Project Properties window or the Task Properties window.

- Specify the Initialize Grid (if available) option when connecting to a workspace in the Options dialog box under SAS Programs.
- Set the EGGridPolicy or the AMOGridPolicy extended attribute on the logical grid server to a value of Force. See "Using Extended Attributes to Specify Grid Usage" on page 52 for more information about these attributes.n0clcosbyh7s72n12g7vvnxyztv2

Note: These options are not needed if you use grid-launched workspace servers.

If you are using grid-launched workspace servers and do not want the Use grid if available option to be available, set the EGGridPolicy or the AMOGridPolicy to a value of *Ignore*. The *Ignore* value is available in the first maintenance release after version 6.1 of SAS Enterprise Guide and SAS Add-In for Microsoft Office.

Using SAS Enterprise Guide or SAS Add-In for Microsoft Office's ability to insert custom code before and after tasks and SAS programs to route the processing to the grid. If you are using SAS Enterprise Guide 4.3 or earlier, you can wrap the code for the project or the task in RSUBMIT/ENDRSUBMIT statements through the use of custom code options that are inserted before and after the code that is submitted with the program. You must also modify the application servers, the SAS Enterprise Guide configuration files, and the SAS Add-In for Microsoft Office options. Download the code and instructions from http://support.sas.com/rnd/ scalability/grid/download.html.

Note: This option is not needed if you use grid-launched workspace servers.

If you use grid-launched workspace servers, you should not specify any of the other grid-related options. If you are using the first maintenance release of version 6.1 of SAS Enterprise Guide or SAS Add-In for Microsoft Office, you can prevent users from using the grid options by specifying a value of *Ignore* for the EGGridPolicy or the AMOGridPolicy extended attribute on the logical grid server. See "Using Extended Attributes to Specify Grid Usage" on page 52 for more information about these attributes.

If you are not using grid-launched workspace servers, you must specify grid load balancing options, and you might have to wrap your code in RSUBMIT/ENDRSUBMIT statements. The statements are required if you are using SAS Enterprise Guide or SAS Add-In for Microsoft Office 4.3 or earlier. If you are using SAS Enterprise Guide or SAS Add-In for Microsoft Office 5.1 or later, the statements are not required.

Parallel Execution and Grid Enablement

The option Allow parallel execution on the same server is not an option to control processing on the grid, but it can affect how grid-enabled jobs are processed. The option causes SAS Enterprise Guide to create a workspace server for each parallel process in a project, regardless of whether the project is grid-enabled or not. The following list explains how this option interacts with the Use grid if available option:

Neither option is selected

All code runs in a single workspace server.

Only Use grid if available option selected

A workspace server starts, performs a grid-enabled SIGNON, and submits code to the grid.

Only Allow parallel execution option selected

Multiple workspace servers are started, one for each parallel code path in a project.

Both options selected

Multiple workspace servers are started. Each server signs on to the grid. Each parallel code path in a project is submitted to the grid.

Selecting both options might cause problems because the GRIDWORK and RMTWORK libraries are duplicated in each workspace server. This causes problems for SAS Enterprise Guide when it tries to read from one of those libraries. Selecting the **Allow parallel execution** option might cause problems because one execution stream might need to use or write to a data set that is in use by another stream.

If you are using grid-launched workspace servers, you do not need to enable the **Use Grid if available** option because the workspace server for SAS Enterprise Guide is already running on the grid. The **Allow parallel execution** option can improve run-time efficiency, but it is more complex because it can run multiple and separate SAS sessions. When possible, perform debug and testing operations with the **Allow parallel execution** option disabled.

Using Extended Attributes to Specify Grid Usage

You can use the EGGridPolicy and AMOGridPolicy attributes on the logical grid server definition to control whether SAS Enterprise Guide or SAS Add-In for Microsoft Office version 5.1 or later uses the grid. These attributes override any other settings in the applications. The following are the possible values for the attributes (values are not case-sensitive):

Noforce

jobs are sent to the grid depending on the setting of the option Use grid if available.

Force

jobs are always sent to the grid, regardless of the value of the option Use grid if available.

Ignore

jobs are never sent to the grid, regardless of the value of the option **Use grid if available**. This value is supported for the first maintenance release after version 6.1 of SAS Enterprise Guide and SAS Add-In for Microsoft Office.

Assigning Libraries in a Grid

In SAS 9.2 and later versions, SAS sessions on the grid use the METAAUTORESOURCES option by default. This option causes SAS libraries that are defined in metadata and identified as "pre-assigned" to automatically be assigned when the SAS session is started. Using pre-assigned libraries with the METAAUTORESOURCES option ensures that the libraries used in the code generated by SAS Enterprise Guide and SAS Add-In for Microsoft Office are available to the SAS sessions on the grid.

However, if your programs use a large number of libraries, you might not want to make all of these libraries pre-assigned. Automatically assigning a large number of libraries could cause performance problems, and not all libraries are likely to be used for all programs. To minimize the performance overhead, define the libraries in SAS metadata but do not identify them as pre-assigned. When you need to refer to the library, you can then use a LIBNAME statement using the META LIBNAME engine.

Developing SAS Programs Interactively Using a Grid

Maintaining a Connection to the Grid

By default, when you start SAS Enterprise Guide or SAS Add-In for Microsoft Office, it connects to a single workspace server and keeps that connection active for the length of the session. If you interactively develop programs in SAS Enterprise Guide or SAS Add-In for Microsoft Office by highlighting and submitting lines of code, the codes use items such as libraries, WORK files, and SAS global statements on the workspace server.

If you are submitting grid-enabled code from SAS Enterprise Guide or SAS Add-In for Microsoft Office in a grid environment, then items such as libraries and SAS global statements must be accessed through the grid rather than through a single workspace server. To maintain access to these items, you must maintain a connection to the grid while you are developing programs interactively. If you are using grid-launched workspace servers, this is not an issue.

Managing Interactive Workload

When SAS Enterprise Guide or SAS Add-In for Microsoft Office is used for interactive program development, the workload is likely to consist of short bursts of work interspersed with varying periods of inactivity while the user considers their next action. The SAS grid configuration can best support this scenario with these configuration settings:

- Increase the number of job slots for each machine. Increasing the number of job slots increases the number of simultaneous SAS sessions on each grid node. Because the jobs that are run on the grid are not I/O or
- Implement CPU utilization thresholds for each machine. If all users submit CPU-intensive work at the same time, SAS Grid Manager can suspend some jobs and resume the suspended jobs when resources are available. This capability prevents resources from being overloaded.

compute intensive like large batch jobs, more jobs can be run on each machine.

The following example shows a sample LSB.HOSTS file that is configured with job slots set to 32 and CPU utilization thresholds set to 80%. The settings needed for a specific site depend on the number of users and the size of the grid nodes.

HOST_NAME	MXJ	ut	r1m	pg	ls	tmp	DISPATCH_WINDOW	#Keywords
#default	!	()	()	()	()	()	()	#Example
host01	32	0.7/0/8	()	()	()	()	()	# host01
host02	32	0.7/0/8	()	()	()	()	()	# host02
host03	32	0.7/0/8	()	()	()	()	()	# host03
host04	32	0.7/0/8	()	()	()	()	()	# host04
host05	32	0.7/0/8	()	()	()	()	()	# host05
End Host								

Using SAS Stored Processes with a SAS Grid

As with SAS Enterprise Guide, SAS stored processes can take advantage of a SAS grid using either one of these approaches or a combination of both:

- Using server-side load balancing through a stored process server. You can convert a stored process server to use load balancing, and then specify grid as the balancing algorithm. When you send jobs from a SAS stored process to this server, the server automatically sends the job to the least busy node in the grid. See "Using SAS Grid Manager for Server Load Balancing" on page 59 for more information about specifying grid load balancing on a stored process server.
- Modifying the stored process code in order to enable the code to run on the grid. You
 must also modify options associated with the stored process. Download the code that
 you must add to the stored process, along with complete information about other
 steps that you must take, from http://support.sas.com/rnd/
 scalability/grid/download.html.

Using SAS Data Integration Studio with a SAS Grid

Scheduling SAS Data Integration Studio Jobs on a Grid

You can schedule jobs from within SAS Data Integration Studio and have those jobs run on the grid. You deploy the job for scheduling in SAS Data Integration Studio, and then use the Schedule Manager plug-in in SAS Management Console to specify the schedule and the scheduling server. For more information, see "Scheduling Jobs on a Grid" on page 47. Also see *Scheduling in SAS*.


Multi-User Workload Balancing with SAS Data Integration Studio

SAS Data Integration Studio enables users to directly submit jobs to a grid or to a workspace server that is launched by the grid. This capability allows the submitted jobs to take advantage of load balancing and job prioritization that you have specified in your grid. SAS Data Integration Studio also enables you to specify the workload that submitted jobs should use. This capability enables users to submit jobs to the correct grid partition for their work.

To submit a job to the grid, select the SAS Grid Server component in the **Server** menu on the Job Editor toolbar. Click **Submit** in the toolbar to submit the job to the grid.

This step is not needed if you use grid-launched workspace servers.


Display 4.1 Submitting a Job to the Grid



To specify a workload value for the server, follow these steps:

- 1. On the SAS Data Integration Studio menu bar, select Tools ⇒ Options, and then select the SAS Server tab on the Options dialog box.
- 2. Select the SAS grid server in the Server field.
- 3. Select the workload to use for the submitted jobs in the **Workload specification** field.

Display 4.2 Selecting the Workload




4. You can also specify the workload in a grid options set and specify the options set name in the **Grid options set specification** field. Only grid options sets that are mapped to SAS Data Integration Studio are listed in this field. For more information, see "Working with Grid Options Sets" on page 31.

SAS Grid Manager uses the workload value to send the submitted job to the appropriate grid partition. For more information about the other steps required, see "Defining and Specifying Resources" on page 36.

Parallel Workload Balancing with SAS Data Integration Studio


A common workflow in applications created by SAS Data Integration Studio is to repeatedly execute the same analysis against different subsets of data. Rather than running the process against each table in sequence, use a SAS grid environment to run the same process in parallel against each source table, with the processes distributed among the grid nodes. For this workflow, the Loop and Loop-End transformation nodes can be used in SAS Data Integration Studio to automatically generate a SAS application that spawns each iteration of the loop to a SAS grid via SAS Grid Manager.

Display 4.3 Loop and Loop-End Transformation Nodes



To specify options for loop processing, open the Loop Properties window and select the **Loop Options** tab. You can specify the workload for the job, and you can specify how many processes can be active at once.

Display 4.4 Loop Properties Dialog Box



For more information, see SAS Data Integration Studio: User's Guide.

Updating SAS Grid Server Definitions for Partitioning

After defining resource names, you can update the grid server metadata so that SAS Data Integration Studio knows the available resource names. To update the definitions, follow these steps:

- 1. In SAS Management Console, open the Server Manager plug-in and locate the logical server definition.
- 2. Expand the logical Grid Server node and select the Grid Server node. Select **Properties** from the pop-up menu or the **File** menu.
- 3. In the Properties window, select the **Options** tab.
- 4. Specify the workload resource name (for example, DI) in the **Workload** field.
- 5. Save and close the definition.
- 6. Repeat this process for all workloads.

Specifying Workload for the Loop Transformation

A SAS Data Integration Studio user performs these steps to specify an LSF resource in the properties for a Loop Transformation in a SAS Data Integration Studio job. When the job is submitted for execution, it is submitted to one or more grid nodes that are associated with the resource.

It is assumed that the default SAS Application Server for SAS Data Integration Studio has a Logical SAS Grid Server component, which was updated in the metadata repository. For more information, see "Defining and Specifying Resources" on page 36.

- 1. In SAS Data Integration Studio, open the job that contains the Loop Transformation to be updated.
- 2. In the Process Designer window, right-click the metadata object for the Loop Transformation and select **Properties**.
- 3. In the Properties window, click the **Loop Options** tab.
- 4. On the Loop Options tab, in the Grid workload specification text box, enter the name of the desired workload, such as DI. The entry is case sensitive.
- 5. Click **OK** to save your changes, and close the Properties window.

Using SAS Enterprise Miner with a SAS Grid

There are three cases where SAS Enterprise Miner uses a SAS grid:

- during model training, for parallel execution of nodes within a model training flow
- during model training, for load balancing of multiple flows from multiple data modelers
- during model scoring, for parallel batch scoring

The workflow for SAS Enterprise Miner during the model training phase consists of executing a series of different models against a common set of data. Model training is CPU-intensive and I/O-intensive. The process flow diagram design of SAS Enterprise Miner lends itself to processing on a SAS grid because each model is independent of the other models. SAS Enterprise Miner generates the SAS program to execute the user-created flow and also automatically inserts the syntax needed to run each model on the grid. Because the models can execute in parallel on the grid, the entire process is accelerated.

In addition, SAS Enterprise Miner is typically used by multiple users who are simultaneously performing model training. Using a SAS grid can provide multi-user load balancing of the flows that are submitted by these users, regardless of whether the flows contain parallel subtasks.

The output from training a model is usually Base SAS code that is known as scoring code. The scoring code is a model, and there are usually many models that need to be scored. You can use SAS Grid Manager to score these models in parallel. This action accelerates the scoring process. You can use any of these methods to perform parallel scoring:

- Use the SAS Grid Manager Client Utility to submit each model independently to the SAS grid.
- Use the Schedule Manager plug-in to create a flow that contains multiple models and schedule the flow to the SAS grid. Because each model is independent, the models are distributed across the grid when the flow runs.
- Use SAS Data Integration Studio to create a flow to loop multiple models, which spawns each model to the grid.


Starting with SAS Enterprise Miner 6.2, you can specify that projects are sent to the grid by default.

In SAS Enterprise Miner 12.3, specify default grid processing by changing the attributes on the logical workspace server. Follow these steps:

- 1. In SAS Management Console, expand the Server Manager plug-in and then expand the SAS Application Server (typically named SASApp).
- 2. Select the Logical Workspace Server and select File ⇒ Properties.
- 3. On the Extended Attributes tab, click New.
- 4. In the Field Name column, enter EM USE GRID IF AVAILABLE.
- 5. In the Value column, enter Y.
- 6. Click **OK** to save the property changes.

In SAS Enterprise Miner 6.2 to 12.1, specify default grid processing by changing a configuration property. To set this property, locate the file app.config. A typical location for this file is C:\SAS\Config\AnalyticsPlatform\apps\EnterpriseMiner\app.config. Locate the property em.enablegrid. To turn on default grid processing, specify a value of Y. If you specify a value of N, you must send projects individually to the grid.

Display 4.5 Grid Processing with SAS Enterprise Miner



Using SAS Risk Dimensions with a SAS Grid

The iterative workflow in SAS Risk Dimensions is similar to that in SAS Data Integration Studio. Both execute the same analysis over different subsets of data. In SAS Risk Dimensions, the data is subsetted based on market states or by instruments. Each iteration of the analysis can be submitted to the grid using SAS Grid Manager to provide load balancing and efficient resource allocation.

Because every implementation is different, an implementation of SAS Risk Dimensions in a grid environment must be customized to your specific business and data requirements.

Using SAS Grid Manager for Server Load Balancing

Overview

SAS servers, such as SAS workspace servers and SAS OLAP servers, are capable of performing load balancing across multiple machines. These servers can be configured to use one of the default algorithms to provide load balancing. However, with SAS Grid Manager installed you can configure workspace servers and other SAS servers to use SAS Grid Manager to provide load balancing. Because SAS Grid Manager accounts for all of the resource consumption on the machine, SAS Grid Manager can make better decisions about which machine is the best candidate for a server session.

SAS Grid Manager can provide load-balancing capabilities for these types of servers:

- workspace servers
- pooled workspace servers
- stored process servers
- · OLAP servers

Any SAS product or solution that uses workspace servers, pooled workspace servers, stored process servers, or OLAP servers would benefit from using SAS Grid Manager to provide load balancing. This includes (but is not limited to) SAS Enterprise Guide, SAS Studio Enterprise Edition, SAS Data Integration Studio, SAS Enterprise Miner, SAS Web Report Studio, and SAS Marketing Automation. However, using the grid to provide load balancing also increases overhead, so your jobs might take longer to run.

You can use two methods to provide workspace server load balancing through SAS Grid Manager. You can have SAS Grid Manager start the workspace servers, or you can have the object spawner start the servers.

Load Balancing Methods

Grid-Launched Servers

With grid-launched workspace servers, the spawner passes the request on to SAS Grid Manager when an application requests a SAS workspace server from the object spawner. SAS Grid Manager submits the job to the grid provider, which determines the best server to run the job based on the policy of the queue. The grid provider uses factors such as CPU utilization, network and disk input and output, disk space, available memory, and queue limits in determining which machine to use.

Because the grid-launched workspace servers are started by SAS Grid Manager, jobs on these servers appear as LSF jobs.

In the first maintenance release after SAS 9.4, pooled workspace servers and stored process servers can also be grid-launched.

An error will result if you use a grid-launched workspace server that specifies more hosts than the queue definition that you are using. For example, using a queue definition that specifies only host2 together with a logical workspace server definition that specifies host1, host2, and host3 causes an error. To accommodate this type of environment, add the line **ENABLE HOST INTERSECTION=Y** to the lsb.params file.

Servers Started by the Object Spawner

When an application or process (for example, SAS Enterprise Guide) requests a SAS server from the object spawner, the spawner determines which hosts can run the new servers. The spawner sends the list of hosts to SAS Grid Manager, which then determines which host is open and is the least busy. The object spawner then directs the client connection to a server on the least busy node on the grid. If there are multiple servers already running on the machine, then the spawner directs the client to the server with the fewest number of connections.

When using the grid load balancing algorithm, jobs are not started by LSF. As a result, jobs that run on the load-balanced servers do not appear as LSF jobs.

For more information, see Chapter 7, "Understanding Server Load Balancing," in SAS Intelligence Platform: Application Server Administration Guide.

SAS OLAP Servers


Because the SAS object spawner is not used to start SAS OLAP servers, the request is not processed through the object spawner if the client requests a SAS OLAP server. However, the same load-sharing logic is used to determine which OLAP server is used for the client connection. As a result, the SAS client connections are spread around to all of the servers in the grid.

Converting Servers to Use Grid Load Balancing

To use SAS Grid Manager for load balancing for a workspace server or an OLAP server, follow these steps:

- 1. In the Server Manager plug-in in SAS Management Console, select the server that will use load balancing.
- 2. Select Convert To ⇒ Load Balancing from the Actions menu or the context menu for the logical server. The Load Balancing Options dialog box appears.

Display 4.6 Server Load Balancing Options Dialog Box



3. Specify the following values:

Balancing algorithm Select Grid.

Launch Servers via Grid

Select this check box to specify that SAS Grid Manager will launch the new servers. Deselect this check box if you want the object spawner to start the servers. This option is not available for OLAP servers.

Select a grid server that was defined during installation and configuration. This field is active only if you did not select Launch Servers via Grid.

Grid server credentials


Select the credentials that the object spawner uses to authenticate to the grid server. This field is active only if you did not select **Launch Servers via Grid**.

4. Click **OK** to save your changes to the server metadata.

To use SAS Grid Manager for load balancing for a stored process server or a pooled workspace server, follow these steps:

- 1. In the Server Manager plug-in in SAS Management Console, select a logical server that will use load balancing.
- 2. Select **Properties** from the **Actions** menu or the context menu. The Properties dialog box appears.
- 3. Select the **Load Balancing** tab.

Display 4.7 Load Balancing Options for a Server



4. Specify the following values:

Balancing algorithm

Select Grid.

Launch Servers via Grid

Select this check box to specify that SAS Grid Manager will launch the new servers. Deselect this check box if you want the object spawner to start the servers.

Grid server

Select a grid server that was defined during installation and configuration. This field is active only if you did not select **Launch Servers via Grid**.

Grid server credentials

Select the credentials that the object spawner uses to authenticate to the grid server. This field is active only if you did not select **Launch Servers via Grid**.

In addition to modifying these server definitions, you must also change server configuration files. For information about the changes that you need to make, see Chapter 7, "Understanding Server Load Balancing," in SAS Intelligence Platform: Application Server Administration Guide.

Chapter 5

High Availability

High Availability and SAS Grid Manager	65
Setting Up High Availability for Critical Applications	66
Restarting Jobs	69
Overview	69
Using SAS Checkpoint and Label Restart	69
Setting Up Automatic Job Requeuing	70

High Availability and SAS Grid Manager

Your organization might have services and long-running SAS programs that are critical to your operations. The services must be available at all times, even if the servers that are running them become unavailable. The SAS programs must complete in a timely manner, even if something happens to cause them to fail. For a SAS program that takes a long time to run, this means that the program cannot be required to restart from the beginning if it ends prematurely.

SAS Grid Manager provides high availability through these capabilities:

- Multi-machine architecture. Because how a SAS grid is configured and operates, there is no single point of failure. Because jobs are processed on the available grid nodes, if a node becomes unavailable other nodes can take over the workload.
- Platform Suite for SAS. The default configuration of Platform Suite for SAS
 provides high availability for the grid operation. The LSF master daemon runs on a
 specified grid node (usually the grid control server), and a failover node is also
 identified. If the master daemon node fails, the failover node automatically takes
 over and broadcasts to the rest of the grid. The grid recognizes the new master
 daemon node and continues operation without interruption. Platform PM and GMS
 must be treated as critical services and configured for failover along with all other
 critical services.
- Critical service failover. There are certain services and processes that are critical to the operation of SAS applications on the grid and that must always be available (for example, the SAS Metadata Server). After providing a failover host for the service, you can use Platform Computing's Enterprise Grid Orchestrator (EGO) to monitor the service, restart the service if it stops, and start the service on the failover host when needed. Once the service has started on the failover host, you can use either hardware (a load balancer) or software (EGO) to automatically direct clients to the failover host. EGO is part of Platform Suite for SAS that is included with the SAS Grid Manager and installed as part of the LSF installation process.

Automatic SAS program failover. If a long-running SAS job fails before completion, rerunning it from the beginning can cause a loss of productivity. You can use the SAS Grid Manager Client Utility to specify that the job is restartable. This means that a failed job restarts from the last successful procedure, DATA step, or labeled section. This capability uses the SAS checkpoint and restart functions to enable failed jobs to complete without causing delays. You can also use attributes on the queue definitions in the grid to automatically restart and requeue any job that ends with a specified return code or that terminates due to host failure. Using these options together ensures that critical SAS programs always run successfully and in a timely manner, even if they encounter problems.

All of these strategies are independent of one another, so you can implement the ones that provide the greatest benefit to your organization.

Setting Up High Availability for Critical Applications

On a grid, there are certain services that always need to be available and accessible to clients. These services are vital to the applications running on the grid and its ability to process SAS jobs. Examples include:

- SAS Metadata Server
- SAS object spawner
- Platform Process Manager
- Platform Grid Management Service
- · web application tier components


Configuring a grid that provides high availability for these services requires these components:

- providing failover hosts for machines that run critical applications. Using multiple machines for critical functions eliminates a single point of failure for the grid.
- providing a way to monitor the high-availability applications on the grid and to automatically restart a failed application on the same host or on a failover host if needed.
- providing a method to let the client know to connect to the failover host instead of the regular host. This can be done through software (DNS resolution) or hardware (the hardware load balancer), but only one is used.

In normal operations, the following sequence takes place:

- 1. The client determines that it needs to access a service on a machine in the grid.
- 2. The client sends a query to the corporate DNS server. The DNS server looks up the address for the machine and returns that information to the client.
- 3. The client uses the address to connect to the machine and use the application.

Figure 5.1 Normal Grid Operations




To provide business continuity for the application, a failover host must be provided for the critical services running in the grid environment. This provides an alternative location for running the critical services and ensures that it remains available to the applications on the grid. In addition, both the main and failover machines must have access to a shared file server. This ensures that the application has access to the data required for operation, regardless of which machine is running the service.

To provide business continuity for the application, the failover capability must also be automatic. EGO is configured to monitor any number of critical services running on the grid. If it detects that the application has failed or that the machine running it has gone down, it is configured to start the application on the failover server automatically, which enables applications to continue running on the grid.

However, once the application has started on the failover server, the client must have a way to know which server is running the application. There are two methods for accomplishing this:


Using a hardware load balancer. The load balancer serves as an intermediary between the client and the services running on the grid, which decouples the grid operation from the physical structure of the grid. When the client wants to connect to the service, it connects to the load balancer, which then directs the request to the machine that is running the service. The load balancer knows the addresses of both the main and failover machines, so it passes the request on to whichever of the machines is running in the servers. During normal operation, the request goes to the main machine. When failover occurs, EGO starts services on the failover host, and the load balancer forwards connections to it (because it is not the host running the services).

Figure 5.2 Grid Failover with a Load Balancer



• DNS resolution. Once EGO starts the application on the failover server, it sends the address of the failover machine to the corporate DNS server. The entry for the application is updated in the server, so the next time a client requests a connection to the application, the DNS server returns the address of the failover machine.

Figure 5.3 Grid Failover with EGO



If you do not want EGO to directly update the corporate DNS, you can configure the DNS server to always point to EGO to provide the IP address for the machine. When EGO starts the application on the failover machine, it then points to the new machine.

The choice of whether to use a load balancer or a DNS solution depends on your organization's policies. Using DNS resolution prevents you from having to purchase an addition piece of hardware (the load balancer). However, your organization's policies might prohibit either the corporate DNS from being changed by an outside DNS (EGO) or DNS requests to be forwarded to an outside DNS. If this is the case, the hardware load balancer provides a high-availability solution.

Restarting Jobs

Overview

An essential component of a highly available grid is the ability to handle SAS jobs that fail or have to be restarted for some reason. If a long-running job fails, it can cause a significant loss of productivity. After the failure is noticed, you must manually resubmit the job and wait while the program starts over again from the beginning. For SAS programs that run for a considerable amount of time, this can cause unacceptable delays.

The SAS Grid Manager Client Utility, combined with LSF queue policies and the SAS checkpoint restart feature, provides support for these solutions to this problem:

- the capability to restart a job from the last successful job step
- the ability to set up a special queue to automatically send failed jobs to another host in the grid to continue execution

Using SAS Checkpoint and Label Restart

The SAS Grid Manager Client Utility includes options that enable you to restart SAS programs from the last successful PROC or DATA step. When the program runs, it records information about the SAS procedures and DATA steps or labels in the program and tracks the ones that have been passed during execution.

If the program fails and has to be restarted, SAS first executes global statements and macros. Then, it reads the checkpoint or label library to determine which checkpoints or labels have been passed. When SAS determines where the program stopped, execution is resumed from that point. Program steps that have already successfully completed are not re-executed.

The restart capability is available on the grid only if you are using the SAS Grid Manager Client Utility or scheduling grid jobs. It is not available if you are using other application interfaces to submit work to the grid.

If you use the restart options, your SAS WORK library must be on shared storage. Using this capability adds some overhead to your SAS program, so it is not recommended for every SAS program that you run.

To set up the checkpoint or label restart capability, use the SAS Grid Manager Client Utility to submit the SAS program to the grid. Specify either the GRIDRESTARTOK argument (for checkpoints) or the GRIDLRESTARTOK argument (for labels). You cannot specify both arguments.

When you use the GRIDRESTARTOK argument, these options are automatically added to your SAS program:

STEPCHKPT

enables checkpoint mode and causes SAS to record checkpoint-restart data.

STEPRESTART

enables restart mode, ensuring that execution resumes at the proper checkpoint.

When you use the GRIDLRESTARTOK argument, these options are automatically added to your SAS program:

LABELCHKPT

enables checkpoint mode for labeled code sections.

LABELRESTART

enables restart mode, ensuring that execution resumes at the proper labeled section.

Other options are automatically added to control restart mode. See "Checkpoint Mode and Restart Mode" in SAS Language Reference: Concepts for a list of options and their definitions as well as complete information about enabling checkpoint restart mode in your SAS programs.

If the host that is running the job becomes unresponsive, the program is automatically restarted at the last checkpoint.

Setting Up Automatic Job Requeuing

You can set up a queue that automatically requeues and redispatches any job that ends with a specified return code or terminates due to host failure. Using job requeuing enables you to handle situations where the host or the system fails while the job is running. Using the requeue capability ensures that any failed jobs are automatically dispatched to another node in the grid.

To use this functionality in a grid, you must use the SAS Grid Manager Client Utility and configure the SAS WORK library to run on shared storage.

To set up a queue for automatic restart, follow these steps:

- 1. Create a queue, including these two options in the queue definition:
 - REQUEUE EXIT VALUES=return code areturn code b ...return code n option in the queue definition. The return code values are the job exit codes that you want to filter. Any job that exits with one of the specified codes is restarted.

Specifying REQUEUE EXIT VALUES=all ~0 ~1 specifies that jobs that end with an exit code other than 0 (success) or 1 (warnings) are requeued.

Note: If you specify a return code value higher than 255, LSF uses the modulus of the value with 256. For example, if SAS returns an exit code of 999, LSF sees that value as (999 mod 256) or 231. Therefore, you must specify a value of 231 on REQUE EXIT VALUES.

- RERUNNABLE=YES. This specifies that jobs sent from this queue can be rerun if the host running them fails.
- 2. Specify the queue that you created in step 1, either by modifying a grid server definition or by specifying the -GRIDJOBOPTS option.

To create or modify a grid server definition, use the Server Manager plug-in in SAS Management Console. To specify the queue, specify

"queue=<name_of_requeue_queue>" in the Additional Options field of the server definition.

To use -GRIDJOBOPTS, submit the job using the -GRIDJOBOPTS queue=name of requeue queue option.

3. Submit the job to the requeue queue on the grid. You must use the SAS Grid Manager Client Utility to specify the -GRIDRESTARTOK option. Send the job to the requeue queue by using the server that you specified in step 2.

Chapter 6

Using Grid Management Applications

Using Platform RTM for SAS	73
Using the Grid Manager Plug-in for SAS Environment Manager	74
Overview	74
Using the Grid Manager Plug-in as the LSF Administrator	75
Viewing Grid Information	75
Viewing LSF Cluster Information	76
Managing Hosts	76
Managing Queues	77
Managing Jobs	78
Viewing Grid Host Information	80
Managing High Availability Applications	80
Viewing Audit Log Records	81
Using the Grid Manager Plug-in for SAS Management Console	83
Overview	83
Maintaining the Grid	84

Using Platform RTM for SAS

Platform RTM for SAS is a web-based tool that lets you graphically view the status of devices and services within your SAS Grid environment as well as manage the policies and configuration of the grid. It is a visual tool to quickly track and diagnose issues before they affect service levels. Platform RTM for SAS provides these features:

- drill-down capabilities to view details of hosts, jobs, queues, and user activities
- instant alerts on job performance and grid efficiency to enable administrators to optimize usage and workloads
- customizable graphs to visually analyze resource usage, workload trends, and job behavior
- interfaces to allow administrators to update the policies and rules in the grid configuration as well as set up high availability for any critical grid services executing in the grid

Platform RTM for SAS helps system administrators improve decision-making, reduce costs, and increase service levels for SAS grid deployments. Refer to the documentation included with the Platform RTM installation package for instructions.

Platform RTM for SAS is supported on the following operating systems:

- Red Hat Linux 32/64 bit
- Windows Server 2008 R2 64 bit
- Windows 7 32/64 bit

If you have a UNIX grid, you must install the Linux version of Platform RTM for SAS on a Linux machine or a Linux virtual machine (VM). If you have a Windows grid, you must install the Windows version of Platform RTM for SAS on a Windows 7 or Windows Server 2008R2 machine or virtual machine (VM).

Download Platform RTM for SAS from http://support.sas.com/downloads/browse.htm?fil=&cat=54.

Using the Grid Manager Plug-in for SAS Environment Manager

Overview

The Grid Manager plug-in for SAS Environment Manager enables you to monitor a SAS grid cluster. The plug-in provides some of the same functions as Platform RTM, so you can monitor your grid using the same application that you use to monitor your SAS environment. This plug-in enables you to manage grid resources by providing dynamic information and management functions for the following:

- The defined LSF cluster
- Hosts that make up the grid
- Queues that control grid processing
- · Jobs submitted to the grid cluster
- High availability applications defined for the grid
- Audit log for any management actions on the plug-in

The management functions provided by the plug-in include the following:

Jobs

Kill (stop execution), suspend (pause execution), and resume (restart a suspended job).

Hosts

Close (prevents jobs from processing on the machine), open (enables jobs to be processed on the machine).

Queue

Close (the queue cannot accept jobs), open (accepts jobs), inactivate (the queue can accept jobs, but cannot process them), activate (reactivates an inactive queue).

High availability applications

Migrate (start the application on the failover host), stop, start, restart (start the application on the original host). Management of high availability applications is available only for LSF administrators.

You must install and configure Platform Web Services in order to use the Grid Manager plug-in for SAS Environment Manager. Use the SAS Deployment Wizard to install Platform Web Services. See "Installing and Configuring SAS Environment Manager in a Grid Environment" on page 24 for more information.

Platform Web Services must run under the account of the LSF Administrator user. To change the account that the service is running under, follow these steps:

- 1. In the Windows Services window, click the entry for the service SASServer14 1 and select **Stop** from the context menu.
- 2. In the dialog box for the SASServer14 1 service, click the **Log On** tab.
- 3. Select the **This account** radio button and specify the user ID and password of the LSF Administrator user. Click **OK** to close the dialog box.
- 4. Click the entry for the service and select **Start** from the context menu.

Using the Grid Manager Plug-in as the LSF Administrator

These Grid Manager functions are available only for the LSF Administrator user:

- High Availability tab
- Audit Log tab
- Ability to view job information for all users

Users in SAS Environment Manager are mapped to users created in SAS metadata. In order for the LSF Administrator user identity to be available as a valid user in SAS Environment Manager, you must perform one of the following actions:

- If the LSF Administrator identity is defined in metadata but not in SAS Environment Manager, then add the identity to the group SAS EV Super User in SAS metadata and synchronize the users in SAS Environment Manager (select Synchronize Users under the Manage tab).
- If the LSF Administrator identity is defined in metadata and in SAS Environment List to add the identity to the Super User Role.
- If identities have been defined in the SAS EV Super User group, then you can specify one of those identities as an LSF Administrator by adding the identity to the LSF configuration file. You do not have to synchronize the SAS metadata and SAS Environment Manager user information if you use this approach.

Adding the LSF Administrator user to the SAS_EV_Super_User group enables the user to sign on to SAS Environment Manager using the LSF Administrator's credentials and assigns the user to the Super User role in SAS Environment Manager. See SAS Environment Manager: User's Guide for information about user management in SAS Environment Manager.

Viewing Grid Information

Start the SAS Environment Manager plug-in by selecting Analyze

⇒ Grid Manager. The plug-in initially displays information about the defined LSF clusters. The management functions of the plug-in are identified by these tabs:

- Cluster
- Hosts
- Queues
- Jobs
- Host Dashboard

- · High Availability
- Audit Logs

Viewing LSF Cluster Information

The initial view of the SAS Environment Manager Grid Manager plug-in is the **Cluster** tab, which displays the **Cluster Summary** table. This table contains the status of the LSF cluster. A cluster is a group of hosts, organized and managed by an LSF administrator. Clusters are the basis for job sharing in Platform LSF.




Managing Hosts

The SAS Environment Manager **Hosts** tab enables you to close or reopen hosts on the grid, and to view information about each host. A closed host cannot process any jobs that are sent to the grid. Closing a host is useful when you want to remove the host from the grid for maintenance. You can also close the grid control server to prevent it from receiving work.

To perform an action on a host in SAS Environment Manager, follow these steps:


1. Select the **Hosts** tab to display the **Host Summary** table.



- 2. In the table, select the check box for the host that you want to close or open.
- 3. In the **Choose an action** menu, select the action that you want to perform and click **Submit**.

Specify a value in the **Auto Refresh** field to specify how often the information in the table is updated. By default, auto refresh is disabled. Click the refresh icon to manually refresh the table.

Click on an entry in the **Host Name** column in the **Host Summary** table to view the **Host Details** table, which contains detailed information about the selected machine.




Managing Queues

You can use the Queues tab on the Grid Manager plug-in to close, open, activate, and inactivate queues. You can also view detailed information about each queue. A closed queue cannot accept any jobs that are sent to the grid. An inactive queue can still accept jobs, but none of the jobs in the queue can be processed. Closing a queue is useful when you need to make configuration changes to the queue.

To manage a queue in SAS Environment Manager, follow these steps:

1. Select the **Queues** tab to display the **Queue Summary** table.



- 2. In the table, select the check box for the queues that you want to perform an action on.
- 3. In the Choose an action menu, select the action that you want to perform and click **Submit**. Choices for actions include the following:

Open

Opens a closed queue. The queue can accept new jobs and processes the jobs in the queue.

Close

Closes a queue. A closed queue cannot accept any jobs that are sent to the grid. Closing a queue is useful when you need to make configuration changes.

Activate


Activate an inactivated queue. The queue can accept jobs, and the jobs in the queue are processed.

Inactivate

Makes a queue inactive. An inactive queue can still accept jobs, but none of the jobs in the queue can be processed.

Specify a value in the **Auto Refresh** field to specify how often the information in the table is updated. By default, auto refresh is disabled. Click the refresh icon to manually refresh the table.

Click on an entry in the **Queue Name** column in the **Queue Summary** table to view the **Queue Details** tables, which contain detailed information about the selected queue.



Managing Jobs

You can use the **Jobs** tab on the Grid Manager plug-in to terminate or suspend running jobs, terminate or resume suspended jobs, or requeue both running and suspended jobs. You can also view detailed information and the history for each job.

To manage jobs in SAS Environment Manager, follow these steps:

- 1. On the **Jobs** tab, select the check box for the job on which you want to perform an action.
- 2. In the **Choose an action** menu, select the action that you want to perform and click **Submit**. Choices for actions are:

Terminate

Stop execution of the selected job. If you log on to SAS Environment Manager using a user ID that has been identified as an LSF Administrator ID, you can terminate any jobs that have been submitted to the grid. Otherwise, you can terminate only your own jobs.

Suspend


Pause the execution of the selected job.

Resume

Resume processing of a suspended job.

Select a value in the Auto Refresh field to specify how often the information in the table is updated. By default, auto refresh is disabled. Click the refresh icon \(\sqrt{1} \) to manually refresh the table.

To view detailed information about a job, click the entry in the **Job ID** column of the Job Summary table. The Job Property Details table displays complete information about the job. Click the job history icon \$\square\$ to display the history of the job.




If you log on to SAS Environment Manager using a user ID that is defined as an LSF Administrator ID, you can terminate any jobs that have been submitted to the grid. Users can terminate only their own jobs. If you are terminating a job on Windows, be sure to match the domain name exactly (including case). See "Using the Grid Manager Plug-in as the LSF Administrator" on page 75 for more information.

Note: Job names that use double-byte characters are not supported by the Grid Manager plug-in.

Viewing Grid Host Information

The SAS Environment Manager **Host Dashboard** tab enables you to view a graphic display of the status of all of the machines on the grid. The tab graphically displays all of the grid machines along with an icon indicating their status:



OK

The host is online and accepting jobs.

• Unavailable

Either the host is down or Platform LSF is unreachable.

Unreachable

Platform LSF is running on the host, but sbatchd is unreachable.

Unlicensed

The Platform LSF license has expired on the machine.

■Closed


The host is active and available, but has been closed and is not accepting jobs.

?Other

The status of the host is a state not covered by one of the other defined states.

Managing High Availability Applications

The SAS Environment Manager **High Availability** tab enables you to control and view information about high availability applications running on the grid. High availability applications are configured through Platform RTM, and are defined to have a primary host and a failover host. If the primary host fails, the application automatically starts on the failover host. The tab enables you to view the status of high availability applications running on a selected host, to stop applications, and to start applications on either the primary host or the failover host.



Note: The **High Availability** tab and its contents are visible only if you sign on to SAS Environment Manager using the credentials for an LSF Administrator. See "Using the Grid Manager Plug-in as the LSF Administrator" on page 75 for more information.

The applications listed in the table in the High Availability tab must be configured using Platform RTM as high availability applications.

To perform an action on a high availability application, select the check box for the application in the table, select the action that you want to perform in the Choose an action menu, and then click Submit. You can perform these actions:

Start the selected application on the failover host. Because migrating an application might take a long time, you should migrate only a few applications at one time in order to avoid time-out errors. This option is useful if you are performing maintenance on the primary host.

Stop

Stop the selected application.

Start


Start the selected application based on the application definition.

Restart the application on the original host if that host is running.

Specify a value in the **Auto Refresh** field to specify how often the information in the table is updated. By default, auto refresh is disabled. Click the refresh icon 🔰 to manually refresh the table.


Viewing Audit Log Records

The **Audit Logs** tab enables you to view information about records in the LSF audit log database. Select the tab to view the Audit Log Summary table, which contains a list of the audit log records.



Specify a value in the **Auto Refresh** field to specify how often the information in the table is updated. By default, auto refresh is disabled. Click the refresh icon to manually refresh the table.

Click on an entry in the **Audit Log ID** column to view the **Details** table for the selected audit log record.



By default, audit logs are purged after 30 days. To change the amount of time that audit logs are kept, change the value of the AUDIT_LOG_KEEP parameter in the Platform Web Services database.

Note: The Audit Logs tab and its contents are visible only if you sign on to SAS Environment Manager using the credentials for an LSF Administrator. See "Using the Grid Manager Plug-in as the LSF Administrator" on page 75 for more information.

Using the Grid Manager Plug-in for SAS Management Console


Overview

The Grid Manager plug-in for SAS Management Console enables you to monitor SAS execution in a grid environment. This plug-in enables you to manage workloads on the grid by providing dynamic information about the following:

- jobs that are running on the grid
- nodes that are configured in the grid
- job queues that are configured in the grid


Information is displayed in tabular or chart format. Here is an example of a job view:

Display 6.1 Job View in the Grid Manager Plug-in to SAS Management Console



Using the SAS Grid Manager, you can customize the view by selecting the columns of data to display and the order in which they should appear. In addition, you can filter, sort, and refresh the display of jobs.

Display 6.2 Subsetting Data in the Grid Manager Plug-in



Each grid that you define must have one grid monitoring server configured and running on a machine in the grid.

Maintaining the Grid


Viewing Grid Information

When you expand the Grid Manager node in the navigation tree, all of the grid monitoring servers that you have defined are listed under the name of the plug-in. Each one represents a unique grid. To view information about a specific grid, expand the server's node in the navigation tree. The information for a grid is grouped into three categories in the navigation tree:

- Job Information
- Host Information
- · Queue Information

Select a category to display a table that contains information for the category. You can also display a graph of the job information. Click the column headings to select the information that is displayed in the table. Click **Options** to start the Filter wizard, which you can use to select which jobs to display.

Figure 6.1 Filter Options Dialog Box



After you have defined filters, you can select a filter and click Filter Now to filter the displayed information. You can also manage jobs, hosts, and queues from the tables.

Right-click the Grid Monitoring Server node in the navigation tree and select **Options** to specify that the information from the grid is automatically refreshed and how often it is refreshed.

Managing Jobs

Use the Grid Manager to terminate or suspend running jobs and terminate or resume suspended jobs.

To terminate a job, follow these steps:

- 1. In the selection tree, select the Job Information node.
- 2. In the table, locate the job that you want to cancel.
- 3. Right-click any column in the row for the job and select Terminate Task from the pop-up menu.

If you log on to SAS Management Console using a user ID that is defined as an LSF Administrator ID, you can terminate any jobs that have been submitted to the grid. Users can terminate only their own jobs. The LSF Administrator can terminate any job. If you are terminating a job on Windows, be sure to match the domain name exactly (including case).

To suspend a job (pause the job's execution), follow these steps:

- 1. In the selection tree, select the **Job Information** node.
- 2. In the table, locate the job that you want to suspend.

3. Right-click any column in the row for the job and select **Suspend Job** from the context menu.

To resume processing of a suspended job, follow these steps:


- 1. In the selection tree, select the **Job Information** node.
- 2. In the table, locate the job that you want to resume.
- 3. Right-click any column in the row for the job and select **Resume Job** from the context menu.

Displaying Job Graphs

You can use the Grid Manager to display GANTT charts for jobs running on the grid. To display a chart, follow these steps:


- 1. In the selection tree, select the Job Information node.
- 2. Right-click and select either Create Graph by Host or Create Graph by Status from the Actions menu, the context menu, or the toolbar.
- 3. Select **Create Graph by Host** to display a Gantt chart that shows the amount of time taken to process each job and identifies the machine on which the job ran.

Display 6.3 Display of Grid Jobs by Host



4. Select **Create Graph by Status** to display a Gantt chart that illustrates the amount of time that each submitted job spent in each job status (such as pending or running).

Display 6.4 Display of Grid Jobs by Status



Closing and Reopening Hosts

You can use the Grid Manager to close or reopen hosts on the grid. A closed host cannot process any jobs that are sent to the grid. Closing a host is useful when you want to remove the host from the grid for maintenance. You can also close the grid control server to prevent it from receiving work.

Note: The status of a host does not change right away after it has been opened or closed. By default, the host status is polled every 60 seconds by the Grid Management Service. The polling time interval is specified by the GA HOST POLL TIME property in the ga.conf file, which is located in the <LSF install dir>/gms/ conf directory.

To close a host, follow these steps:

- 1. In the navigation area, open the node for the grid containing the host.
- 2. Select the **Host Information** node.

The display area contains a table of the hosts in the grid.

3. In the table, right-click the host that you want to close and select Close from the context menu.

The host now cannot accept jobs that are sent to the grid.

To open a host that has been closed, follow these steps:

- 1. In the navigation area, open the node for the grid containing the host.
- 2. Select the **Host Information** node. The display area contains a table of the hosts in the grid.

3. In the table, right-click the host that you want to open and select **Open** from the context menu. The host can now accept jobs that are sent to the grid.

Managing Queues

You can use the Grid Manager to close, open, activate, and inactivate queues. A closed queue cannot accept any jobs that are sent to the grid. An inactive queue can still accept jobs, but none of the jobs in the queue can be processed. Closing a queue is useful when you need to make configuration changes to the queue.

To close a queue, follow these steps:

- 1. In the navigation area, open the node for the grid containing the queue.
- 2. Select the Queue Information node.

The display area contains a table of the queues in the grid.

3. In the table, right-click the queue that you want to close and select **Close** from the context menu.

The queue is now prevented from accepting jobs that are sent to the grid.

To open a closed queue, follow these steps:

- 1. In the navigation area, open the node for the grid containing the queue.
- 2. Select the **Queue Information** node.

The display area contains a table of the queues in the grid.

3. In the table, right-click the queue that you want to open and select **Open** from the context menu.

The queue can now accept jobs that are sent to the grid.

To inactivate a queue, follow these steps:

- 1. In the navigation area, open the node for the grid containing the queue.
- 2. Select the **Queue Information** node.

The display area contains a table of the queues in the grid.

3. In the table, right-click the active queue that you want to make inactive and select **Inactivate** from the context menu.

To activate a queue, follow these steps:

- 1. In the navigation area, open the node for the grid containing the queue.
- 2. Select the **Queue Information** node.

The display area contains a table of the queues in the grid.

3. In the table, right-click the inactive queue that you want to make active and select **Activate** from the context menu.

Chapter 7

Troubleshooting

Overview of the Troubleshooting Process	89
Verifying the Network Setup	. 90
Overview	. 90
Host Addresses	. 90
Host Connectivity	. 90
Host Ports	. 90
Verifying the Platform Suite for SAS Environment	. 91
Verifying That LSF Is Running	. 91
Verifying LSF Setup	. 92
Verifying LSF Job Execution	. 93
Verifying the SAS Environment	. 93
Verifying SAS Grid Metadata	93
Verifying Grid Monitoring	. 94
Verifying SAS Job Execution	. 94
Debugging Grid Jobs	96
Fixing Issues with the Grid Manager Plug-in for SAS Environment Manager	96

Overview of the Troubleshooting Process

These topics provide the framework for a systematic, top-down approach to analyzing problems with a grid environment. By starting at the highest level (the network) and working downward to the job execution, many common problems can be eliminated.

For the troubleshooting information not contained here, go to http://support.sas.com/rnd/scalability/grid/gridinstall.html or contact SAS Technical Support.

Verifying the Network Setup

Overview

The first step in troubleshooting problems with a SAS grid is to verify that all computers in the grid can communicate with one another through the ports that are used by Platform Suite for SAS.

Host Addresses

Check the /etc/hosts file on each grid node to ensure that the machine name is not mapped to the 127.0.0.1 address. This mapping causes the sign-on connection to the grid node to fail or to hang. This happens because the SAS session that is being invoked on the grid node cannot determine the correct IP address of the machine on which it is running. A correct IP address must be returned to the client session in order to complete the connection. For example, delete the name "myserver" if the following line is present in the /etc/hosts file:

127.0.0.1 myserver localhost.localdomain localhost

Host Connectivity

You must verify that the network has been set up properly and that each machine knows the network address of all the other machines in the grid. Follow these steps to test the network setup:

- 1. Run the **hostname** command on every machine in the grid (including grid nodes, grid control servers, and Foundation SAS grid clients).
- Run the ping command on all grid node machines and the grid control machine against every other machine in the grid (including grid client machines). When you ping a grid client machine, use the host name without the domain suffix.
- 3. Run the ping command on each grid client machine against every other machine in the grid (including itself). When a grid client machine pings itself using the value from the hostname command, verify that the returned IP address is the same IP address that is returned when the grid nodes ping the client. However, this might not occur on machines with multiple network adapters.

If the network tests indicate a problem, you must either correct the DNS server or add entries to each machine's hosts file. Contact your network administrator for the best way to fix the problem.

Platform LSF assumes that each host in the grid has a single name, that it can resolve the IP address from the name, and that it can resolve the official name from the IP address. If any of these conditions are not met, LSF needs its own hosts file, which is located in its configuration directory (LSF ENVDIR/conf/hosts).

Host Ports

You must verify that the ports that SAS and LSF use for communication are accessible from other machines. The ports might not be accessible if a firewall is running on one or

more machines. If firewalls are running, you must open ports so that communication works between the LSF daemons and the instances of SAS. Issue the telnet <host><port> command to determine whether a port is open on a specific host.

The default ports used in a grid include the following:

- LSF: 6878, 6881, 6882, 7869, 7870, 7871, 7872
- Grid Monitoring Service: 1976
- Platform Process Manager: 1966

If you need to change any port numbers, modify these files:

- LSF ports: LSF ENVDIR/conf/lsf.conf and EGO CONFDIR/ego.conf
- Grid Monitoring Service port: gms/conf/ga.conf
- Platform Process Manager port: pm/conf/js.conf

If you change the Grid Monitoring Service port, you must also change the metadata for the Grid Monitoring Server. If you change the Platform process Manager port, you must also change the metadata for the Job Scheduler Server.

Ports might be used by other programs. To check for ports that are in use, stop the LSF daemons and issue the command netstat -an | <search-tool >< port>, where searchtool is grep (UNIX) or findstr (Windows). Check the output of the command for the LSF ports. If a port is in use, reassign the port or stop the program that is using the port.

SAS assigns random ports for connections, but you can restrict the range of ports SAS uses by using the -tcpportfirst <first-port> and -tcpportlast <lastport> options. You can specify these options in the SAS configuration file or on the SAS command line. For remote sessions, you must specify these options either in the grid command script (sasgrid.cmd on Windows or sasgrid on UNIX) or in the **Command** field in the logical grid server definition in metadata. For example, adding the following parameters to the SAS command line in the grid script restricts the ports that the remote session uses to between 5000 and 5005:

-tcpportfirst 5000 -tcpportlast 5005

Verifying the Platform Suite for SAS Environment

Verifying That LSF Is Running

After the installation and configuration process is complete, verify that all of the LSF daemons are running on each machine.

For Windows machines, log on to each machine in the grid and check the Services dialog box to verify that these services are running:

- Platform LIM
- Platform RES
- Platform SBD

For UNIX machines, log on to each machine in the grid and execute the ps command to check for processes that are running in a subdirectory of the \$LSF_install_dir. An example command follows:

```
ps -ef|grep LSF install dir
```

The daemons create log files that can help you debug problems. The log files are located in the machine's LSF install dir\logs directory (Windows) or the shared LSF TOP/log directory (UNIX). If the daemon does not have access to the share on UNIX, the log files are located in the /tmp directory.

If the command fails, check the following:

- Verify that the path to the LSF programs is in the PATH environment variable. For LSF 7, the path is LSF install dir/7.0/bin.
- On UNIX machines, you might have to source the LSF TOP/conf/profile.lsf file to set up the LSF environment.
- A machine might not be able to access the configuration files. Verify that the machine has access to the shared directory that contains the binary and configuration files, defined by the LSF ENVDIR environment variable. If the file server that is sharing the drive starts after the grid machine that is trying to access the shared drive, the daemons on the machine might not start. Add the LSF GETCONF TIMES environment variable to the system environment and set the variable value to the number of times that you want the daemon to try accessing the share in each fivesecond interval before the daemon quits. For example, setting the variable to a value of 600 results in the node trying for 50 minutes ((600*5 seconds)/60 seconds per minute) before quitting.
- The license file might be invalid or missing. If LSF cannot find a license file, some daemons might not start or work correctly. Make sure that the license file exists, is properly referenced by the LSF LICENSE FILE parameter in the LSF ENVDIR/ conf/lsf.conf file, and is accessible by the daemons.
- All daemons might not be running. Restart the daemons on every machine in the grid using the lsfrestart command. If this command does not work, run the /etc/ init.d/lsf restart command (UNIX) or use the Services Administration tool (Windows). Open Services Administration, stop the SBD, RES, and LIM services (in that order). Next, start the LIM, RES, and SBD services (in that order).
- A grid machine might not be able to connect to the SAS grid control machine. The grid control machine is the first machine listed in the lsf.cluster.cluster name> file. Make sure that the daemons are running on the master host, and verify that the machines can communicate with each other.

Verifying LSF Setup

You must verify that all grid machine names are specified correctly in the LSF ENVDIR/conf/lsf.cluster.<cluster name> file and the resource is specified in the lsf.shared file. Follow these steps to make sure the configuration is correct:

- 1. Log on as an LSF administrator on one of the machines in the grid, preferably the grid control server machine. The LSP Administrator ID is listed in the lsf.cluster.<cluster name> file under the line
 - Administrators=username1username2 ... usernameN.
- 2. Run the command lsadmin ckconfig -v to check the LSF configuration files
- 3. Run the command badmin ckconfig -v to check the batch configuration files
- 4. Run the command lshosts to list all the hosts in LSF, and to verify that all the hosts are listed with the proper resources.

- 5. Run the command bhosts to list all the hosts in LSF's batch system. Verify that all hosts are listed. Make sure that the Status for all hosts is set to ok and that the correct number of jobs slots have been defined for each host in the MAX column (the maximum number of jobs the host can process at the same time).
- 6. If you find any problems, correct the LSF configuration file and issue the commands lsadmin reconfig and badmin reconfig so that the daemons use the updated configuration files.
- 7. If you added or removed hosts from the grid, restart the master batch daemon by issuing the command badmin mbdrestart. To restart everything, issue the lsfrestart command.

Verifying LSF Job Execution

Some problems occur only when you run jobs on the grid. To minimize and isolate these problems, you can run debug jobs on specific machines in the grid.

To submit the debug job, run the command bsub -I -m <host_name> set from the grid client machine to each grid node. This command displays the environment for a job running on the remote machine and enables you to verify that a job runs on the machine.

If this job fails, run the bhist -1 < job_id>' command, where job_id is the ID of the test job. The output of the command includes the user name of the person submitting the job, the submitted command, and all the problems LSF encountered when executing the job. Some messages in the bhist output for common problems include the following:

Failed to log on user with password

specifies that the password in the Windows passwd.lsfuser file is invalid. Update the password using the lspasswd command.

Unable to determine user account for execution

specifies that the user does not have an account on the destination machine. This condition can occur between a Windows grid client to a UNIX grid node because a domain has been prefixed to the Windows user name. Correct this problem by making sure that the user has an account on the UNIX machines. Also, add the line LSF_USER_DOMAIN= to the Windows lsf.conf file to strip the domain from the user name.

Verifying the SAS Environment

Verifying SAS Grid Metadata

SAS needs to retrieve metadata about the grid from a SAS Metadata Server in order to operate properly. Start SAS Management Console and use the Server Manager plug-in to verify the following:

Logical grid server

Under the SAS Application Server context (for example, SASApp), verify that a logical grid server has been defined.

Open the Properties window for the logical grid server. Verify that the properties contain the correct path to the script file or the correct command that is executed on

the grid node. Verify that the path exists on every node in the grid and that the command is valid on every node in the grid.

Grid monitoring server

Verify that a grid monitoring server has been defined.

Open the connection properties for the server. Verify that the properties contain the name or address of the machine that is running the Grid Monitoring Server daemon (typically the SAS grid control machine). Verify that the port specified in the properties is the same as that specified in the Grid Monitoring Service configuration file (the default value is 1976).

Verifying Grid Monitoring

The Grid Manager plug-in for SAS Management Console displays information about the grid's jobs, hosts, and queues. After you define the Grid Monitoring Server and the Grid Management Service is running on the control server, grid information is displayed in the Grid Manager plug-in in SAS Management Console. Common error messages encountered in the Grid Manager plug-in include the following:

Connection timed out or Connection refused

The Grid Management Service is not running. Start the Grid Management Service on the grid control machine.

Your user ID or password is invalid. Please try again or contact your systems administrator

Either the user provided invalid credentials for the machine running the Grid Monitoring Service, or the user's credentials that are stored in the metadata do not include a password for the login that is associated with the authorization domain used by the Grid Monitoring Server connection. For example, "Grid 1 Monitoring Server" is defined in the metadata to use the "DefaultAuth" authorization domain. A login has been defined for "User1" in the User Manager for the "DefaultAuth" domain, but only the user ID has been specified and the password is blank.

There are three ways to correct the problem. First, provide complete credentials for the authorization domain for the user. Second, you can remove the login for the authorization domain. The third option is to use a different authorization domain for the Grid Monitoring Server connection. If you provide the correct credentials, the user is not prompted for a user ID and password. If you remove the login for that authorization domain or change the Grid Monitoring Server connection to use a different authorization domain without adding credentials for the user for that domain, the user is prompted for their user ID and password to connect to the machine where the Grid Monitoring Server is running.

Verifying SAS Job Execution

SAS provides a grid test program on the SAS support website that tests connectivity to all nodes in the grid. Run the program from a grid client. You can download the program from http://support.sas.com/rnd/scalability/grid/ gridfunc.html#testprog. After you download the program, follow these steps:

- 1. Copy and paste the grid test program into a Foundation SAS Display Manager session.
- 2. If the application server associated with your logical grid server in your metadata is not named "SASMain", change all occurrences of "SASMain" in the test program to the name of the application server that is associated with your logical grid server. For

example, some SAS installations have named the application server "SASApp", so all occurrences of SASMain should be replaced with "SASApp".

3. Submit the code.

The program attempts to start one remote SAS session for every job slot available in the grid. The program might start more than one job on multi-processor machines, because LSF assigns one job slot for each core by default.

Here are some problems that you might encounter when running the grid test program:

Grid Manager not licensed message

Make sure that your SID contains a license for SAS Grid Manager.

Grid Manager cannot be loaded message

Make sure that Platform Suite for SAS has been installed and that the LSF and PATH environment variables are defined properly.

Invalid resource requested message

The application server name or workload value has not been defined in the lsf.shared file. Also, make sure that you associate the value with the hosts that you want to run SAS programs in the lsf.cluster.<*cluster name*> file.

The number of grid nodes is 0.

Possible reasons for this error include the following:

- The application server name was not defined as a resource name in the lsf.shared
- The application server name was not associated with any grid nodes in the lsf.cluster.<cluster name> file.
- The grid client where the job was submitted cannot communicate with the entire

The number of grid nodes is not the same as the number of grid node machines.

As shipped, the number of grid nodes equals the number of job slots in the grid. By default, the number of job slots is equal to the number of cores, but the number of job slots for a grid node can be changed.

Another explanation is that the application server name has not been associated with all the grid nodes in the lsf.cluster. < cluster name > file.

Jobs fail to start.

Possible reasons for this problem include the following:

- The grid command defined in the logical grid server metadata is either not valid on grid nodes or does not bring up SAS on the grid node when the command is run. To verify the command, log on to a grid node and run the command defined in the logical grid server definition. The command should attempt to start a SAS session on the grid node. However, the SAS session might not run successfully because grid parameters have not been included. Platform Suite for SAS provides a return code of 127 if the command to be executed is not found and a return code of 128 return code if the command is found, but there is a problem executing the command.
- Incorrect version of SAS installed on grid nodes. SAS 9.1.3 Service Pack 3 is the minimum supported version. A return code of 231 might be associated with this problem.
- Unable to communicate between the grid client and grid nodes. Verify that the network is set up properly, using the information in "Verifying the Network Setup" on page 90.

Jobs run on machines that are supposed to be only grid clients.

By default, all machines that are listed in the lsf.cluster.<*cluster_name>* file are part of the grid and can process jobs. If you want a machine to be able to submit jobs to the grid (a grid client) but not be a machine that can process the job (a grid node), set its maximum job slots to 0 or use the Grid Manager plug-in to close the host.

Debugging Grid Jobs

When a grid-enabled SIGNON is used or a job is submitted by SASGSUB, the sasgrid script is used to start a SAS session on the grid node. To aid in debugging, the output from the script (but not the SAS log and SAS output) is written to a unique log file. The file is located in the <code>GridServer/Logs</code> directory of the machine where the job runs. If the job is successful, the log file is deleted when the job finishes running. If the job is unsuccessful, the log file is saved.

The log file is named using the format SASGrid.userID.hostname.process_ID.YYYMMDDhhmmss.log

The log file is not created if the job is run on a grid-enabled IOM server (workspace server, stored process server, or pooled workspace server), because these servers do not use the sasgrid script. These servers are started by the object spawner, so you must configure logging of the object spawner to debug grid-enabled IOM servers. For example, you can set the logger App.tk.tkegrid to TRACE and then review the object spawner's log.

Fixing Issues with the Grid Manager Plug-in for SAS Environment Manager

Here are some possible solutions if the Grid Manager plug-in fails to invoke in SAS Environment Manager:

You receive a "Service is temporarily not available" error

Verify that Platform Web Services is running. Restart the service if needed.

You receive a "Connecting to the server failed" error

Verify that SAS Environment Manager is running.

You receive an "Internal server error" message

Verify that Platform LSF is running.

You receive the message "You do not have permission to perform this action" when attempting to use the Grid Manager plug-in on Windows

This message indicates that Platform Web Services is not running under the LSF Administrator account. To change the account that the service is running under, follow these steps:

- 1. In the Windows Services window, click the entry for the service **SASServer14_1** and select **Stop** from the context menu.
- 2. In the dialog box for the SASServer14 1 service, click the **Log On** tab.

- 3. Select the **This account** radio button and specify the user ID and password of the LSF Administrator user. Click **OK** to close the dialog box.
- 4. Click the entry for the service and select **Start** from the context menu.

If you would rather issue commands, open a Windows Command window and issue these commands:

- net stop "SAS [SASConfig-Lev] SASServer14 1 WebAppServer"
- sc config "SAS [SASConfig-Lev] SASServer14 1 WebAppServer" obj= domain \userid password= password

Note: You must include a space between the equal sign and the value for the obj= and password= parameters.

net start "SAS [SASConfig-Lev] SASServer14 1 - WebAppServer"

Substitute your directory names for SASConfig-Lev.

You must update the entry for this service anytime the password for the LSF Administrator account changes.

Platform Web Services Errors

You receive permission errors or LSF library initialization errors

Verify that Platform Web Services is running under the LSP Administrator account. These errors occur if Platform Web Services runs under a local user account. To change the account that the service is running under, follow these steps:

- 1. In the Windows Services window, click on the entry for the service SASServer14 1 and select **Stop** from the context menu.
- 2. In the dialog box for the SASServer14 1 service, click the **Log On** tab.
- 3. Select the **This account** radio button and specify the user ID and password of the LSF Administrator user. Click **OK** to close the dialog box.
- 4. Click the entry for the service and select **Start** from the context menu.

Examining the debug log might help diagnose problems with the Grid Manager plug-in. To start logging, open the file server-log4j.xml (in the directory \$SASEV/conf) and change the root-level value to **DEBUG**. The debugging information is written to the file server.log in the directory \$SASEV/logs.

Part 2

SAS Grid Language Reference

Chapter 8	
SAS Functions for SAS Grid	101
Chapter 9	
SASGSUB Command	115

Chapter 8

SAS Functions for SAS Grid

ictionary	. 101
GRDSVC_ENABLE Function	101
GRDSVC_GETADDR Function	. 106
GRDSVC_GETINFO Function	. 107
GRDSVC_GETNAME Function	110
GRDSVC NNODES Function	111

Dictionary

GRDSVC_ENABLE Function

Enables or disables one or all SAS sessions on a grid.

Valid in: %SYSFUNC or %QSYSFUNC Macro, DATA step

Category: Grid

Syntax

```
grdsvc_enable(identifier <,option-1; ... option-n>)
grdsvc_enable(identifier,"" | " )
```

Required Argument

identifier

specifies one or all server sessions to be enabled or disabled for grid execution. The *identifier* is specified as follows:

```
server-ID
```

specifies the name of a SAS/CONNECT server session to be enabled or disabled for grid execution.

You use this *server-ID* when you sign on to a server session using the SIGNON or the RSUBMIT statement. For information about ways to specify the server ID, see *SAS/CONNECT User's Guide*.

Requirement If the function is used in a DATA step, enclose server-ID in

double or single quotation marks. A server-ID cannot exceed

eight characters.

```
ALL
```

specifies that all SAS sessions are enabled or disabled for grid execution.

See SIGNON statement and RSUBMIT statement in SAS/CONNECT

User's Guide

Example %let rc=%sysfunc(grdsvc_enable(grdnode1,server=SASApp));

%let rc=%sysfunc(grdsvc_enable(_all_, server=SASApp));

%let rc=%sysfunc(grdsvc enable(notgrid1,""));

Optional Arguments

SASAPPSERVER=server-value

specifies the name of a SAS Application Server that has been defined in the SAS Metadata Repository. The SAS Application Server contains the definition for the logical grid server that defines the grid environment.

Alias SERVER=, RESOURCE=

Restriction

Although a SAS Application Server is configured as a required grid resource in most environments, some grids are not partitioned by resource names. In these environments, passing the SAS Application Server name as a required resource causes the job to fail. To find out whether the SAS Application Server is designated as a required resource value or not in the SAS Metadata Repository, use the GRDSVC GETINFO function call.

Interaction

The name of the SAS Application Server is passed to Platform Suite for SAS as a resource value. When the job is executed, Platform Suite for SAS selects a grid node that meets the requirements that are specified by this value. If *SAS-application-server* contains one or more spaces, the spaces are converted to underscores before the name is passed to Platform Suite for SAS as a resource value.

Tip

For Platform Suite for SAS, this *server-value* corresponds with the value of a resource that the LSF administrator has configured in the lsf.cluster.*cluster-name* file and the lsf.shared file on the grid-control server

See

"GRDSVC_GETINFO Function" on page 107 to find out whether the SAS Application Server is designated as a required resource value in the SAS Metadata Repository. To remove the SAS Application Server name as a required resource, see "Modifying SAS Logical Grid Server Definitions" on page 17.

Example %1e

rc=%sysfunc(grdsvc_enable(_all_, server=SASApp));

GRIDOPTSET="grid options set name"

specifies the grid options set to be used when running jobs on the grid. A grid options set is a collection of grid options, SAS options, and required resources that are associated with a particular SAS client application. The purpose of a grid options

set is to enable a SAS grid administrator to define a collection of options in SAS metadata. These options will map to one or more SAS client applications and will be applied to workload submitted to the grid.

Requirements

A grid options set must be defined in SAS Management Console before it can be used in the GRDSVC ENABLE function.

The grid options set name must be enclosed in quotation marks.

WORKLOAD=workload-value

identifies the resource for the job to be executed on the grid. This value specifies an additional resource requirement for which Platform Suite for SAS selects the appropriate grid nodes.

The specified workload value should match one of the workload values that are defined in the SAS Application Server in the SAS Metadata Repository.

Requirement Workload values are case sensitive.

Interaction

If workload-value contains one or more spaces, the spaces are converted to underscores before the value is passed to the grid provider. If workload-value is not located in the SAS Application Server definition and no other errors occur, a 0 result code is returned, and this note is displayed:

NOTE: Workload value "gridResource" does not exist in the SAS Metadata Repository

Tip

For Platform Suite for SAS, this workload-value corresponds with the resource that the LSF administrator has configured in the lsf.cluster.cluster-name file and the lsf.shared file on the grid-control computer.

Example

%let rc=%sysfunc(grdsvc enable(grdnode1, server=SASApp; workload=EM));

The workload value EM specifies the resource name. EM must be assigned to a grid node in order to process this job. An example is assigning EM to machines that can process SAS Enterprise Miner jobs.

JOBNAME=job-name-macro-variable

specifies the macro variable that contains the name that is assigned to the job that is executed on the grid.

Example %let

hrjob=MyJobName;

%let rc=%sysfunc(grdsvc enable(grdnode1, server=SASApp; jobname=hrjob)); signon grdnode1;

In this example, hrjob is the name of the macro variable to which the job name is assigned. The actual job name is MyJobName. The status of the job can be tracked using the SAS Grid Manager Plug-in for SAS Management Console. In this example, you track the status of the job named MyJobName.

JOBOPTS=job-opts-macro-variable

specifies the macro variable that contains the job options. The job option name/value pairs are assigned to *job-opts-macro-variable*.

The job options are used by the grid job to control when and where a job runs. Job options are specified as name/value pairs in this format:

```
option-1=value-1; option-2="value-2 with spaces"; ...
option-n='value-n with spaces';
```

For a list of the job options that you can specify, see Appendix 1, "Supported Job Options," on page 131.

Requirement Use a semicolon to separate job option and value pairs. For multiple values, use a macro quoting function for the semicolon or use single or double quotation marks to enclose all job options. If the value contains one or more spaces, tabs, semicolons, or quotation marks, enclose the value in single or double quotation marks.

Example

```
rc=%sysfunc(grdsvc_enable(all, server=SASApp; jobopts=hrqueue));
%let hrqueue=queue=priority%str(;)project="HR Monthly";
signon grdnodel;
%let hrqueue='queue=priority;project="HR Yearly"';
signon grdnode2
```

Both jobs are sent to the priority queue. The first job is associated with the project named "HR Monthly" and the second job is associated with the project named "HR Yearly."

disables grid execution for the specified server ID or all server sessions.

This value is intended to be used when you have specified _ALL_ in a previous call but you want to disable it for a small number of exceptions.

Requirement Double or single quotation marks can be used. Do not insert a space between the double or single quotation marks.

Interaction When quotation marks are used with ALL, it clears all previous grid settings that were specified using the GRDSVC_ENABLE

function.

Example %let rc=%sysfunc(grdsvc enable(grdnode1,"")); %let rc=%sysfunc(grdsvc enable(all ,''));

Details

The GRDSVC ENABLE function is used to enable and disable a grid execution. Grid execution can be enabled for a specified SAS session or for all SAS grid sessions. If a grid environment is not configured or is unavailable, the job is started as a symmetric multi-processor (SMP) process instead.

The GRDSVC ENABLE function does not resolve to a specific grid node, and it does not cause grid execution. The server ID is mapped to a specific grid node. The server session starts on the grid node when requested by subsequent SAS statements (for example, when the SIGNON statement or the RSUBMIT statement is executed).

In order to restrict the use of specific grid nodes to be used by server sessions, the name of the SAS Application Server and the workload resource value are passed as required resources to Platform Suite for SAS.

Note: An exception to this behavior is when the SAS Application Server is disabled as a required resource for the grid server. For details, see the restriction for the SASAPPSERVER= option.

The grid can be partitioned according to resource or security requirements. If grid nodes do not have the required resources, then SAS requests fail. If grid nodes have the required resources but are busy, SAS requests are queued until grid resources become available. For information, see "Defining and Specifying Resources" on page 36.

Some SAS applications are appropriate for execution in a grid environment, but not in an SMP environment. Such applications should contain a macro that checks the return code from the GRDSVC ENABLE function to ensure that a grid node, rather than an SMP process, is used.

Here are the result codes:

Table 8.1 GRDSVC_ENABLE Function Result Codes

Result Code	Explanation		
2	Reports that one or all server sessions were disabled from grid execution.		
1 Reports that a grid environment is unavailable due to one or more of conditions:			
	A connection to the SAS Metadata Server is unavailable.		
	• A logical grid server has not been defined in the SAS Metadata Repository.		
	 The current user identity does not have authorization to use the specified logical grid server. 		
	 SAS Grid Manager has not been licensed. 		
	Instead, server sessions execute on the multi-processor (SMP) computers as a SASCMD sign-on. One of these commands, in order of precedence, is used to start the server session:		
	• the value of the SASCMD system option		
	• !sascmd -noobjectserver		
0	Reports that the specified session was enabled.		
-1	Reports a syntax error in the function call. An example is the omission of the server ID.		
-2	Reports a parsing error in the function call. An example is an invalid option.		
-3	Reports an invalid server ID in the function call.		
	Reports an out-of-memory condition while the function is executing.		

Result Code	Explanation
-6	Reports that the function cannot connect to the SAS Metadata Server or cannot access the grid metadata information. This condition frequently occurs when the user is not explicitly defined in metadata. By default, users without a definition in metadata are assigned to the PUBLIC group, which is not granted the ReadMetadata permission.

See Also

SAS/CONNECT User's Guide

• SAS/CONNECT User's Guide

SAS Language Reference: Dictionary

• SAS Macro Language: Reference

GRDSVC GETADDR Function

Reports the IP address of the grid node on which the SAS session was chosen to execute.

Valid in: %SYSFUNC or %QSYSFUNC Macro, DATA step

Category: Grid

Syntax

grdsvc getaddr(identifier)

Without Arguments

Required Argument

identifier

identifies the server session that is executing on the grid. The identifier can be specified as follows:

""| "

is an empty string that is used to refer to the computer on which the function is executing.

server-ID

specifies the server session that is executing on a grid.

You use the same *server-ID* that was used to sign on to a server session using the RSUBMIT statement or the SIGNON statement. Each server ID is associated with a fully qualified domain name (FQDN). The name resolution system that is part of the TCP/IP protocol is responsible for associating the IP address with the FQDN. The output is one or more IP addresses that are associated with the server. IP addresses are represented in IPv4 and IPv6 format, as appropriate.

Requirement Double or single quotation marks can be used. Do not insert a space between the double or single quotation marks.

Interaction

If the function is used in a DATA step, enclose server-ID in double or single quotation marks.

Example

```
/*----*/
/* The following sets the macro variable 'myip' to the IP address
/* of the grid node associated with the server session 'task1'
                                         */
/*-----*/
myip=%sysfunc(grdsvc_getaddr(task1));
```

See Also

RSUBMIT statement

SAS/CONNECT User's Guide

SIGNON statement

SAS/CONNECT User's Guide

DATA step

SAS Language Reference: Dictionary

%SYSFUNC or %QSYSFUNC

SAS Macro Language: Reference

GRDSVC_GETINFO Function

Reports information about the grid environment.

Valid in: %SYSFUNC or %QSYSFUNC Macro, DATA step

Category: Grid

Syntax

grdsvc_getinfo(identifier)

Required Argument

identifier

specifies the server session or the SAS Application Server whose details you want to have reported to the SAS log.

The *identifier* is specified as follows:

```
server-ID
```

reports details about the specified server ID. The details that are returned by the GRDSRV_INFO function reflect the arguments that are specified in the

GRDSVC ENABLE function. You can request details about a server-ID that you have used to create a server session or that you will use to create a server session on the grid.

Requirement A *server-ID* cannot exceed eight characters.

ALL

reports details about all server IDs to the SAS log. The details that are returned by the GRDSRV_INFO function reflect the arguments that are specified in the GRDSVC ENABLE function.

SASAPPSERVER=SAS-application-server

reports information about the specified SAS Application Server to the SAS log.

```
Alias SERVER=, RESOURCE=
```

SHOWID

lists each server session and its status: enabled for grid execution, enabled for SMP execution, or disabled.

Interaction If the GRDSVC GETINFO function is used in a DATA step, enclose the identifier in single or double quotation marks. The identifier can be specified as server-ID, ALL, SASAPPSERVER=SAS-application-server, or SHOWID . If no grid processes were enabled using the GRDSRV_ENABLE function or if all grid processes were disabled using the GRDSVC ENABLE function with ALL option, this message is displayed:

NOTE: No remote session ID enabled/disabled for the grid service.

Tip

You do not have to be signed on to a specific server session in order to get information about it.

Example

This log message reports that the SAS Application Server is a required resource.

```
%put
```

```
%sysfunc(grdsvc_getinfo(server=SASApp));
NOTE: SAS Application Server Name= SASAPP
           Grid Provider= Platform
           Grid Workload= gridwrk
           Grid SAS Command= gridsasgrid
           Grid Options= gridopts
           Grid Server Addr= d15003.na.sas.com
           Grid Server Port= 123
           Grid Module= gridmod
           Server name is a required grid resource value.
```

If the SAS Application Server is a disabled required resource, this message is displayed:

Server name is not a required grid resource value.

Optional Arguments

CLIENTAPP="client application"

returns information about the grid options set associated with the specified application. The information returned includes the grid options, SAS options, and required resources that are specified in the grid options set and are associated with the specified application.

GRIDOPTSET="grid_options_set_name"

returns information about the specified grid options set. A grid options set is a collection of grid options, SAS options, and required resources that are associated with a particular SAS client application. The purpose of a grid options set is to enable a SAS grid administrator to define a collection of options in SAS metadata. These options will map to one or more SAS client applications and will be applied to workload submitted to the grid.

Requirement	The grid options set name must be enclosed in quotation marks.			
Example This example returns information about the grid options set "OptionsSet1 %put %sysfunc(grdsvc_getinfo(server=CNTWin;gridoptset="OptionsS				
NOTE: SAS Application Server Name= CNTWin				
Grid Provider= Platform				
	Grid Workload=	idbvm1, idbvm2, idbvm3		
	Grid SAS Command=	gridsas		
	Grid Server Addr=	rlsgrid.mycorp.com		
Grid Required Resources= <none></none>				
Grid SAS options= -set GAOvar OptionsSet1				

Details

Here are the result codes:

Table 8.2 GRDSVC_GETINFO Function Return Codes

Result Code	Explanation			
2	Reports that the specified server ID is not enabled for grid execution.			
1	Reports that the specified server ID is enabled for SMP execution.			
0	Reports that the specified server ID is enabled for a grid execution or that no error occurred.			
-1	Reports a syntax error in the function call. An example is that an empty string is specified for the server ID.			
-2	Reports a parsing error in the function call. An example is the failure to specify the SAS Application Server using the SASAPPSERVER= option.			
-3	Reports an invalid server ID in the function call.			
-5	Reports an out-of-memory condition while the function is executing.			
-6	Reports that an error occurred when the SAS Metadata Server was accessed or when the information was returned from the SAS Metadata Server.			

Example

```
/*-----*/
/* Show grid logical server definition for SAS Application Server 'SASApp'*/
```

See Also

RSUBMIT statement

• SAS/CONNECT User's Guide

SIGNON statement

• SAS/CONNECT User's Guide

DATA step

• SAS Language Reference: Dictionary

%SYSFUNC or %QSYSFUNC

• SAS Macro Language: Reference

GRDSVC_GETNAME Function

Reports the name of the grid node on which the SAS grid server session was chosen to execute.

Valid in: %SYSFUNC or %QSYSFUNC Macro, DATA step

Category: Grid

Syntax

grdsvc_getname(identifier)

Required Argument

identifier

identifies the server session that is executing on the grid. The identifier can be specified as follows:

is an empty string that is used to refer to the computer at which the statement is executed.

server-ID

specifies the server session that is executing on a grid.

You use the same server-ID that you used to sign on to a server session using the RSUBMIT statement or the SIGNON statement.

If the function is used in a DATA step, enclose server-ID in double or single quotation marks.

Example

```
/* The following sets the macro variable 'mynodea' to the name of
/* the grid node associated with the server ID 'task1'.
%let
mynodea=%sysfunc(grdsvc_getname(task1));
```

See Also

RSUBMIT statement

SAS/CONNECT User's Guide

SIGNON statement

SAS/CONNECT User's Guide

DATA step

• SAS Language Reference: Dictionary

%SYSFUNC or %QSYSFUNC

• SAS Macro Language: Reference

GRDSVC_NNODES Function

Reports the total number of job slots that are available for use on a grid.

Valid in: %SYSFUNC or %QSYSFUNC Macro, DATA step

Category: Grid

Syntax

grdsvc nnodes(argument;option)

Without Arguments

Required Argument

SASAPPSERVER=SAS-application-server

specifies the name of the SAS Application Server that has been defined in the SAS Metadata Repository. The SAS Application Server contains the definition for the logical grid server that is used to access the grid environment. The name of the SAS Application Server is passed to Platform Suite for SAS as a required resource. Platform Suite for SAS selects the grid nodes that meet the requirements for the specified SAS Application Server and returns the total number of job slots in the grid.

An exception to this behavior is when the SAS Application Server is disabled as a required resource for the grid server. For details, see the SASAPPSERVER= option for the GRDSVC ENABLE function on page 101.

Alias	SERVER=, RESOURCE=
Interaction	If <i>SAS-application-server</i> contains one or more spaces, the spaces are converted to underscores before the name is passed to Platform Suite for SAS.
Example	<pre>%let numofnodes%sysfunc(grdsvc_nnodes(server=SASApp));</pre>

Optional Argument

WORKLOAD=workload-value

identifies the resource for the type of job to be executed on the grid. This value specifies the workload requirements for which Platform Suite for SAS selects the grid nodes that contain these resources.

The specified workload value should match one of the workload values that are

	defined in the SAS Application Server in the SAS Metadata Repository.				
	Requirement	If you specify WORKLOAD=, you must also specify the SASAPPSERVER= option. Workload values are case sensitive.			
Interaction	If workload-value contains one or more spaces, the spaces are converted to underscores before the value is passed to Platform Suite for SAS. If workload-value is not located in the SAS Application Server definition and no other errors occur, a 0 result code is returned. A 0 result code means that no grid nodes contain the requested resources. Also, this note is displayed:				
		NOTE: Workload value "gridResource" does not exist in the SAS Metadata Repository.			
		If workload-value is undefined to Platform Suite for SAS, the GRDSVC_NNODES function returns the result code 0.			
	Tip	For Diatform Suite for SAS, this workload value corresponds with the			

Tip For Platform Suite for SAS, this workload-value corresponds with the resource that the LSF administrator has configured in the

lsf.cluster.cluster-name file and the lsf.shared file on the grid-control computer.

Example numofnodes=%sysfunc(grdsvc_nnodes(server=SASApp; workload=em)); The workload value, EM, specifies the resource name. EM must be assigned to a grid node in order to process this job. An example is assigning EM to machines that can process SAS Enterprise Miner jobs.

Details

When a grid environment is available, the GRDSVC_NNODES function returns the total number of job slots (busy and idle) that are available for job execution. This value is resolved when the function is called. Because of this, the value might vary over time, according to whether job slots have been added or removed from the grid. It can also vary based on the user, the queue that is being used, or other slot limits that are defined in the LSF configuration.

Here are the result codes:

Table 8.3 GRDSVC_NNODES Function Result Codes

Result Code	Explanation
nnn	If a grid environment is available, reports the total number of job slots (idle and busy) that have been configured in a grid environment. The grid contains the resources that are specified by the SASAPPSERVER= argument and the WORKLOAD= option.
	If a grid environment is not available, assumes a multi-processor (SMP) environment, and reports the value of the CPUCOUNT system option. In this case, the lowest value that can be reported is 1.
1	If a grid environment is not available, assumes a multi-processor (SMP) environment, and reports the value of the CPUCOUNT system option. In this case, the lowest value that can be reported is 1.
0	Reports that no grid nodes contain the requested resources.
-1	Reports a syntax error in the function call. For example, a syntax error would result from supplying no value, or an empty string, to the SASAPPSERVER= option.

Example

```
/*----*/
/* Get the number of grid nodes that have 'SASApp' as a resource
/*-----*/
%let NumNodes=%sysfunc(grdsvc nnodes(server=SASApp));
/*----*/
/* Get the number of grid nodes that have 'SASApp' 'EM' as resources
/*-----*/
numofnodes=%sysfunc(grdsvc nnodes(server=SASApp;workload=EM));
```

See Also

RSUBMIT statement

• SAS/CONNECT User's Guide

SIGNON statement

• SAS/CONNECT User's Guide

DATA step

• SAS Language Reference: Dictionary

CPUCOUNT= system option

• SAS Language Reference: Dictionary

Chapter 9

SASGSUB Command

SASGSUB Overview	115
Disabling SASGSUB Actions	116
Dictionary	116
SASGSUB Syntax: Submitting a SAS Program in Batch Mode	116
SASGSUB Syntax: Starting SAS in Interactive Mode	117
SASGSUB Syntax: Running a Command in Batch Mode	118
SASGSUB Syntax: Running a Command in Interactive Mode	119
SASGSUB Syntax: Ending a Job	120
SASGSUB Syntax: Viewing Job Status	120
SASGSUB Syntax: Retrieving Job Output	122
SASGSUB Syntax: Common Arguments	123
SASGSUB Syntax: Batch Options	126
SASGSUB Syntax: Grid Job Arguments	127

SASGSUB Overview

SAS Grid Manager Client Utility is a command-line utility that enables users to submit SAS programs, operating system commands, or command files to a grid for processing and to start interactive sessions on grid machines. This utility allows a grid client to submit SAS programs to a grid without requiring that SAS be installed on the machine performing the submission. It also enables jobs to be processed on the grid without requiring that the client remain active.

You can use the SAS Grid Manager Client Utility's SASGSUB command to submit jobs to the grid, start interactive sessions, view job status, retrieve results, and terminate jobs. The SAS Grid Manager Client Utility options can be specified in a configuration file so that they do not have to be entered manually. SASGSUB uses the sasgsub.cfg configuration file, which contains the required options. This file is automatically created by the SAS Deployment Wizard during installation. It stores the file in <config dir>/Applications/SASGridManagerClientUtiliy/<version>.

Platform LSF must be installed on any machine where the SAS Grid Manager Client Utility runs.

Disabling SASGSUB Actions

You might want to prevent users from using the SAS Grid Manager Client Utility to perform certain actions, such as terminating jobs. To disable these actions, you can specify these SasgsubDisable extended attributes on the grid server metadata definitions:

Sasg sub Disable GRID SUBMITPGM

prevents SAS jobs from being submitted

SasgsubDisableGRIDKILLJOB

prevents jobs from being terminated

Sasg sub Disable GRIDRUNCMD

prevents arbitrary commands from running in batch

SasgsubDisableGRIDRUNCMDINT

prevents arbitrary commands from running in an interactive session

S asg sub Disable GRIDRUNS ASLM

prevents an interactive SAS line mode session from starting

SasgsubDisableGRIDRUNSASDMS

prevents an interactive SAS Display Manager session from starting

You do not need to specify a value for these extended attributes.

Dictionary

SASGSUB Syntax: Submitting a SAS Program in Batch Mode

The following is the complete syntax for submitting a SAS program to a grid in batch mode. Enter the command on a Windows or UNIX command line.

Syntax

SASGSUB

-GRIDSUBMITPGM sas-program-file common_arguments batch_arguments <-GRIDRESTARTOK | -GRIDLRESTARTOK> <-GRIDSASOPTS grid-sas-options> <grid_job_arguments>

Required Arguments

-GRIDSUBMITPGM sas-program-file

specifies the path and filename of the SAS program that you want to run on the grid.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some arguments are optional. See

"SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

batch_arguments

specifies any of the arguments that are common to all SASGSUB commands that run in batch mode. Some arguments are required and some are optional. See "SASGSUB" Syntax: Batch Options" on page 126 for the syntax for each argument.

Optional Arguments

-GRIDRESTARTOK | -GRIDLRESTARTOK

specifies that the job can be restarted at a checkpoint or a label.

-GRIDSASOPTS grid-sas-options

specifies any SAS options that are applied to the SAS session started on the grid. Multiple options can be enclosed in quotation marks. If you are specifying options that contain quotation marks, you can enclose all of the options in parentheses before enclosing them in quotation marks. Each of these forms is valid:

GRIDSASOPTS option

GRIDSASOPTS "option1 option2"

GRIDSASOPTS "(option1 option2 option3)"

GRIDSASOPTS "(option1 option2 'option3')"

When SASGSUB runs, the outer set of quotation marks is removed.

grid job arguments

specifies any of the arguments valid when submitting jobs or commands to the grid. See "SASGSUB Syntax: Grid Job Arguments" on page 127 for the syntax for each of these arguments.

Example: Submitting a SAS Program to the Grid in Batch Mode

The following is an example of a SASGSUB statement used to submit the SAS program Lab report.sas in the directory C:\SAS programs to the grid in batch mode. The job has been enabled for restarting, and it needs to run in the overnight queue. The grid uses a shared file system.

SASGSUB -GRIDSUBMITPGM C:\SAS programs\Lab report.sas -GRIDRESTARTOK -GRIDJOBOPTS queue=overnight

SASGSUB Syntax: Starting SAS in Interactive Mode

The following is the complete syntax for starting SAS in interactive mode. You can use either line mode or SAS Display Manager mode to run SAS in a UNIX grid, with input coming from and output going to the client machine. SAS Display Manager mode also requires that an X server be present on the client machine. If you terminate SASGSUB in interactive mode, you also terminate the SAS session running in the grid.

Syntax

SASGSUB

-GRIDRUNSASLM | -GRIDRUNSASDMS

<hostname:>displaynumber<.screennumber>
common_arguments
<-GRIDWAITTIMEOUT seconds>
<grid_job_arguments>

Required Arguments

-GRIDRUNSASLM

specifies that the SASGSUB command runs a SAS session in line mode. Standard output and standard error are displayed by SASGSUB. SASGSUB also redirects standard input to the SAS session running on the grid.

-GRIDRUNSASDMS <hostname:>displaynumber<.screennumber>

specifies that the SASGSUB command runs in SAS Display Manager mode. Standard output and standard error are displayed by SASGSUB. The X Windows session is directed to the host and port specified by the *hostname:displaynumber.screennumber* options.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some are optional. See "SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

Optional Arguments

-GRIDWAITTIMEOUT timeout-value

specifies that the interactive SAS session is terminated when the *timeout-value* (in seconds) is reached.

grid job arguments

specifies any of the arguments that are valid when submitting jobs or commands to the grid. See "SASGSUB Syntax: Grid Job Arguments" on page 127 for the syntax for each of these arguments.

SASGSUB Syntax: Running a Command in Batch Mode

The following is the complete syntax for submitting a grid job to run a command in batch mode.

Syntax

SASGSUB

-GRIDRUNCMD command common_arguments batch_arguments <grid_job_arguments>

Required Arguments

-GRIDRUNCMD command

specifies a command that you want to run on the grid.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some are optional. See "SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

batch arguments

specifies any of the arguments that are common to all SASGSUB commands that run in batch mode. Some arguments are required and some are optional. See "SASGSUB Syntax: Batch Options" on page 126 for the syntax for each argument.

Optional Argument

grid job arguments

specifies any of the arguments valid when submitting jobs or commands to the grid. See "SASGSUB Syntax: Grid Job Arguments" on page 127 for the syntax for each of these arguments.

Example: Submitting a Command in Batch Mode

The following is an example of a SASGSUB batch mode statement used to submit a command to the grid to copy a set of files from the prod directory to the backup directory:

SASGSUB -GRIDRUNCMD "cp /prod/file1.* /backup"

SASGSUB Syntax: Running a Command in Interactive Mode

The following is the complete syntax for submitting a grid job to run a command interactively. If you terminate SASGSUB in interactive mode, you also terminate the SAS session running in the grid.

Syntax

SASGSUB

-GRIDRUNCMDINT command common arguments <-GRIDWAITTIMEOUT>timeout-value <grid job arguments>

Required Arguments

-GRIDRUNCMDINT command

specifies that an arbitrary command is run on the grid in interactive mode. Standard output and standard error is displayed on the user's machine. Standard input is redirected from the client to the grid.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some are optional. See "SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

Optional Arguments

-GRIDWAITTIMEOUT timeout-value

specifies that the SAS Grid Manager Client Utility waits until either the job has completed running (either successfully or with an error) or timeout-value (in seconds) is reached. If you use this option with -GRIDWAIT or -GRIDWAITRESULTS, it enables you to specify how long to wait for results.

grid job arguments

specifies any of the arguments valid when submitting jobs or commands to the grid. See "SASGSUB Syntax: Grid Job Arguments" on page 127 for the syntax for each of these arguments.

SASGSUB Syntax: Ending a Job

The following is the complete syntax for ending a job on a SAS grid. Enter the command on a Windows or UNIX command line.

Syntax

SASGSUB

-GRIDKILLJOB job-id | ALL common arguments

Required Arguments

-GRIDKILLJOB job-id | ALL

terminates the job specified by *job-id*. If you specify ALL, all jobs are terminated.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some are optional. See "SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

Example: Ending a Job

The following is an example of a SASGSUB statement used to end the job 61361 that is running on the grid:

SASGSUB -GRIDKILLJOB 61361

SASGSUB Syntax: Viewing Job Status

The following is the syntax for using SASGSUB to view the status of a job on a SAS grid. Enter the command on a Windows or UNIX command line.

Syntax

SASGSUB

-GRIDGETSTATUS job-id | ALL common arguments batch arguments

Required Arguments

-GRIDGETSTATUS job-id | ALL

displays the status of the job specified by job-id. If you specify ALL, the status of all jobs for the current user is displayed.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some are optional. See "SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

batch arguments

specifies any of the arguments that are common to all SASGSUB commands that run in batch mode. Some arguments are required and some are optional. See "SASGSUB Syntax: Batch Options" on page 126 for the syntax for each argument.

Examples

Example 1: Viewing the Status of a Single Job

The following is an example of a SASGSUB statement used to view the status of job 61361 that is running on the grid:

```
SASGSUB -GRIDGETSTATUS 61361
```

The output from the command looks like this:

Output 9.1 Status of a Single Job

```
Current Job Information
 Job 61361 (testPgm) is Finished: Submitted: 06Jan2011:10:28:57, Started:
06Jan2011:10:28:57 on Host d12345, Ended: 06Jan2011:10:28:57
```

Example 2: Viewing the Status of All Jobs

The following is an example of a SASGSUB statement used to view the status of all jobs running on the grid:

```
SASGSUB -GRIDGETSTATUS ALL
```

The output from the command looks like this:

Output 9.2 Status of All Jobs

```
Current Job Information
 Job 1917 (Pgm_01) is Finished: Submitted: 08May2011:10:28:57, Started:
08May2011:10:28:57 on Host d12345, Ended: 08May2011:10:28:57
 Job 1918 (Pgm 02) is Finished: Submitted: 08May2011:10:28:57, Started:
08May2011:10:28:57 on Host d12345, Ended: 08May2011:10:28:57
 Job 1919 (Pgm 03) is Finished: Submitted: 08May2011:10:28:57, Started:
08Ma2011:10:28:57 on Host d12345, Ended: 08May2011:10:28:57
 Job information in directory U:\jobs\GridSub\GridWork
\user1\SASGSUB-2011-05-11_13.17.17.327_testPgm is invalid.
 Job 1925 (Pgm 04) is Submitted: Submitted: 08May2011:10:28:57
```

SASGSUB Syntax: Retrieving Job Output

The following is the syntax for using SASGSUB to retrieve the output of a job that has completed processing on a SAS grid. Enter the command on a Windows or UNIX command line.

Syntax

SASGSUB

```
-GRIDGETRESULTS job-id | ALL
 common arguments batch arguments
 <-GRIDRESULTSDIR directory>
 <-GRIDFORCECLEAN> <-VERBOSE>
```

Required Arguments

-GRIDGETRESULTS job-id | ALL

Copies the job information from the work directory to the directory specified by -GRIDRESULTSDIR for the specified *job-id* or for all jobs. If you do not specify a value for -GRIDRESULTSDIR, the job information is copied to the current directory. An error results if the current directory cannot be written to.

common arguments

specifies any of the arguments that are common to all uses of the SASGSUB command. Some arguments are required and some are optional. See "SASGSUB Syntax: Common Arguments" on page 123 for the syntax for each argument.

batch arguments

specifies any of the arguments that are common to all SASGSUB commands that run in batch mode. Some arguments are required and some are optional. See "SASGSUB" Syntax: Batch Options" on page 126 for the syntax for each argument.

Optional Arguments

-GRIDRESULTSDIR directory

specifies the directory to which the job results are moved. If you do not specify a value for this argument, the default value is used, which is the current directory.

-GRIDFORCECLEAN

specifies that the job directory on the grid is deleted, regardless of whether the job was successful or not.

Examples

Example 1: Retrieving the Output of a Job

The following is an example of a SASGSUB statement used to view the output of job 61361 that is running on the grid:

```
SASGSUB -GRIDGETRESULTS 61361
```

The output from the command looks like this:

Output 9.3 Output of a Single Job

```
Current Job Information
 Job 61361 (testPgm) is Finished: Submitted: 06Jan2011:10:53:33, Started:
06Jan2011:10:53:33 on Host d15003, Ended: 06Jan2011:10:53:33
   Moved job information to .\SASGSUB-2011-01-06_21.52.57.130_testPgm
```

Example 2: Retrieving the Output of All Jobs

The following is an example of a SASGSUB statement used to view the output of all jobs on the grid:

```
SASGSUB -GRIDGETRESULTS ALL
```

The output from the command looks like this:

Output 9.4 Output of All Jobs

```
Current Job Information
 Job 1917 (Pgm1) is Finished: Submitted: 08Dec2008:10:53:33, Started:
08May2011:10:53:33 on Host d15003, Ended: 08May2011:10:53:33
   Moved job information to .\SASGSUB-2011-05-06 21.52.57.130 Pgm1
 Job 1918 (Pgm2) is Finished: Submitted: 08May2011:10:53:33, Started:
08May2011:10:53:33 on Host d15003, Ended: 08May2011:10:53:33
   Moved job information to .\SASGSUB-2011-05-06_13.13.39.167_Pgm2
 Job 1919 (Pgm3) is Finished: Submitted: 08May2011:10:53:34, Started:
08May2011:10:53:34 on Host d15003, Ended: 08May2011:10:53:34
   Moved job information to .\SASGSUB-2011-05-06_13.16.06.060_Pgm3
 Job information in directory U:\jobs\GridSub\GridWork
\user1\SASGSUB-2011-05-06_13.17.17.327_testPgm is invalid.
   Moved job information to .\SASGSUB-2011-05-06 13.17.17.327 Pgm4
 Job 1925 (Pgm4) is Submitted: Submitted: 08May2011:10:53:34
```

SASGSUB Syntax: Common Arguments

The following arguments are valid for all SASGSUB commands. Argument values that contain spaces must be contained in quotation marks.

Syntax

- -METASERVER server
- -METAUSER user-ID
- -METAPORT port
- -METAPASS password
- -METAPROFILE profile-name
- -METACONNECT connection-name
- -XMLCONFIGFILE pathname
- -GRIDAPPSERVER sas-application-server
- <-GRIDCONFIG grid-option-file >
- < -GRIDLICENSEFILE grid-enabled-license-file>
- <-LOGCONFIGLOC logging-option-file>
- <-GRIDLIBPATH path>
- <-VERBOSE>
- <-GRIDUSER grid-logon-username | PROMPT >
- <-GRIDPASSWORD grid-logon-password | PROMPT >
- <-GRIDPLUGINPATH grid-jar-file-path>
- <-JREOPTIONS java-runtime-options>

Required Arguments

-GRIDAPPSERVER sas-application-server

specifies the name of the SAS Application Server that contains the grid's logical grid server definition. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

-METASERVER server

specifies the name or IP address of the SAS Metadata Server.

You must specify either -METASERVER, -METAPORT, -METAUSER, and

- -METAPASS; or -METAPROFILE and -METACONNECT; or
- -XMLCONFIGFILE. You cannot specify more than one group of options.

This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

-METAPORT port

specifies the port to use to connect to the SAS Metadata Server specified by the -METASERVER argument. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

-METAUSER user-ID

specifies the user ID to use to connect to the SAS Metadata Server specified by the -METASERVER argument. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard. Specify _PROMPT_ for user-ID to specify that the SAS Grid Manager Client Utility prompts the user for a user ID.

-METAPASS password | PROMPT

specifies the password of the user specified in the -METAUSER argument. If the value of the argument is set to _PROMPT_, the user is prompted for a password. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

-METAPROFILE profile_pathname

specifies the pathname of the connection profile for the SAS Metadata Server.

You must specify either -METASERVER, -METAPORT, -METAUSER, and -METAPASS; or -METAPROFILE and -METACONNECT; or

-XMLCONFIGFILE. You cannot specify more than one group of options.

This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

If you are using a clustered metadata server, you can use -METAPROFILE to specify the clustered metadata server definition XML file. In this scenario, you do not need to specify the -METACONNECT option.

-METACONNECT connection-name

specifies the name of the connection to use when connecting to the SAS Metadata Server. The connection must be defined in the metadata profile specified in the -METAPROFILE argument. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

-XMLCONFIGFILE pathname

specifies the path to an XML file that contains the metadata profile connection information.

You must specify either -METASERVER, -METAPORT, -METAUSER, and

-METAPASS; or -METAPROFILE and -METACONNECT; or

-XMLCONFIGFILE. You cannot specify more than one group of options.

Optional Arguments

-GRIDLICENSEFILE grid-enabled-license-file

specifies the path and filename of a SAS license file that contains the SAS Grid Manager license. The default value is to retrieve the license file information from metadata. If specified, the location must point to a valid SID file that contains a SAS Grid Manager license. Do not use this option unless instructed by SAS Technical Support.

-GRIDCONFIG grid-option-file

specifies the path and filename of a file containing other SASGSUB options. The default value is sasgsub.cfg.

-LOGCONFIGLOC logging-option-file

specifies the path and name of a file containing any options for the SAS logging facility. SASGSUB uses the App. Grid logger name with these keys:

App.Grid.JobID specifies the job ID as returned by Platform Suite

for SAS.

specifies the job name. App.Grid.JobName

specifies the job status. Possible values are App.Grid.JobStatus

Submitted, Running, or Finished.

App.Grid.JobDir specifies the job directory name.

specifies the full path of job directory. App.Grid.JobDirPath

App.Grid.JobSubmitTime specifies the time at which the job was submitted.

specifies the time at which the job started running. App.Grid.JobStartTime

App.Grid.JobEndTime specifies the time at which the job completed.

App.Grid.JobHost specifies the host that ran the job.

-GRIDLIBPATH path

the path to the shared libraries used by the utility. This value is set in the configuration file and should not be altered. The path cannot contain spaces.

-VERBOSE

specifies that extra debugging information is printed. If this argument is not specified, only warning and error messages are printed.

-GRIDUSER grid-logon-password | PROMPT

specifies the user name to be used to log on to the grid, if required by the grid provider. This option is not required if the grid uses Platform Suite for SAS. Specify _PROMPT_ for *grid-logon-username* to specify that the SAS Grid Manager Client Utility prompts the user for a user ID.

-GRIDPASSWORD grid-logon-password | PROMPT

specifies the password to log on to the grid, if required by the grid provider. This option is not required if the grid uses Platform Suite for SAS. Specify _PROMPT_ for *grid-logon-password* to specify that the SAS Grid Manager Client Utility prompts the user for a password.

-GRIDPLUGINPATH grid-jar-file-path1 ... grid-jar-file-pathN

specifies a list of paths to search for additional grid provider JAR files. Paths are separated by semicolons and cannot contain spaces. This option is not required if the grid uses Platform Suite for SAS.

-JREOPTIONS java-runtime-options

specifies any Java run-time options that are passed to the Java Virtual Machine. This argument is required if you are using a grid provider other than Platform Suite for SAS. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

SASGSUB Syntax: Batch Options

The following options are used when running SASGSUB in batch mode. Argument values that contain spaces must be contained in quotation marks.

Syntax

- -GRIDWORK work-directory
- <-GRIDWORKREM shared-file-system-path>
- <-GRIDFILESIN grid-file-list>
- <-GRIDSTAGECMD command>
- <-GRIDSTAGEHOST hostname>
- <-GRIDWAIT>
- <-GRIDWAITTIMEOUT>timeout-value
- <-GRIDWAITRESULTS>
- <-GRIDWATCHOUTPUT>

Required Argument

-GRIDWORK work-directory

specifies the path for the shared directory that the job uses to store the program, output, and job information. On Windows, the path can contain spaces, but must be in quotation marks. On UNIX, the path cannot contain spaces. This option is stored in the configuration file that is automatically created by the SAS Deployment Wizard.

Optional Arguments

-GRIDWORKREM shared-file-system-path

when using a shared file system, specifies the pathname of the GRIDWORK directory in the shared file system relative to a grid node. Use this argument when the machine used to submit the job is on a different platform than the grid. The path cannot contain spaces.

When you are using file staging, this artument specifies the location of the GRIDWORK directory as passed to the GRIDSTAGECMD parameter. For example, Windows clients could have GRIDWORK set to \myServer\myShare \SharedPath with the grid using LSRCP to stage files with GRIDSTAGEFILEHOST set to myserver.mydomain.com. If you set Windows to map C:\myShare on myServer to the Windows share \\myServer\myShare, you would set GRIDWORKREM to C:\myShare\SharedPath.

-GRIDFILESIN grid-file-list

specifies a comma-separated list of files that need to be moved to the grid work directory before the job starts running.

-GRIDSTAGECMD command

specifies the remote copy command used to stage files to the grid. Valid values are LSRCP, RCP, SCP, or SMBCLIENT. This option is used when the grid client machines and the grid machines do not share a common directory structure.

-GRIDSTAGEHOST hostname

specifies the name of the host that stores files that are staged into the grid. This option is used when a machine submits files to the grid and then shuts down.

-GRIDWAIT

specifies that the SAS Grid Manager Client Utility waits until the job has completed running, either successfully or with an error. If the job does not complete, it must be ended manually.

-GRIDWAITTIMEOUT timeout-value

specifies that the SAS Grid Manager Client Utility waits until either the job has completed running (either successfully or with an error) or timeout-value (in seconds) is reached. If you use this option with -GRIDWAIT or -GRIDWAITRESULTS, it enables you to specify how long to wait for results.

-GRIDWAITRESULTS

specifies that the SAS Grid Manager Client Utility waits until the job has completed running (either successfully or with an error). It then returns the results of the processing. If the job does not complete, it must be ended manually.

-GRIDWATCHOUTPUT

specifies that the output of what was submitted by the SASGSUB command is displayed on the user's machine. If this argument is used with -GRIDSUBMITPGM, the SAS log and output are displayed. If the argument is used with -GRIDRUNCMD, the command's standard output and standard error are displayed. While the output is being displayed, entering the command prompt does not affect the processing in the grid.

SASGSUB Syntax: Grid Job Arguments

The following arguments are used when submitting a SAS job or command to the grid. Argument values that contain spaces must be contained in quotation marks.

Syntax

- <-GRIDJOBNAME grid-program-name>
- <-GRIDJOBOPTS grid-provider-options >
- <-GRIDOPTSET> options-set-name
- <-GRIDWORKLOAD grid-resource-names>

Optional Arguments

-GRIDJOBNAME grid-program-name

specifies the name of the grid job as it appears on the grid. If this argument is not specified, the SAS program name is used.

-GRIDJOBOPTS grid-provider-options

specifies any options that are passed to the grid provider when the job is submitted. You can separate multiple options with spaces or with semicolons. If you use spaces, you must enclose the option string in quotation marks. See Appendix 1, "Supported Job Options," on page 131.

-GRIDOPTSET options-set-name

specifies the name of a grid options set to be used in job processing. This option is needed only if there is more than one grid options set associated with the current SAS Grid Manager Client Utility user. If there is only one grid options set for the user, it is used by default. A grid options set is a collection of grid options, SAS options, and required resources that are associated with a particular SAS client application and SAS user or group.

-GRIDWORKLOAD grid-resource-name

specifies a resource name to use when submitting the job to the grid.

Part 3

Appendix

Appendix 1			
Supported Job Options .	 	 	131

Appendix 1

Supported Job Options

The following table lists the job options that are supported by Platform Suite for SAS. You can specify these options in these locations:

- the JOBOPTS= option of the GRDSVC_ENABLE function
- the **Additional Options** field in the metadata definition for the SAS Logical Grid Server

Options specified in metadata override those specified in a GRDSVC_ENABLE statement.

Table A1.1 Platform Suite for SAS Job Option Name/Value Pairs

Job Option Name/Value Pairs	Explanation
app=grid_application_name	specifies the LSF application name to use. This option is valid only for LSF version 7 and higher.
exclusive=0 1	specifies whether the job runs as the only job on the grid node. 0 means that the job does not run exclusively; 1 means that the job runs exclusively. The default is 0.
ignoreFull=value	if value is anything other than 0, specifies that during object spawner load balancing, SAS Grid Manager ignores the closed status of a host if the host is closed because it is full of jobs. If the value is 0, a host that is closed because it is full is not used for the next server.
jobgroup=job-group	specifies the name of the job group to associate with the job.
jobname=job_name	specifies a job name to be used for all jobs. The name specified in this option overrides any job name specified by an application.
jobSlots=number_of_slots	specifies the number of available job slots for the grid. Use this option in configurations where the grid is controlled by Platform Computing's Enterprise Grid Orchestrator (EGO). EGO always shows grid hosts as being closed. However, specifying a high value for this option shows the grid as being open and enables jobs to be submitted to the grid.

Job Option Name/Value Pairs	Explanation
maxpendingtime=time	specifies the number of seconds a job can wait in the pending state before it is terminated.
priority=job-priority	specifies the user-assigned job priority. This is a value between 1 and MAX_USER_PRIORITY, as defined in the lsb.params file.
project= <i>project</i> v	specifies the name of the project to associate with the job.
queue=queue	specifies the name of the queue to put the job in. The default queue name is normal .
reqres="requested-resources"	specifies additional resource requirements.
runlimit=time-in-seconds	specifies the maximum amount of time that a job is allowed to run. This value is used as an absolute limit or as part of an SLA job.
sla=service-level-agreement	specifies the name of the service-level agreement to associate with the job.
usergroup=user-group	specifies the name of the user group.

For complete information about job options, see *Platform LSF Reference*.

Glossary

application server

a server that is used for storing applications. Users can access and use these server applications instead of loading the applications on their client machines. The application that the client runs is stored on the client. Requests are sent to the server for processing, and the results are returned to the client. In this way, little information is processed by the client, and nearly everything is done by the server.

authentication

the process of verifying the identity of a person or process within the guidelines of a specific authorization policy.

authentication domain

a SAS internal category that pairs logins with the servers for which they are valid. For example, an Oracle server and the SAS copies of Oracle credentials might all be classified as belonging to an OracleAuth authentication domain.

grid

a collection of networked computers that are coordinated to provide load balancing of multiple SAS jobs, scheduling of SAS workflows, and accelerated processing of parallel jobs.

grid computing

a type of computing in which large computing tasks are distributed among multiple computers on a network.

grid control server

the machine on a grid that distributes SAS programs or jobs to the grid nodes. The grid control server can also execute programs or jobs that are sent to the grid.

grid monitoring server

a metadata object that stores the information necessary for the Grid Manager plug-in in SAS Management Console to connect with the Platform Suite for SAS to allow monitoring and management of the grid.

grid node

a machine that is capable of receiving and executing work that is distributed to a grid.

identity

See metadata identity.

job

a metadata object that specifies processes that create output.

load balancing

for IOM bridge connections, a program that runs in the object spawner and that uses an algorithm to distribute work across object server processes on the same or separate machines in a cluster.

logical grid server

a metadata object that stores the command that is used by a grid-enabled SAS program to start a SAS session on a grid.

logical server

in the SAS Metadata Server, the second-level object in the metadata for SAS servers. A logical server specifies one or more of a particular type of server component, such as one or more SAS Workspace Servers.

login

a SAS copy of information about an external account. Each login includes a user ID and belongs to one SAS user or group. Most logins do not include a password.

metadata identity

a metadata object that represents an individual user or a group of users in a SAS metadata environment. Each individual and group that accesses secured resources on a SAS Metadata Server should have a unique metadata identity within that server.

metadata repository

a collection of related metadata objects, such as the metadata for a set of tables and columns that are maintained by an application. A SAS Metadata Repository is an example.

metadata server

a server that provides metadata management services to one or more client applications. A SAS Metadata Server is an example.

plug-in

a file that modifies, enhances, or extends the capabilities of an application program. The application program must be designed to accept plug-ins, and the plug-ins must meet design criteria specified by the developers of the application program. In SAS Management Console, a plug-in is a JAR file that is installed in the SAS Management Console directory to provide a specific administrative function. The plug-ins enable users to customize SAS Management Console to include only the functions that are needed.

SAS Management Console

a Java application that provides a single user interface for performing SAS administrative tasks.

SAS Metadata Repository

one or more files that store metadata about application elements. Users connect to a SAS Metadata Server and use the SAS Open Metadata Interface to read metadata from or write metadata to one or more SAS Metadata Repositories. The metadata types in a SAS Metadata Repository are defined by the SAS Metadata Model.

SAS Metadata Server

a multi-user server that enables users to read metadata from or write metadata to one or more SAS Metadata Repositories. The SAS Metadata Server uses the Integrated Object Model (IOM), which is provided with SAS Integration Technologies, to communicate with clients and with other servers.

SAS Workspace Server

a SAS IOM server that is launched in order to fulfill client requests for IOM workspaces. See also IOM server and workspace.

Index

A	central file server 12
accelerated processing 3	client applications 17
addresource utility 13	grid 5, 11
addresses	grid control server 12
grid server address 19	grid environment 11
host address 90	grid nodes 17
IP address of grid nodes 106	Platform Suite for SAS 12
analysis on data 9	queues 28
applications	SAS Grid Manager Client Utility 21
configuring client applications 17 grid enabling 40	SAS products and metadata definitions
SAS applications supporting grid	sasgsub.cfg file 23
processing 7	connections
asynchronous rsubmits 42	maintaining connection to the grid 53
authentication domain 19, 20	refused 94
	timed out 94
	connectivity
В	host 90
batch jobs 7	testing for 94
submitting to grid 43	CPU utilization thresholds 53
business problems 8	critical service failover 65
high availability 9	
increased data growth 9	
many users on single resource 8	D
need for flexible IT infrastructure 10	data analysis 9
running larger and more complex	flexible IT infrastructure and 10
analysis 9	data growth 9
	data volume 9
_	debug jobs 93
С	distributed enterprise scheduling 7
Calendar Editor 0	distributed parallel execution of jobs 48
central file server 5	DNS resolution 68
configuring 12	
checkpoint restart 69	_
clients	E
configuring client applications 17	ending jobs 45, 85, 120
grid clients 6	environment
running jobs and 96	information about grid environment
complexity of analysis 9	107
computer failure 10	verifying Platform Suite for SAS
configuration	environment 91

verifying SAS environment 93	planning and configuring 11
	grid maintenance 84
	closing and reopening hosts 87
F	displaying job graphs 86
failover	managing jobs 85
of critical services 65	managing queues 88
of SAS programs 66	viewing grid information 84
Flow Manager 0	grid management 25
functions 101	defining resources 36
	grid options sets 31
	overview 25
G	queues 28
Gantt charts 86	specifying job slots 27
GMS (Grid Management Services) 4	Grid Management Services (GMS) 4
graphs	Grid Manager plug-in 4, 83
displaying job graphs 86	closing and reopening hosts 87
GRDSVC ENABLE function 101	displaying job graphs 86
result codes 105	job views 83
specifying resource names 37	maintaining the grid 84
GRDSVC GETADDR function 106	managing jobs 85
GRDSVC GETINFO function 107	managing queues 88
result codes 109	viewing grid information 84
GRDSVC GETNAME function 110	grid metadata 17
GRDSVC NNODES function 111	verifying 93
result codes 113	grid monitoring
grid	verifying 94
comparing submission methods 48	grid monitoring server
configuring 5, 11	modifying definitions 20
enabling or disabling grid execution	verifying SAS grid metadata 94
101	viewing grid information 84
information about 84, 107	grid nodes 5
installing Platform Suite for SAS 12	configuring 17
maintaining connection to 53	IP address of 106
grid clients 6	name of 110
jobs running on 96	number of grid nodes is zero 95
Grid Command property 18	required software components for 17
grid computing 3	testing connectivity to 94
business problems solved by 8	grid options sets 26, 31
processing types 6	creating 32
grid control machine 92	mapping 34
grid control server 5	merging option values 31
configuring 12	grid processing
grid enabling 40	processing types supported 6
distributed parallel execution of jobs 48	SAS applications supporting 7
SAS Add-In for Microsoft Office and	grid server
50	address 19
SAS Data Integration Studio and 54	port 19
SAS Display Manager and 40	updating definitions for partitioning 57
SAS Enterprise Guide and 50	grid syntax 4
SAS Enterprise Miner and 57	grid topology 5
SAS Grid Manager for workspace	grid-launched workspace servers 60
server load balancing 59	GRIDOPTSET= option
SAS Risk Dimensions and 59	GRDSVC ENABLE function 102, 109
scheduling jobs on grid 47	
grid environment	
information about 107	

H	machines that are only grid clients 96
hardware load balancer 67	managing 85
high availability	prioritizing 54
and critical applications 66	queue for short jobs 30
overview 9	restarting 69
high-priority queues 29	resuming 85
host name 20	retrieving output 45, 122
hosts	status of 45, 120
addresses 90	submitting batch jobs to grid 43
closing and reopening 87	submitting from Program Editor to grid
connectivity 90	41
information about 84	submitting with SASGSUB command
ports 90	116, 117
	suspending 85
	terminating 45, 85, 120
I	verifying LSF job execution 93
installation 11	verifying SAS job execution 94
Platform Suite for SAS 12	viewing log and output lines from 42
Platform Suite for SAS, on UNIX 13	
SAS Grid Manager Client Utility 21	
SAS products and metadata definitions	L
11	label restart 69
interactively developing SAS programs	LIBNAME statement
53	assigning SAS Add-In for Microsoft
invalid resource request 95	Office libraries 52
invalid userid or password 94	assigning SAS Enterprise Guide
IP address of grid nodes 106	libraries 52
IT infrastructure 10	libraries
iterative processing 7	assigning SAS Add-In for Microsoft
	Office libraries 52
_	assigning SAS Enterprise Guide
J	libraries 52
job	browsing with SAS Explorer Window
requeuing 70	42
job graphs 86	license
job options 131	for SAS Grid Manager 95
job scheduling	license file 92
See scheduling jobs	load balancer 67
job slots 26	load balancing
increasing 53	multi-user workload balancing with
specifying 27	SAS Data Integration Studio 54
specifying limits on a queue 30	SAS Grid Manager for workspace
total number available on grid 111	server load balancing 59
job views 83	Load Sharing Facility (LSF) 4
JOBNAME= option	specifying job slots 27
GRDSVC_ENABLE function 103	specifying workload for Loop Transformation 57
JOBOPTS= option CRDSVC_ENABLE function 104	
GRDSVC_ENABLE function 104	terminating LSF jobs 79, 85
jobs	verifying J SE is running 01
See also scheduling jobs	verifying LSF is running 91
comparing grid submission methods 48	verifying setup 92
debug jobs 93	log lines
distributed parallel processing 48	viewing from grid jobs 42
ending 45, 85, 120 failure to start 95	logical grid server modifying definitions 17
information about 84	verifying SAS grid metadata 93
miormation about 07	vornymg omo gnu metadata 73

Loop Transformation	P
specifying workload for 57	parallel execution, distributed 48
LSF	parallel scoring 58
See Load Sharing Facility (LSF)	parallel workload balancing 7, 55
See Load Sharing Facility (LSF)	partitions 26
	updating grid server definitions for 57
М	1 00
	password invalid 94
maintenance issues 10	performance
many users on single resource 8	assigning SAS Add-In for Microsoft
merging option values 31	Office libraries 52
METAAUTORESOURCES option	assigning SAS Enterprise Guide
assigning SAS Add-In for Microsoft	libraries 52
Office libraries 52	ping command 90
assigning SAS Enterprise Guide	planning grid environment 11
libraries 52	Platform RTM for SAS
metadata	downloading 4
modifying logical grid server definitions	functions 4
17	host name 20
verifying SAS grid metadata 93	Platform Suite for SAS 4
metadata definitions	components 4
installing and configuring 11	installing and configuring 12
metadata server 6	installing on UNIX 13
verifying grid metadata 93	supported job options 131
model scoring 57	verifying environment 91
model training 57	verifying LSF job execution 93
Module Name property 20	verifying LSF setup 92
monitoring	verifying that LSF is running 91
verifying 94	PM (Process Manager) 4
multi-user workload balancing 6, 54	ports 20
	grid server port 19
	verifying host ports 90
N	pre-assigned libraries
names	assigning SAS Add-In for Microsoft
grid nodes 110	Office libraries 52
host name 20, 32	assigning SAS Enterprise Guide
Module Name property 20	libraries 52
specifying resource names 37	prioritizing jobs 54
network setup verification 90	Process Manager (PM) 4
host addresses 90	processing types 6
host connectivity 90	distributed enterprise scheduling 7
host ports 90	multi-user workload balancing 6
night queues 29	parallel workload balancing 7
nodes	processing, iterative 7
See grid nodes	profile.lsf file 13
NORMAL queue 28	Program Editor
	submitting jobs to grid from 41
	programs
0	developing interactively with SAS Add-
OLAP servers	In for Microsoft Office 53
converting to grid load balancing 61	developing interactively with SAS
option values	Enterprise Guide 53
merging with grid options sets 31	Provider property 18, 20
Options property 20	· ·
output	
retrieving 45, 122	Q
viewing output lines from grid jobs 42	queues 26, 28
- · · · · · · · · · · · · · · · · · · ·	-

activating 88	scheduling jobs 54
activating 88 closing 88	specifying resource names 37
configuring 28	specifying workload for Loop
for short jobs 30	Transformation 57
high-priority 29	updating grid server definitions for
inactivating 88	partitioning 57
information about 84	SAS Deployment Wizard
	configuring grid control server 12
managing 88 mismatch with workspace servers 31	configuring grid nodes 17
night queue 29	SAS Display Manager 40
NORMAL queue 28	browsing libraries with SAS Explorer
opening 88	Window 42
server specification 31	submitting jobs from Program Editor to
specifying 28	grid 41
specifying job slot limits on 30	viewing log and output lines from grid jobs 42
	SAS Enterprise Guide
R	assigning libraries 52
refused connection 94	developing SAS programs interactively
requeuing 70	53
required resources 32	grid enabling and 50
resource names	maintaining connection to the grid 53
specifying in grid options sets 32	setting workload values 53
specifying in SAS Data Integration	users 25
Studio 37	SAS Enterprise Miner
specifying with GRDSVC_ENABLE	grid enabling and 57
function 37	users 25
specifying with SAS Grid Manager	SAS environment
Client Utility 37	verifying 93
resources	verifying grid metadata 93
many users on single resource 8	verifying grid monitoring 94
specifying LSF resources for Loop	verifying SAS job execution 94
Transformation 57	SAS Explorer Window
specifying names 37	browsing libraries 42
restart	SAS Grid Manager 3
checkpoint and label 69	components 4
restarting jobs 69	for workspace server load balancing 59
resuming jobs 85	grid enabling and 59
rsubmits, asynchronous 42	license for 95
	loading 95
	multi-user workload balancing 6
S CALLAND A DE CALLAND	parallel workload balancing 7
SAS Add-In for Microsoft Office	SAS Grid Manager Client Utility 43
assigning libraries 52	ending jobs 45
developing SAS programs interactively 53	ending jobs with SASGSUB command 120
grid enabling and 50	installing and configuring 21
SAS applications	retrieving job output 45, 122
grid enabling 40	SASGSUB command 115
specifying as grid capable 34	specifying resource names 37
supporting grid processing 7	submitting batch jobs to grid 44
SAS Code Analyzer 48	submitting jobs 48, 116, 117
SAS Data Integration Studio	viewing job status 45, 120
grid enabling and 54	SAS grid metadata
multi-user workload balancing with 54	verifying 93
parallel workload balancing with 55	SAS language statements

submitting jobs to grid 48 SAS Management Console 6 Schedule Manager plug-in 7, 48 SAS Metadata Server 6 verifying grid metadata 93 SAS products installing and configuring 11 SAS program failover 66	timed out connection 94 troubleshooting 89 overview of process 89 verifying network setup 90 verifying Platform Suite for SAS environment 91 verifying SAS environment 93
SAS programs	
developing interactively with SAS Add-	U
In for Microsoft Office 53	UNIX
developing interactively with SAS	0 - 1
Enterprise Guide 53	installing Platform Suite for SAS 13 userid invalid 94
SAS Risk Dimensions	
	users
grid enabling and 59	categories of 25
users 26	many users on single resource 8
SAS sessions	utilization thresholds, CPU 53
enabling or disabling 101	
IP address of grid nodes 106	
name of grid node 110	V
SAS Web Report Studio users 25	verification
SAS Workspace Servers	grid monitoring 94
SAS Grid Manager for load balancing	grid monitoring server 94
59	host addresses 90
SASAPPSERVER= option	host connectivity 90
GRDSVC_ENABLE function 102	host ports 90
SASGSUB command 115	logical grid server 93
ending jobs 120	LSF job exeuction 93
overview 115	LSF setup 92
retrieving job output 122	network setup 90
submitting jobs 116, 117	Platform Suite for SAS environment 91
viewing job status 120	SAS environment 93
sasgsub.cfg file 23	SAS grid metadata 93
SCAPROC procedure 48	SAS job execution 94
Schedule Manager plug-in 7	that LSF is running 91
submitting jobs to grid 48	volume of data 9
scheduling jobs 3, 47	
distributed enterprise scheduling 7	14/
SAS Data Integration Studio jobs 54	W
scoring code 58	workflow
short jobs queue 30	controlling with queues 28
single resource	workload
many users on 8	specifying for Loop Transformation 57
submitting jobs	workload balancing 3
comparing grid submission methods 48	multi-user 6, 54
from Program Editor to grid 41	parallel 7, 55
submitting batch jobs to grid 43	workload values
with SASGSUB command 116, 117	setting for SAS Enterprise Guide 53
subtasks 3, 7	WORKLOAD= option
suspending jobs 85	GRDSVC_ENABLE function 103
	workspace servers
_	converting to grid load balancing 61
T	grid-launched 60
terminating jobs 45, 85, 120	SAS Grid Manager for load balancing
testing connectivity 94	59
thresholds, CPU utilization 53	stared by object spawner 60