

SAS/STAT® 13.2 User's Guide The FACTOR Procedure



This document is an individual chapter from SAS/STAT® 13.2 User's Guide.

The correct bibliographic citation for the complete manual is as follows: SAS Institute Inc. 2014. SAS/STAT® 13.2 User's Guide. Cary, NC: SAS Institute Inc.

Copyright © 2014, SAS Institute Inc., Cary, NC, USA

All rights reserved. Produced in the United States of America.

For a hard-copy book: No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, or otherwise, without the prior written permission of the publisher, SAS Institute Inc.

For a Web download or e-book: Your use of this publication shall be governed by the terms established by the vendor at the time you acquire this publication.

The scanning, uploading, and distribution of this book via the Internet or any other means without the permission of the publisher is illegal and punishable by law. Please purchase only authorized electronic editions and do not participate in or encourage electronic piracy of copyrighted materials. Your support of others' rights is appreciated.

U.S. Government License Rights; Restricted Rights: The Software and its documentation is commercial computer software developed at private expense and is provided with RESTRICTED RIGHTS to the United States Government. Use, duplication or disclosure of the Software by the United States Government is subject to the license terms of this Agreement pursuant to, as applicable, FAR 12.212, DFAR 227.7202-1(a), DFAR 227.7202-3(a) and DFAR 227.7202-4 and, to the extent required under U.S. federal law, the minimum restricted rights as set out in FAR 52.227-19 (DEC 2007). If FAR 52.227-19 is applicable, this provision serves as notice under clause (c) thereof and no other notice is required to be affixed to the Software or documentation. The Government's rights in Software and documentation shall be only those set forth in this Agreement.

SAS Institute Inc., SAS Campus Drive, Cary, North Carolina 27513.

August 2014

SAS provides a complete selection of books and electronic products to help customers use SAS® software to its fullest potential. For more information about our offerings, visit **support.sas.com/bookstore** or call 1-800-727-3228.

SAS® and all other SAS Institute Inc. product or service names are registered trademarks or trademarks of SAS Institute Inc. in the USA and other countries. ® indicates USA registration.

Other brand and product names are trademarks of their respective companies.



Gain Greater Insight into Your SAS® Software with SAS Books.

Discover all that you need on your journey to knowledge and empowerment.





Chapter 37

The FACTOR Procedure

		4		4
	on	tρ	n	tc
v	1711			

nts	
Overview: FACTOR Procedure	2296
Background	2296
Outline of Use	2299
Getting Started: FACTOR Procedure	2304
Syntax: FACTOR Procedure	2309
PROC FACTOR Statement	2309
BY Statement	2325
FREQ Statement	2325
PARTIAL Statement	2326
PATHDIAGRAM Statement	2326
PRIORS Statement	2331
VAR Statement	2331
WEIGHT Statement	2331
Details: FACTOR Procedure	2332
Input Data Set	2332
Output Data Sets	2334
Confidence Intervals and the Salience of Factor Loadings	2336
Simplicity Functions for Rotations	2337
Missing Values	2338
Cautions	2338
Factor Scores	2339
Variable Weights and Variance Explained	2340
Heywood Cases and Other Anomalies about Communality Estimates	2341
Time Requirements	2342
Displayed Output	2343
ODS Table Names	2347
ODS Graphics	2349
Examples: FACTOR Procedure	2350
Example 37.1: Principal Component Analysis	2350
Example 37.2: Principal Factor Analysis	2356
Example 37.3: Maximum Likelihood Factor Analysis	2374
Example 37.4: Using Confidence Intervals to Locate Salient Factor Loadings	2380
Example 37.5: Creating Path Diagrams for Factor Solutions	2384
References	2390

Overview: FACTOR Procedure

The FACTOR procedure performs a variety of common factor and component analyses and rotations. Input can be multivariate data, a correlation matrix, a covariance matrix, a factor pattern, or a matrix of scoring coefficients. The procedure can factor either the correlation or covariance matrix, and you can save most results in an output data set.

PROC FACTOR can process output from other procedures. For example, it can rotate the canonical coefficients from multivariate analyses in the GLM procedure.

The methods for factor extraction are principal component analysis, principal factor analysis, iterated principal factor analysis, unweighted least squares factor analysis, maximum likelihood (canonical) factor analysis, alpha factor analysis, image component analysis, and Harris component analysis. A variety of methods for prior communality estimation is also available.

Specific methods for orthogonal rotation are varimax, quartimax, biquartimax, equamax, parsimax, and factor parsimax. Oblique versions of these methods are also available. In addition, quartimin, biquartimin, and covarimin methods for (direct) oblique rotation are available. General methods for orthogonal rotation are orthomax with user-specified gamma, Crawford-Ferguson family with user-specified weights on variable parsimony and factor parsimony, and generalized Crawford-Ferguson family with user-specified weights. General methods for oblique rotation are direct oblimin with user-specified tau, Crawford-Ferguson family with user-specified weights on variable parsimony and factor parsimony, generalized Crawford-Ferguson family with user-specified weights, promax with user-specified exponent, Harris-Kaiser case II with user-specified exponent, and Procrustes with a user-specified target pattern.

Output includes means, standard deviations, correlations, Kaiser's measure of sampling adequacy, eigenvalues, a scree plot, eigenvectors, prior and final communality estimates, the unrotated factor pattern, residual and partial correlations, the rotated primary factor pattern, the primary factor structure, interfactor correlations, the reference structure, reference axis correlations, the variance explained by each factor both ignoring and eliminating other factors, plots of both rotated and unrotated factors, squared multiple correlation of each factor with the variables, standard error estimates, confidence limits, coverage displays, scoring coefficients, and path diagrams.

The FACTOR procedure uses ODS Graphics to create graphs as part of its output. For general information about ODS Graphics, see Chapter 21, "Statistical Graphics Using ODS."

Any topics that are not given explicit references are discussed in Mulaik (1972) or Harman (1976).

Background

See Chapter 79, "The PRINCOMP Procedure," for a discussion of principal component analysis. See Chapter 29, "The CALIS Procedure," for a discussion of confirmatory factor analysis.

Common factor analysis was invented by Spearman (1904). Kim and Mueller (1978a, b) provide a very elementary discussion of the common factor model. Gorsuch (1974) presents a broad survey of factor analysis, and Gorsuch (1974) and Cattell (1978) are useful as guides to practical research methodology. Harman (1976) gives a lucid discussion of many of the more technical aspects of factor analysis, especially oblique rotation. Morrison (1976) and Mardia, Kent, and Bibby (1979) provide excellent statistical treatments of common factor analysis. Mulaik (1972) provides the most thorough and authoritative general reference on

factor analysis and is highly recommended to anyone familiar with matrix algebra. Stewart (1981) gives a nontechnical presentation of some issues to consider when deciding whether or not a factor analysis might be appropriate.

A frequent source of confusion in the field of factor analysis is the term *factor*. It sometimes refers to a hypothetical, unobservable variable, as in the phrase *common factor*. In this sense, *factor analysis* must be distinguished from component analysis since a component is an observable linear combination. *Factor* is also used in the sense of *matrix factor*, in that one matrix is a factor of a second matrix if the first matrix multiplied by its transpose equals the second matrix. In this sense, *factor analysis* refers to all methods of data analysis that use matrix factors, including component analysis and common factor analysis.

A *common factor* is an unobservable, hypothetical variable that contributes to the variance of at least two of the observed variables. The unqualified term "factor" often refers to a common factor. A *unique factor* is an unobservable, hypothetical variable that contributes to the variance of only one of the observed variables. The model for common factor analysis posits one unique factor for each observed variable.

The equation for the common factor model is

$$y_{ij} = x_{i1}b_{1j} + x_{i2}b_{2j} + \dots + x_{iq}b_{qj} + e_{ij}$$

where

 y_{ij} is the value of the *i*th observation on the *j*th variable

 x_{ik} is the value of the *i*th observation on the *k*th common factor

 b_{kj} is the regression coefficient of the kth common factor for predicting the jth variable

 e_{ij} is the value of the *i*th observation on the *j*th unique factor

q is the number of common factors

It is assumed, for convenience, that all variables have a mean of 0. In matrix terms, these equations reduce to

$$Y = XB + E$$

In the preceding equation, X is the matrix of factor scores, and B' is the factor pattern.

There are two critical assumptions:

- The unique factors are uncorrelated with each other.
- The unique factors are uncorrelated with the common factors.

In principal component analysis, the residuals are generally correlated with each other. In common factor analysis, the unique factors play the role of residuals and are defined to be uncorrelated both with each other and with the common factors. Each common factor is assumed to contribute to at least two variables; otherwise, it would be a unique factor.

When the factors are initially extracted, it is also assumed, for convenience, that the common factors are uncorrelated with each other and have unit variance. In this case, the common factor model implies that the covariance s_{jk} between the *j*th and *k*th variables, $j \neq k$, is given by

$$s_{jk} = b_{1j}b_{1k} + b_{2j}b_{2k} + \dots + b_{qj}b_{qk}$$

or

$$S = B'B + U^2$$

where S is the covariance matrix of the observed variables, and U^2 is the diagonal covariance matrix of the unique factors.

If the original variables are standardized to unit variance, the preceding formula yields correlations instead of covariances. It is in this sense that common factors explain the correlations among the observed variables. When considering the diagonal elements of standardized S, the variance of the *j*th variable is expressed as

$$s_{jj} = 1 = b_{1j}^2 + b_{2j}^2 + \dots + b_{qj}^2 + [\mathbf{U}^2]_{jj}$$

where $b_{1j}^2 + b_{2j}^2 + \cdots + b_{qj}^2$ and $[U^2]_{jj}$ are the communality and uniqueness, respectively, of the *j*th variable. The communality represents the extent of the overlap with the common factors. In other words, it is the proportion of variance accounted for by the common factors.

The difference between the correlation predicted by the common factor model and the actual correlation is the *residual correlation*. A good way to assess the goodness of fit of the common factor model is to examine the residual correlations.

The common factor model implies that the partial correlations among the variables, removing the effects of the common factors, must all be zero. When the common factors are removed, only unique factors, which are by definition uncorrelated, remain.

The assumptions of common factor analysis imply that the common factors are, in general, not linear combinations of the observed variables. In fact, even if the data contain measurements on the entire population of observations, you cannot compute the scores of the observations on the common factors. Although the common factor scores cannot be computed directly, they can be estimated in a variety of ways.

The problem of factor score indeterminacy has led several factor analysts to propose methods yielding components that can be considered approximations to common factors. Since these components are defined as linear combinations, they are computable. The methods include Harris component analysis and image component analysis. The advantage of producing determinate component scores is offset by the fact that, even if the data fit the common factor model perfectly, component methods do not generally recover the correct factor solution. You should not use any type of component analysis if you really want a common factor analysis (Dziuban and Harris 1973; Lee and Comrey 1979).

After the factors are estimated, it is necessary to interpret them. Interpretation usually means assigning to each common factor a name that reflects the *salience* of the factor in predicting each of the observed variables—that is, the coefficients in the pattern matrix corresponding to the factor. Factor interpretation is a subjective process. It can sometimes be made less subjective by *rotating* the common factors—that is, by applying a nonsingular linear transformation. A rotated pattern matrix in which all the coefficients are close to 0 or ± 1 is easier to interpret than a pattern with many intermediate elements. Therefore, most rotation methods attempt to optimize a simplicity function of the rotated pattern matrix that measures, in some sense, how close the elements are to 0 or ± 1 . Because the loading estimates are subject to sampling variability, it is useful to obtain the standard error estimates for the loadings for assessing the uncertainty due to random sampling. Notice that the *salience* of a factor loading refers to the magnitude of the loading, while statistical

significance refers to the statistical evidence against a particular hypothetical value. A loading significantly different from 0 does not automatically mean it must be salient. For example, if salience is defined as a magnitude larger than 0.4 while the entire 95% confidence interval for a loading lies between 0.1 and 0.3, the loading is statistically significant larger than 0 but it is not salient. Under the maximum likelihood method, you can obtain standard errors and confidence intervals for judging the salience of factor loadings.

After the initial factor extraction, the common factors are uncorrelated with each other. If the factors are rotated by an *orthogonal transformation*, the rotated factors are also uncorrelated. If the factors are rotated by an *oblique transformation*, the rotated factors become correlated. Oblique rotations often produce more useful patterns than do orthogonal rotations. However, a consequence of correlated factors is that there is no single unambiguous measure of the importance of a factor in explaining a variable. Thus, for oblique rotations, the pattern matrix does not provide all the necessary information for interpreting the factors; you must also examine the *factor structure* and the *reference structure*.

Rotating a set of factors does not change the statistical explanatory power of the factors. You cannot say that any rotation is better than any other rotation from a statistical point of view; all rotations, orthogonal or oblique, are equally good statistically. Therefore, the choice among different rotations must be based on nonstatistical grounds. For most applications, the preferred rotation is that which is most easily interpretable, or most compatible with substantive theories.

If two rotations give rise to different interpretations, those two interpretations must not be regarded as conflicting. Rather, they are two different ways of looking at the same thing, two different points of view in the common-factor space. Any conclusion that depends on one and only one rotation being correct is invalid.

Outline of Use

Principal Component Analysis

One important type of analysis performed by the FACTOR procedure is principal component analysis. The following statements result in a principal component analysis:

```
proc factor;
run;
```

The output includes all the eigenvalues and the pattern matrix for eigenvalues greater than one.

Most applications require additional output. For example, you might want to compute principal component scores for use in subsequent analyses or obtain a graphical aid to help decide how many components to keep. You can save the results of the analysis in a permanent SAS data library by using the OUTSTAT= option. For more information about permanent libraries and SAS data sets, see *SAS Language Reference: Concepts*. Assuming that your SAS data library has the libref save and that the data are in a SAS data set called raw, you could do a principal component analysis as follows:

```
proc factor data=raw method=principal scree mineigen=0 score
    outstat=save.fact_all;
run;
```

The SCREE option produces a plot of the eigenvalues that is helpful in deciding how many components to use. Alternative, you can use the PLOTS=SCREE option to produce high-quality scree plots. The MINEIGEN=0 option causes all components with variance greater than zero to be retained. The SCORE option requests that scoring coefficients be computed. The OUTSTAT= option saves the results in a specially structured SAS data

set. The name of the data set, in this case fact_all, is arbitrary. To compute principal component scores, use the SCORE procedure:

```
proc score data=raw score=save.fact_all out=save.scores;
run;
```

The SCORE procedure uses the data and the scoring coefficients that are saved in save.fact_all to compute principal component scores. The component scores are placed in variables named Factor1, Factor2, ..., Factorn and are saved in the data set save.scores. If you know ahead of time how many principal components you want to use, you can obtain the scores directly from PROC FACTOR by specifying the NFACTORS= and OUT= options. To get scores from three principal components, specify the following:

To plot the scores for the first three components, use the SGSCATTER procedure:

```
proc sgscatter;
  matrix factor1-factor3;
run;
```

Principal Factor Analysis

The simplest and computationally most efficient method of common factor analysis is principal factor analysis, which is obtained in the same way as principal component analysis except for the use of the PRIORS= option. The usual form of the initial analysis is as follows:

The squared multiple correlations (SMC) of each variable with all the other variables are used as the prior communality estimates. If your correlation matrix is singular, you should specify PRIORS=MAX instead of PRIORS=SMC. The SCREE and MINEIGEN= options serve the same purpose as in the preceding principal component analysis. Saving the results with the OUTSTAT= option enables you to examine the eigenvalues and scree plot before deciding how many factors to rotate and to try several different rotations without re-extracting the factors. The OUTSTAT= data set is automatically marked TYPE=FACTOR, so the FACTOR procedure realizes that it contains statistics from a previous analysis instead of raw data.

After looking at the eigenvalues to estimate the number of factors, you can try some rotations. Two and three factors can be rotated with the following statements:

```
proc factor data=save.fact_all method=principal n=2
    rotate=promax reorder score outstat=save.fact_2;
run;
proc factor data=save.fact_all method=principal n=3
    rotate=promax reorder score outstat=save.fact_3;
run;
```

The output data set from the previous run is used as input for these analyses. The options N=2 and N=3 specify the number of factors to be rotated. The specification ROTATE=PROMAX requests a promax rotation, which has the advantage of providing both orthogonal and oblique rotations with only one invocation of

PROC FACTOR. The REORDER option causes the variables to be reordered in the output so that variables associated with the same factor appear next to each other.

You can now compute and plot factor scores for the two-factor promax-rotated solution as follows:

```
proc score data=raw score=save.fact_2 out=save.scores;
run;
proc sgplot;
    scatter y=factor2 x=factor1;
run:
```

Maximum Likelihood Factor Analysis

Although principal factor analysis is perhaps the most commonly used method of common factor analysis, most statisticians prefer maximum likelihood (ML) factor analysis (Lawley and Maxwell 1971). The ML method of estimation has desirable asymptotic properties (Bickel and Doksum 1977) and produces better estimates than principal factor analysis in large samples. You can test hypotheses about the number of common factors by using the ML method. You can also obtain standard error and confidence interval estimates for many classes of rotated or unrotated factor loadings, factor correlations, and structure loadings under the ML theory.

The unrotated ML solution is equivalent to Rao's canonical factor solution (Rao 1955) and Howe's solution maximizing the determinant of the partial correlation matrix (Morrison 1976). Thus, as a descriptive method, ML factor analysis does not require a multivariate normal distribution. The validity of Bartlett's χ^2 test for the number of factors does require approximate normality plus additional regularity conditions that are usually satisfied in practice (Geweke and Singleton 1980). Bartlett's test of sphericity in the context of factor analysis is equivalent to Bartlett's χ^2 test for zero common factors. This test is routinely displayed in the maximum likelihood factor analysis output.

Lawley and Maxwell (1971) derive the standard error formulas for unrotated loadings, while Archer and Jennrich (1973) and Jennrich (1973, 1974) derive the standard error formulas for several classes of rotated solutions. Extended formulas for computing standard errors in various situations appear in Browne et al. (2008); Hayashi and Yung (1999); Yung and Hayashi (2001). A combination of these methods is used in PROC FACTOR to compute standard errors in an efficient manner. Confidence intervals are computed by using the asymptotic normality of the estimates. To ensure that the confidence intervals fall within the admissible parameter range, transformation methods due to Browne (1982) are used. The validity of the standard error estimates and confidence limits requires the assumptions of multivariate normality and a fixed number of factors.

The ML method is more computationally demanding than principal factor analysis for two reasons. First, the communalities are estimated iteratively, and each iteration takes about as much computer time as principal factor analysis. The number of iterations typically ranges from about five to twenty. Second, if you want to extract different numbers of factors, as is often the case, you must run the FACTOR procedure once for each number of factors. Therefore, an ML analysis can take 100 times as long as a principal factor analysis. This does not include the time for computing standard error estimates, which is even more computationally demanding. For analyses with fewer than 35 variables, the computing time for the ML method, including the computation of standard errors, usually ranges from a few seconds to well under a minute. This seems to be a reasonable performance.

You can use principal factor analysis to get a rough idea of the number of factors before doing an ML analysis. If you think that there are between one and three factors, you can use the following statements for the ML analysis:

```
proc factor data=raw method=ml n=1
    outstat=save.fact1;
run;
proc factor data=raw method=ml n=2 rotate=promax
    outstat=save.fact2;
run;
proc factor data=raw method=ml n=3 rotate=promax
    outstat=save.fact3;
run;
```

The output data sets can be used for trying different rotations, computing scoring coefficients, or restarting the procedure in case it does not converge within the allotted number of iterations.

If you can determine how many factors should be retained before an analysis, as in the following statements, you can get the standard errors and confidence limits to aid interpretations for the ML analysis:

```
proc factor data=raw method=ml n=3 rotate=quartimin se
    cover=.4;
run;
```

In this analysis, you specify the quartimin rotation in the ROTATE= option. The SE option requests the computation of standard error estimates. In the COVER= option, you require absolute values of 0.4 or greater in order for loadings to be salient. In the output of coverage display, loadings that are salient would have their entire confidence intervals spanning beyond the 0.4 mark (or the –0.4 mark in the opposite direction). Only those salient loadings should be used for interpreting the factors. See the section "Confidence Intervals and the Salience of Factor Loadings" on page 2336 for more details.

The ML method cannot be used with a singular correlation matrix, and it is especially prone to Heywood cases. See the section "Heywood Cases and Other Anomalies about Communality Estimates" on page 2341 for a discussion of Heywood cases. If you have problems with ML, the best alternative is to use the METHOD=ULS option for unweighted least squares factor analysis.

Factor Rotation

After the initial factor extraction, the factors are uncorrelated with each other. If the factors are rotated by an *orthogonal transformation*, the rotated factors are also uncorrelated. If the factors are rotated by an *oblique transformation*, the rotated factors become correlated. Oblique rotations often produce more useful patterns than orthogonal rotations do. However, a consequence of correlated factors is that there is no single unambiguous measure of the importance of a factor in explaining a variable. Thus, for oblique rotations, the pattern matrix does not provide all the necessary information for interpreting the factors; you must also examine the *factor structure* and the *reference structure*.

Nowadays, most rotations are done analytically. There are many choices for orthogonal and oblique rotations. An excellent summary of a wide class of analytic rotations is in Crawford and Ferguson (1970). The Crawford-Ferguson family of orthogonal rotations includes the orthomax rotation as a subclass and the popular varimax rotation as a special case. To illustrate these relationships, the following four specifications for orthogonal rotations with different ROTATE= options will give the same results for a data set with nine observed variables:

```
/* Orthogonal Crawford-Ferguson Family with
         variable parsimony weight = nvar - 1 = 8, and
          factor parsimony weight = 1 */
  proc factor data=raw n=3 rotate=orthcf(8,1);
  run;
      /* Orthomax without the GAMMA= option */
  proc factor data=raw n=3 rotate=orthomax(1);
  run;
      /* Orthomax with the GAMMA= option */
  proc factor data=raw n=3 rotate=orthomax gamma=1;
  run;
      /* Varimax */
  proc factor data=raw n=3 rotate=varimax;
You can also get the oblique versions of the varimax in two equivalent ways:
      /* Oblique Crawford-Ferguson Family with
         variable parsimony weight = nvar - 1 = 8, and
         factor parsimony weight = 1; */
  proc factor data=raw n=3 rotate=oblicf(8,1);
  run;
      /* Oblique Varimax */
  proc factor data=raw n=3 rotate=obvarimax;
```

Jennrich (1973) proposes a generalized Crawford-Ferguson family that includes the Crawford-Ferguson family and the (direct) oblimin family (see Harman 1976) as subclasses. The better-known quartimin rotation is a special case of the oblimin class, and hence a special case of the generalized Crawford-Ferguson family. For example, the following four specifications of oblique rotations are equivalent:

```
/* Oblique generalized Crawford-Ferguson Family
    with weights 0, 1, 0, -1 */
proc factor data=raw n=3 rotate=obligencf(0,1,0,-1);
run;

/* Oblimin family without the TAU= option */
proc factor data=raw n=3 rotate=oblimin(0);
run;

/* Oblimin family with the TAU= option */
proc factor data=raw n=3 rotate=oblimin tau=0;
run;

/* Quartimin */
proc factor data=raw n=3 rotate=quartimin;
run;
```

run;

In addition to the generalized Crawford-Ferguson family, the available oblique rotation methods in PROC FACTOR include Harris-Kaiser, promax, and Procrustes. See the section "Simplicity Functions for Rotations" on page 2337 for details about the definitions of various rotations. See Harman (1976) and Mulaik (1972) for further information.

Getting Started: FACTOR Procedure

The following example demonstrates how you can use the FACTOR procedure to perform common factor analysis and factor rotation.

In this example, 103 police officers were rated by their supervisors on 14 scales (variables). You conduct a common factor analysis on these variables to see what latent factors are operating behind these ratings. The overall rating variable is excluded from the factor analysis.

The following DATA step creates the SAS data set jobratings:

```
options validvarname=any;
data jobratings;
   input ('Communication Skills'n
          'Problem Solving'n
          'Learning Ability'n
          'Judgment under Pressure'n
          'Observational Skills'n
          'Willingness to Confront Problems'n
          'Interest in People'n
          'Interpersonal Sensitivity'n
          'Desire for Self-Improvement'n
          'Appearance'n
          'Dependability'n
          'Physical Ability'n
          'Integrity'n
          'Overall Rating'n) (1.);
   datalines;
26838853879867
74758876857667
56757863775875
67869777988997
99997798878888
89897899888799
89999889899798
87794798468886
   ... more lines ...
99899899899899
76656399567486
```

The following statements invoke the FACTOR procedure:

```
proc factor data=jobratings(drop='Overall Rating'n) priors=smc
  rotate=varimax;
run;
```

The DATA= option in PROC FACTOR specifies the SAS data set jobratings as the input data set. The DROP= option drops the Overall Rating variable from the analysis. To conduct a common factor analysis, you need to set the prior communality estimate to less than one for each variable. Otherwise, the factor solution would simply be a recast of the principal components solution, in which "factors" are linear combinations of observed variables. However, in the common factor model you always assume that observed variables are functions of underlying factors. In this example, the PRIORS= option specifies that the squared multiple correlations (SMC) of each variable with all the other variables are used as the prior communality estimates. Note that squared multiple correlations are usually less than one. By default, the principal factor extraction is used if the METHOD= option is not specified. To facilitate interpretations, the ROTATE= option specifies the VARIMAX orthogonal factor rotation to be used.

The output from the factor analysis is displayed in Figure 37.1 through Figure 37.5.

As displayed in Figure 37.1, the prior communality estimates are set to the squared multiple correlations. Figure 37.1 also displays the table of eigenvalues (the variances of the principal factors) of the reduced correlation matrix. Each row of the table pertains to a single eigenvalue. Following the column of eigenvalues are three measures of each eigenvalue's relative size and importance. The first of these displays the difference between the eigenvalue and its successor. The last two columns display the individual and cumulative proportions that the corresponding factor contributes to the total variation. The last line displayed in Figure 37.1 states that three factors are retained, as determined by the PROPORTION criterion.

Figure 37.1 Table of Eigenvalues from PROC FACTOR

The FACTOR Procedure Initial Factor Method: Principal Factors

		Prior Comm	unality Estin	nates: SMC		
Communication Skills		Learning Ability		Observationa Skill	al Confror	o nt Interest in
0.62981394	0.58657431	0.61009871	0.63766021	0.6718758	3 0.6477980	5 0.75641519
Interpersona Sensitivit	al De ty Self-Impro	esire for ovement Ap	pearance De	ependability	Physical Ability	Integrity
0.7558489	1 0.5	7460176 0.4	15505304	0.63449045 0	.42245324 0	.68195454

Figure 37.1 continued

Ei	Eigenvalues of the Reduced Correlation Matrix: Total = 8.06463816 Average = 0.62035678					
	Eigenvalue	Difference	Proportion	Cumulative		
1	6.17760549	4.71531946	0.7660	0.7660		
2	1.46228602	0.90183348	0.1813	0.9473		
3	0.56045254	0.28093933	0.0695	1.0168		
4	0.27951322	0.04766016	0.0347	1.0515		
5	0.23185305	0.16113428	0.0287	1.0802		
6	0.07071877	0.07489624	0.0088	1.0890		
7	00417747	0.03387533	-0.0005	1.0885		
8	03805279	0.04776534	-0.0047	1.0838		
9	08581814	0.02438060	-0.0106	1.0731		
10	11019874	0.01452741	-0.0137	1.0595		
11	12472615	0.02356465	-0.0155	1.0440		
12	14829080	0.05823605	-0.0184	1.0256		
13	20652684		-0.0256	1.0000		

3 factors will be retained by the PROPORTION criterion.

Figure 37.2 displays the initial factor pattern matrix. The factor pattern matrix represents standardized regression coefficients for predicting the variables by using the extracted factors. Because the initial factors are uncorrelated, the pattern matrix is also equal to the correlations between variables and the common factors.

Figure 37.2 Factor Pattern Matrix from PROC FACTOR

Factor Pattern						
	Factor1	Factor2	Factor3			
Communication Skills	0.75441	0.07707	-0.25551			
Problem Solving	0.68590	0.08026	-0.34788			
Learning Ability	0.65904	0.34808	-0.25249			
Judgment under Pressure	0.73391	-0.21405	-0.23513			
Observational Skills	0.69039	0.45292	0.10298			
Willingness to Confront Problems	0.66458	0.47460	0.09210			
Interest in People	0.70770	-0.53427	0.10979			
Interpersonal Sensitivity	0.64668	-0.61284	-0.07582			
Desire for Self-Improvement	0.73820	0.12506	0.09062			
Appearance	0.57188	0.20052	0.16367			
Dependability	0.79475	-0.04516	0.16400			
Physical Ability	0.51285	0.10251	0.34860			
Integrity	0.74906	-0.35091	0.18656			

The pattern matrix suggests that Factor1 represents general ability. All loadings for Factor1 in the Factor Pattern are at least 0.5. Factor2 consists of high positive loadings on certain task-related skills (Willingness to Confront Problems, Observational Skills, and Learning Ability) and high negative loadings on some interpersonal skills (Interpersonal Sensitivity, Interest in People, and Integrity). This factor measures individuals' relative strength in these skills. Theoretically, individuals with high positive scores on this factor would exhibit better task-related skills than interpersonal skills. Individuals with high negative scores would exhibit better interpersonal skills than task-related skills. Individuals with scores near zero would have those skills balanced. Factor3 does not have a cluster of very high or very low factor loadings. Therefore, interpreting this factor is difficult.

Figure 37.3 displays the proportion of variance explained by each factor and the final communality estimates, including the total communality. The final communality estimates are the proportion of variance of the variables accounted for by the common factors. When the factors are orthogonal, the final communalities are calculated by taking the sum of squares of each row of the factor pattern matrix.

Figure 37.3 Variance Explained and Final Communality Estimates

		y Each	Explained b	Variance		
		Factor3	Factor2	Factor1		
).5604525	1.4622860 (6.1776055		
<u> </u>	00344	Total = 8.20	y Estimates:	Communalit	Final	
Willingness	Wi					
to Confront Interest in		Observation	Judgment	Loomina	Droblom	Communication
Problems People		Observatio Sk		Learning Ability		Skills
0.67538695 0.79833968	485 0.0	0.692374	0.63972863	0.61924167	0.59791844	0.64036292
Physical	Dh			esire for	d De	Interpersona

Figure 37.4 displays the results of the VARIMAX rotation of the three extracted factors and the corresponding orthogonal transformation matrix. The rotated factor pattern matrix is calculated by postmultiplying the original factor pattern matrix (Figure 37.4) by the transformation matrix.

Ability

0.66056907 0.39504805 0.71903222

Integrity

Sensitivity Self-Improvement Appearance Dependability

0.56879171 0.39403630

Figure 37.4 Transformation Matrix and Rotated Factor Pattern

	Orthogonal Transformation Matrix							
	1	2	3					
1	0.59125	0.59249	0.54715					
2	-0.80080	0.51170	0.31125					
3	0.09557	0.62219	-0.77701					

Figure 37.4 continued

Rotated Factor Pattern					
Notated 1 detor					
	Factor1	Factor2	Factor3		
Communication Skills	0.35991	0.32744	0.63530		
Problem Solving	0.30802	0.23102	0.67058		
Learning Ability	0.08679	0.41149	0.66512		
Judgment under Pressure	0.58287	0.17901	0.51764		
Observational Skills	0.05533	0.70488	0.43870		
Willingness to Confront Problems	0.02168	0.69391	0.43978		
Interest in People	0.85677	0.21422	0.13562		
Interpersonal Sensitivity	0.86587	0.02239	0.22200		
Desire for Self-Improvement	0.34498	0.55775	0.37242		
Appearance	0.19319	0.54327	0.24814		
Dependability	0.52174	0.54981	0.29337		
Physical Ability	0.25445	0.57321	0.04165		
Integrity	0.74172	0.38033	0.15567		

The rotated factor pattern matrix is somewhat simpler to interpret. If a magnitude of at least 0.5 is required to indicate a salient variable-factor relationship, Factor1 now represents interpersonal skills (Interpersonal Sensitivity, Interest in People, Integrity, Judgment Under Pressure, and Dependability). Factor2 measures physical skills and job enthusiasm (Observational Skills, Willingness to Confront Problems, Physical Ability, Desire for Self-Improvement, Dependability, and Appearance). Factor3 measures cognitive skills (Communication Skills, Problem Solving, Learning Ability, and Judgment Under Pressure).

However, using 0.5 for determining a salient variable-factor relationship does not take sampling variability into account. If the underlying assumptions for the maximum likelihood estimation are approximately satisfied, you can output standard error estimates and the confidence intervals with METHOD=ML. You can then determine the salience of the variable-factor relationship by using the coverage displays. See the section "Confidence Intervals and the Salience of Factor Loadings" on page 2336 for more details.

Figure 37.5 displays the variance explained by each factor and the final communality estimates after the orthogonal rotation. Even though the variances explained by the rotated factors are different from that of the unrotated factor (compare with Figure 37.3), the cumulative variance explained by the common factors remains the same. Note also that the final communalities for variables, as well as the total communality, remain unchanged after rotation. Although rotating a factor solution will not increase or decrease the statistical quality of the factor model, it can simplify the interpretations of the factors and redistribute the variance explained by the factors.

Figure 37.5 Variance Explained and Final Communality Estimates after Rotation

Variance Explained by Each Factor						
Factor1	Factor2	Factor3				
3.1024330	2.7684489	2.3294622				

Figure 37.5 continued

		Final	Communa	lity Estimate	25: T	otal = 8.20	0344	1			—
Comm	unication Skills	Problem Solving	Learnin Abili	Judgme ng und	nt er O	bservatio		Willingn Confr Proble	to ont	Interes	•
0.6	64036292	0.59791844	0.6192416	67 0.6397286	63	0.692374	185	0.67538	695	0.798339	968
	erpersona Sensitivity		esire for evement A	ppearance	Dep	endability	F	Physical Ability		ntegrity	
).79951357	7 0.56	879171 (0.39403630	0.	66056907	0.39	9504805	0.7	1903222	

Syntax: FACTOR Procedure

The following statements are available in the FACTOR procedure:

```
PROC FACTOR < options>;

VAR variables;

PRIORS communalities;

PATHDIAGRAM < options>;

PARTIAL variables;

FREQ variable;

WEIGHT variable;

BY variables;
```

Usually only the VAR statement is needed in addition to the PROC FACTOR statement. The descriptions of the BY, FREQ, PARTIAL, PRIORS, VAR, and WEIGHT statements follow the description of the PROC FACTOR statement in alphabetical order.

PROC FACTOR Statement

PROC FACTOR < options> ;

The PROC FACTOR statement invokes the FACTOR procedure. The *options* listed in Table 37.1 are available in the PROC FACTOR statement.

 Table 37.1
 Options Available in the PROC FACTOR Statement

Option	Description
Data Set Options	
DATA=	Specifies input SAS data set
OUT=	Specifies output SAS data set
OUTSTAT=	Specifies output data set containing statistical results
TARGET=	Specifies input data set containing the target pattern for rotation
Factor Extraction an	d Communalities
HEYWOOD	Sets to 1 any communality greater than 1

Tab	le 37	'.1 (continued

Table 37.1 continued		
Option	Description	
METHOD=	Specifies the estimation method	
PRIORS=	Specifies the method for computing prior communality	
	estimates	
RANDOM=	Specifies the seed for pseudo-random number generation	
ULTRAHEYWOOD	Allows communalities to exceed 1	
Number of Factors		
MINEIGEN=	Specifies the smallest eigenvalue for retaining a factor	
NFACTORS=	Specifies the number of factors to retain	
PROPORTION=	Specifies the proportion of common variance in extracted	
	factors	
Data Analysis Option	s	
ALPHA=	Specifies the confidence level for interval construction	
COVARIANCE	Requests factoring of the covariance matrix	
COVER=	Computes the confidence interval and specifies the	
	coverage reference point	
NOINT	Omits the intercept from computing covariances or	
	correlations	
SE	Requests the standard error estimates in ML estimation	
VARDEF=	Specifies the divisor used in calculating covariances or	
WEIGHT	correlations	
WEIGHT	Factors a weighted correlation or covariance matrix	
Rotation Method and	Properties	
GAMMA=	Specifies the orthomax weight	
HKPOWER=	Specifies the power in Harris-Kaiser rotation	
NORM=	Specifies the method for row normalization in rotation	
NOPROMAXNORM	Turns off row normalization in promax rotation	
POWER=	Specifies the power to be used in promax rotation	
PREROTATE=	Specifies the prerotation method in promax rotation	
RCONVERGE=	Specifies the convergence criterion for rotation cycles	
RITER=	Specifies the maximum number of cycles for rotation	
ROTATE= TAU=	Specifies the rotation method Specifies the oblimin weight	
IAU-	Specifies the obliffin weight	
ODS Graphics		
PLOTS=	Specifies ODS Graphics selection	
Control Display Outp	out	
ALL	Displays all optional output except plots	
CORR	Displays the (partial) correlation matrix	
EIGENVECTORS	Displays the eigenvectors of the reduced correlation matrix	
FLAG=	Specifies the minimum absolute value to be flagged in the	
	correlation and loading matrices	
FUZZ=	Specifies the maximum absolute value to be displayed as	
	missing in the correlation and loading matrices	

Table 37.1 continued

Table 37.1 Co	Jilliliaea
Option	Description
MSA	Computes Kaiser's measure of sampling adequacy and the
	related partial correlations
NOPRINT	Suppresses the display of all output
NPLOT=	Specifies the number of factors to be plotted
PLOT	Plots the rotated factor pattern
PLOTREF	Plots the reference structure
PREPLOT	Plots the factor pattern before rotation
PRINT	Displays the input factor pattern or scoring coefficients and related statistics
REORDER	Reorders the rows (variables) of various factor matrices
RESIDUALS	Displays the residual correlation matrix and the associated
	partial correlation matrix
ROUND	Prints correlation and loading matrices with rounded
	values
SCORE	Displays the factor scoring coefficients
SCREE	Displays the scree plot of the eigenvalues
SIMPLE	Displays means, standard deviations, and number of
	observations
Numerical Properties	
CONVERGE=	Specifies the convergence criterion
MAXITER=	Specifies the maximum number of iterations
SINGULAR=	Specifies the singularity criterion
Miscellaneous	
NOCORR	Excludes the correlation matrix from the OUTSTAT= data
	set
NOBS=	Specifies the number of observations
PARPREFIX=	Specifies the prefix for the residual variables in the output
	data sets
PREFIX=	Specifies the prefix for naming factors

ALL

displays all optional output except plots. When the input data set is TYPE=CORR, TYPE=UCORR, TYPE=COV, TYPE=UCOV, or TYPE=FACTOR, simple statistics, correlations, and MSA are not displayed.

ALPHA=p

specifies the level of confidence 1-p for interval construction. By default, p=0.05, corresponding to 1-p=95% confidence intervals. If p is greater than one, it is interpreted as a percentage and divided by 100. With multiple confidence intervals to be constructed, the ALPHA= value is applied to each interval construction one at a time. This will not control the coverage probability of the intervals simultaneously. To control familywise coverage probability, you might consider supplying a nonconventional p by using methods such as Bonferroni adjustment.

CONVERGE=p

CONV=p

specifies the convergence criterion for the METHOD=PRINIT, METHOD=ULS, METHOD=ALPHA, or METHOD=ML option. Iteration stops when the maximum change in the communalities is less than the value of the CONVERGE= option. The default value is 0.001. Negative values are not allowed.

CORR

C

displays the correlation matrix or partial correlation matrix.

COVARIANCE

COV

requests factoring of the covariance matrix instead of the correlation matrix. The COV option is effective only with the METHOD=PRINCIPAL, METHOD=PRINIT, METHOD=ULS, or METHOD=IMAGE option. For other methods, PROC FACTOR produces the same results with or without the COV option.

COVER <=p>

CI <=p>

computes the confidence intervals and optionally specifies the value of factor loading for coverage detection. By default, p = 0. The specified value is represented by an asterisk (*) in the coverage display. This is useful for determining the salience of loadings. For example, if COVER=0.4, a display '0*[]' indicates that the entire confidence interval is above 0.4, implying strong evidence for the salience of the loading. See the section "Confidence Intervals and the Salience of Factor Loadings" on page 2336 for more details.

DATA=SAS-data-set

specifies the input data set, which can be an ordinary SAS data set or a specially structured SAS data set as described in the section "Input Data Set" on page 2332. If the DATA= option is omitted, the most recently created SAS data set is used.

EIGENVECTORS

ΕV

displays the eigenvectors of the reduced correlation matrix, of which the diagonal elements are replaced with the communality estimates. When METHOD=ML, the eigenvectors are for the weighted reduced correlation matrix. PROC FACTOR chooses the solution that makes the sum of the elements of each eigenvector nonnegative. If the sum of the elements is equal to zero, then the sign depends on how the number is rounded off.

FLAG=p

flags absolute values larger than p with an asterisk in the correlation and loading matrices. Negative values are not allowed for p. Values printed in the matrices are multiplied by 100 and rounded to the nearest integer (see the ROUND option). The FLAG= option has no effect when standard errors or confidence intervals are also printed.

FUZZ=p

prints correlations and factor loadings with absolute values less than *p* printed as missing. For partial correlations, the FUZZ= value is divided by 2. For residual correlations, the FUZZ= value is divided by 4. The exact values in any matrix can be obtained from the OUTSTAT= and ODS output data sets. Negative values are not allowed. The FUZZ= option has no effect when standard errors or confidence intervals are also printed.

GAMMA=p

specifies the orthomax weight used with the option ROTATE=ORTHOMAX or PRE-ROTATE=ORTHOMAX. Alternatively, you can use ROTATE=ORTHOMAX(*p*) with *p* representing the orthomax weight. There is no restriction on valid values for the orthomax weight, although the most common values are between zero and the number of variables. The default GAMMA= value is one, resulting in the varimax rotation. See the section "Simplicity Functions for Rotations" on page 2337 for more details.

HEYWOOD

HEY

sets to 1 any communality greater than 1, allowing iterations to proceed. See the section "Heywood Cases and Other Anomalies about Communality Estimates" on page 2341 for a discussion of Heywood cases.

HKPOWER=p

HKP=*p*

specifies the power of the square roots of the eigenvalues used to rescale the eigenvectors for Harris-Kaiser (ROTATE=HK) rotation, assuming that the factors are extracted by the principal factor method. If the principal factor method is not used for factor extraction, the eigenvectors are replaced by the normalized columns of the unrotated factor matrix, and the eigenvalues are replaced by the column normalizing constants. HKPOWER= values between 0.0 and 1.0 are reasonable. The default value is 0.0, yielding the independent cluster solution, in which each variable tends to have a large loading on only one factor. An HKPOWER= value of 1.0 is equivalent to an orthogonal rotation, with the varimax rotation as the default. You can also specify the HKPOWER= option with ROTATE=QUARTIMAX, ROTATE=BIQUARTIMAX, ROTATE=EQUAMAX, or ROTATE=ORTHOMAX, and so on. The only restriction is that the Harris-Kaiser rotation must be associated with an orthogonal rotation.

MAXITER=n

specifies the maximum number of iterations for factor extraction. You can use the MAXITER= option with the PRINIT, ULS, ALPHA, or ML method. The default is 30.

METHOD=name

M=name

specifies the method for extracting factors. The default is METHOD=PRINCIPAL unless the DATA= data set is TYPE=FACTOR, in which case the default is METHOD=PATTERN. Valid values for *name* are as follows:

ALPHA | A produces alpha factor analysis.

HARRIS | **H** yields Harris component analysis of $S^{-1}RS^{-1}$ (Harris 1962), a noniterative approximation to canonical component analysis.

IMAGE | I yields principal component analysis of the image covariance matrix, not the im-

age analysis of Kaiser (1963, 1970) or Kaiser and Rice (1974). A nonsingular

correlation matrix is required.

ML | M performs maximum likelihood factor analysis with an algorithm due, except for

minor details, to Fuller (1987). The option METHOD=ML requires a nonsingular

correlation matrix.

PATTERN reads a factor pattern from a TYPE=FACTOR, TYPE=CORR, TYPE=UCORR,

TYPE=COV, or TYPE=UCOV data set. If you create a TYPE=FACTOR data set in a DATA step, only observations containing the factor pattern (_TYPE_='PATTERN') and, if the factors are correlated, the interfactor corre-

lations (_TYPE_='FCORR') are required.

PRINCIPAL | PRIN | P yields principal component analysis if no PRIORS option or statement is

used or if you specify PRIORS=ONE; if you specify a PRIORS statement or a PRIORS= value other than PRIORS=ONE, a principal factor analysis is performed.

PRINIT yields iterated principal factor analysis.

score reads scoring coefficients (_TYPE_='SCORE') from a TYPE=FACTOR,

TYPE=CORR, TYPE=UCORR, TYPE=COV, or TYPE=UCOV data set. The data set must also contain either a correlation or a covariance matrix. Scoring

coefficients are also displayed if you specify the OUT= option.

ULS | U produces unweighted least squares factor analysis.

MINEIGEN=p

MIN=p

specifies the smallest eigenvalue for which a factor is retained. If you specify two or more of the MINEIGEN=, NFACTORS=, and PROPORTION= options, the number of factors retained is the minimum number satisfying any of the criteria. The MINEIGEN= option cannot be used with either the METHOD=PATTERN or the METHOD=SCORE option. Negative values are not allowed. The default is 0 unless you omit both the NFACTORS= and the PROPORTION= options and one of the following conditions holds:

- If you specify the METHOD=ALPHA or METHOD=HARRIS option, then MINEIGEN=1.
- If you specify the METHOD=IMAGE option, then

$$MINEIGEN = \frac{total\ image\ variance}{number\ of\ variables}$$

• For any other METHOD= specification, if prior communality estimates of 1.0 are used, then

$$MINEIGEN = \frac{total\ weighted\ variance}{number\ of\ variables}$$

When an unweighted correlation matrix is factored, this value is 1.

MSA

produces the partial correlations between each pair of variables controlling for all other variables (the negative anti-image correlations) and Kaiser's measure of sampling adequacy (Kaiser 1970; Kaiser and Rice 1974; Cerny and Kaiser 1977).

NFACTORS=n NFACT=n

N=n

specifies the maximum number of factors to be extracted and determines the amount of memory to be allocated for factor matrices. The default is the number of variables. Specifying a number that is small relative to the number of variables can substantially decrease the amount of memory required to run PROC FACTOR, especially with oblique rotations. If you specify two or more of the NFACTORS=, MINEIGEN=, and PROPORTION= options, the number of factors retained is the minimum number satisfying any of the criteria. If you specify the option NFACTORS=0, eigenvalues are computed, but no factors are extracted. If you specify the option NFACTORS=-1, neither eigenvalues nor factors are computed. You can use the NFACTORS= option with the METHOD=PATTERN or METHOD=SCORE option to specify a smaller number of factors than are present in the data set.

NOBS=n

specifies the number of observations. If the DATA= input data set is a raw data set, *nobs* is defined by default to be the number of observations in the raw data set. The NOBS= option overrides this default definition. If the DATA= input data set contains a covariance, correlation, or scalar product matrix, the number of observations can be specified either by using the NOBS= option in the PROC FACTOR statement or by including a _TYPE_='N' observation in the DATA= input data set.

NOCORR

prevents the correlation matrix from being transferred to the OUTSTAT= data set when you specify the METHOD=PATTERN option. The NOCORR option greatly reduces memory requirements when there are many variables but few factors. The NOCORR option is not effective if the correlation matrix is required for other requested output; for example, if the scores or the residual correlations are displayed (for example, by using the SCORE, RESIDUALS, or ALL option).

NOINT

omits the intercept from the analysis; covariances or correlations are not corrected for the mean.

NOPRINT

suppresses the display of all output. Note that this option temporarily disables the Output Delivery System (ODS). For more information, see Chapter 20, "Using the Output Delivery System."

NOPROMAXNORM | NOPMAXNORM

turns off the default row normalization of the prerotated factor pattern, which is used in computing the promax target matrix.

NORM=COV | KAISER | NONE | RAW | WEIGHT

specifies the method for normalizing the rows of the factor pattern for rotation. If you specify the option NORM=KAISER, Kaiser's normalization is used ($\sum_j p_{ij}^2 = 1$). If you specify the option NORM=WEIGHT, the rows are weighted by the Cureton-Mulaik technique (Cureton and Mulaik 1975). If you specify the option NORM=COV, the rows of the pattern matrix are rescaled to represent covariances instead of correlations. If you specify the option NORM=NONE or NORM=RAW, normalization is not performed. The default is NORM=KAISER.

NPLOTS | **NPLOT**=*n*

specifies the number of factors to be plotted. The default is to plot all factors. The smallest allowable value is 2. If you specify the option NPLOTS=n, all pairs of the first n factors are plotted, producing a total of n(n-1)/2 plots.

OUT=SAS-data-set

creates a data set containing all the data from the DATA= data set plus variables called Factor1, Factor2, and so on, containing estimated factor scores. The DATA= data set must contain multivariate data, not correlations or covariances. You must also specify the NFACTORS= option to determine the number of factor score variables. If you specify partial variables in the PARTIAL statement, the OUT= data set will also contain the residual variables that are used for factor analysis. The output data set is described in detail in the section "Output Data Sets" on page 2334. If you want to create a SAS data set in a permanent library, you must specify a two-level name. For more information about permanent libraries and SAS data sets, see SAS Language Reference: Concepts.

OUTSTAT=SAS-data-set

specifies an output data set containing most of the results of the analysis. The output data set is described in detail in the section "Output Data Sets" on page 2334. If you want to create a SAS data set in a permanent library, you must specify a two-level name. For more information about permanent libraries and SAS data sets, see SAS Language Reference: Concepts.

PARPREFIX=name

specifies the prefix for the residual variables in the OUT= and the OUTSTAT= data sets when partial variables are specified in the PARTIAL statement.

PLOT

plots the factor pattern after rotation. This option produces printer plots. High-quality ODS graphical plots for factor patterns can be requested with the PLOTS=LOADINGS or PLOTS=INITLOADINGS option.

PLOTREF

plots the reference structure instead of the default factor pattern after oblique rotation.

```
PLOTS < (global-plot-options) > = plot-request < (options) >
```

```
PLOTS < (global-plot-options) > = (plot-request < (options) > < ... plot-request < (options) > > )
specifies one or more ODS graphical plots in PROC FACTOR. When you specify only one plot-request,
you can omit the parentheses around the plot-request. Here are some examples:
```

```
plots=all
plots(flip)=loadings
plots=(loadings(flip) scree(unpack))
```

ODS Graphics must be enabled before plots can be requested. For example:

```
ods graphics on;
proc factor plots=all;
run;
ods graphics off;
```

For more information about enabling and disabling ODS Graphics, see the section "Enabling and Disabling ODS Graphics" on page 606 in Chapter 21, "Statistical Graphics Using ODS."

For an example containing graphical displays of factor analysis results, see Example 37.2.

Plot-Request	Plot Description	Suboptions
ALL	all available plots	all
INITLOADINGS	unrotated factor loadings	CIRCLE=, FLIP, NPLOTS=,
		PLOTREF, and VECTOR
LOADINGS	rotated factor loadings	CIRCLE=, FLIP, NPLOTS=,
		PLOTREF, and VECTOR
NONE	no ODS graphical plots	
PATHDIAGRAM	path diagram	
PRELOADINGS	prerotated factor loadings	CIRCLE=, FLIP, NPLOTS=,
		PLOTREF, and VECTOR
SCREE	scree and variance explained	UNPACK

The following are the available *global-plot-options* or *options* for plots:

CIRCLE | CIRCLES < = numbers > draws circular reference lines in scatter plots or vector plots of factor loadings. You can specify the locations of the circular reference lines in the *numbers* list. Each number indicates the proportion or percentage of area of the unit circle that is enclosed by the specified circle. Each of the *numbers* must lie between 0 and 100, inclusively. When a number is between 0 and 1 (inclusively), it is interpreted as a proportion; otherwise, it is interpreted as a percentage. The maximum number of circles is 5.

The CIRCLE option applies to the scatter or vector plots requested by the INIT-LOADINGS, LOADINGS, and PRELOADINGS options. By default, a unit-circle, which represents 100% of the total area, is drawn for the vector plots. However, no circle will be drawn for scatter plots unless the CIRCLE option is specified. Two special cases for this option are: (1) With no *numbers* following the CIRCLE option, a 100% circle will be drawn. (2) With CIRCLE=0, no circle will be drawn. This special case is primarily used to turn off the default unit-circle in vector plots. switches the X and Y axes. It applies to the INITLOADINGS, LOADINGS, and PRELOADINGS *plot-requests*.

FLIP

NPLOTS=n specifies the number of factors n ($n \ge 2$) to be plotted. It applies to the INITLOADINGS, LOADINGS, and PRELOADINGS *plot-requests*. Since this option can also be specified in the PROC FACTOR statement, the final value of n is determined by the following steps. The NPLOTS= value of the PROC FACTOR is read first. If the NPLOTS= option is specified as a *global-plot-option*, the value of n will be updated. Then, if the NPLOTS= option is again specified in an individual *plot-request*, the value will be updated again for that individual *plot-request*. For example, in the following statement, four factors are extracted with the N=4 option:

Initially, plots of the first three factors are specified with the NPLOTS=3 option. When you are producing ODS graphical plots, the *global-plot-option* NPLOTS=4

The default NPLOTS= value is 5 or the total number of factors (m), whichever is smaller. If you specify an NPLOTS= value that is greater than m, NPLOTS=m will be used.

PATHDIAGRAM

creates a path diagram for the last factor model. The last factor model refers to the initial factor solution if you do not specify any rotations. It refers to the rotated factor solution if you use the ROTATE= option. The path diagram shows the links between factors and variables, the factor correlations, and the error variances in the model.

The path diagram does not display all non-zero directed links between factors and variables. It displays only those directed links that have factor loading estimates at 0.3 or bigger in magnitude. PROC FACTOR uses this 0.3-criterion by default. You can set your own criterion by using the FUZZ= option in the PROC FACTOR statement.

If you use both the METHOD=ML and SE options in the PROC FACTOR statement, the statistical significance of the factor loading estimate is also required for displaying the corresponding directed link between a variable and a factor. The default level of significance is 0.05. You can set your own level of significance by using the ALPHA= option in the PROC FACTOR statement.

Alternatively, you can produce path diagrams by using the the PATHDIAGRAM Statement, which provides many options that enables you to create highly customized path diagrams.

PLOTREF

plots the reference structures rather than the factor pattern loadings. It applies to the INITLOADINGS, LOADINGS, and PRELOADINGS *plot-requests* when the factor solution is oblique. This option can also be set globally as an option in the PROC FACTOR statement.

UNPACK

plots component graphs separately. It applies to the SCREE *plot-request* only.

VECTOR

plots loadings in vector form. It applies to the INITLOADINGS, LOADINGS, and PRELOADINGS *plot-requests* when the factor solution is orthogonal. For oblique solutions, the VECTOR option is ignored and the default scatter plots for factor loadings or reference structures are displayed.

Be aware that the PLOT option in the PROC FACTOR statement requests only the printer plots of factor loadings. The current option PLOTS= or PLOT=, however, is for ODS graphical plots.

You can specify options for the requested ODS graphical plots as *global-plot-options* or as local *options*. *Global-plot-options* apply to all appropriate individual *plot-requests* specified. For example, because the SCREE plot is not subject to axes flipping, the following two specifications are equivalent:

plots(flip)=(loadings preloadings scree)
plots=(loadings(flip) preloadings(flip) scree)

Options specified locally after each *plot-request* apply to that plot-request only. For example, consider the following specification:

```
plots=(scree(unpack) loadings(plotref) preloadings(flip))
```

The FLIP option applies to the PRELOADINGS *plot-request* but not the LOADINGS *plot-request*; the PLOTREF option applies to the LOADINGS *plot-request* but not the PRELOADINGS *plot-request*; and the UNPACK option applies to the SCREE *plot-request* only.

POWER=n

specifies the power to be used in computing the target pattern for the option ROTATE=PROMAX. Valid values must be integers ≥ 1 . The default value is 3. You can also specify the POWER= value in the ROTATE= option—for example, ROTATE=PROMAX(4).

PREFIX=name

specifies a prefix for naming the factors. By default, the names are Factor1, Factor2, ..., Factorn. If you specify PREFIX=ABC, the factors are named ABC1, ABC2, ABC3, and so on. The number of characters in the prefix plus the number of digits required to designate the variables should not exceed the current name length defined by the VALIDVARNAME= system option.

PREPLOT

plots the factor pattern before rotation. This option produces printer plots. High-quality ODS graphical plots for factor patterns can be requested with the PLOTS=PRELOADINGS option.

PREROTATE=name

PRE=name

specifies the prerotation method for the option ROTATE=PROMAX. Any rotation method other than PROMAX or PROCRUSTES can be used. The default is PREROTATE=VARIMAX. If a previously rotated pattern is read using the option METHOD=PATTERN, you should specify the PREROTATE=NONE option.

PRINT

displays the input factor pattern or scoring coefficients and related statistics. In oblique cases, the reference and factor structures are computed and displayed. The PRINT option is effective only with the option METHOD=PATTERN or METHOD=SCORE.

PRIORS=name

specifies a method for computing prior communality estimates. You can specify numeric values for the prior communality estimates by using the PRIORS statement. Valid values for *name* are as follows:

ASMC A	sets the prior communality estimates proportional to the squared multiple correlations but adjusted so that their sum is equal to that of the maximum absolute correlations (Cureton 1968).
INPUT I	reads the prior communality estimates from the first observation with either _TYPE_='PRIORS' or _TYPE_='COMMUNAL' in the DATA= data set (which cannot be TYPE=DATA).
MAX M	sets the prior communality estimate for each variable to its maximum absolute

correlation with any other variable.

ONE | O sets all prior communalities to 1.0.

RANDOM | **R** sets the prior communality estimates to pseudo-random numbers uniformly dis-

tributed between 0 and 1.

SMC | S sets the prior communality estimate for each variable to its squared multiple corre-

lation with all other variables.

The default prior communality estimates are as follows:

METHOD=	PRIORS=
PRINCIPAL	ONE
PRINIT	ONE
ALPHA	SMC
ULS	SMC
ML	SMC
HARRIS	(not applicable)
IMAGE	(not applicable)
PATTERN	(not applicable)
SCORE	(not applicable)

By default, the options METHOD=PRINIT, METHOD=ULS, METHOD=ALPHA, and METHOD=ML stop iterating and set the number of factors to 0 if an estimated communality exceeds 1. The options HEYWOOD and ULTRAHEYWOOD allow processing to continue.

PROPORTION=*p*

PERCENT=p

D _

P=*p*

specifies the proportion of common variance to be accounted for by the retained factors. The proportion of common variance is computed using the total prior communality estimates as the basis. If the value is greater than one, it is interpreted as a percentage and divided by 100. The options PROPORTION=0.75 and PERCENT=75 are equivalent. The default value is 1.0 or 100%. You cannot specify the PROPORTION= option with the METHOD=PATTERN or METHOD=SCORE option. If you specify two or more of the PROPORTION=, NFACTORS=, and MINEIGEN= options, the number of factors retained is the minimum number satisfying any of the criteria.

RANDOM=n

specifies a positive integer as a starting value for the pseudo-random number generator for use with the option PRIORS=RANDOM. If you do not specify the RANDOM= option, the time of day is used to initialize the pseudo-random number sequence. Valid values must be integers ≥ 1 .

RCONVERGE=p

RCONV=p

specifies the convergence criterion value p (p > 0) for rotation cycles. Rotation stops when the scaled change of the simplicity function value is less than p. Mathematically, the convergence criterion is

$$|f_{new} - f_{old}|/K < p$$

where f_{new} and f_{old} are simplicity function values of the current cycle and the previous cycle, respectively, $K = \max(1, |f_{old}|)$ is a scaling factor, and p is 1E–9 by default.

REORDER

RE

causes the rows (variables) of various factor matrices to be reordered on the output. Variables with their highest absolute loading (reference structure loading for oblique rotations) on the first factor are displayed first, from largest to smallest loading, followed by variables with their highest absolute loading on the second factor, and so on. The order of the variables in the output data set is not affected. The factors are not reordered.

RESIDUALS

RES

displays the residual correlation matrix and the associated partial correlation matrix. The diagonal elements of the residual correlation matrix are the unique variances.

RITER=n

specifies the maximum number of cycles *n* for factor rotation. Except for promax and Procrustes, you can use the RITER= option with all rotation methods. The default *n* is the maximum between 10 times the number of variables and 100.

ROTATE=name

R=name

specifies the rotation method. The default is ROTATE=NONE.

Valid *names* for orthogonal rotations are as follows:

- **BIQUARTIMAX** | **BIQMAX** specifies orthogonal biquartimax rotation. This corresponds to the specification ROTATE=ORTHOMAX(.5).
- **EQUAMAX** | **E** specifies orthogonal equamax rotation. This corresponds to the specification ROTATE=ORTHOMAX with GAMMA=number of factors/2.
- **FACTORPARSIMAX** | **FPA** specifies orthogonal factor parsimax rotation. This corresponds to the specification ROTATE=ORTHOMAX with GAMMA=number of variables.
- **NONE** | **N** specifies that no rotation be performed, leaving the original orthogonal solution.
- **ORTHCF**(p1,p2) | **ORCF**(p1,p2) | specifies the orthogonal Crawford-Ferguson rotation with the weights p1 and p2 for variable parsimony and factor parsimony, respectively. See the definitions of weights in the section "Simplicity Functions for Rotations" on page 2337.
- **ORTHGENCF**(*p1,p2,p3,p4*) | **ORGENCF**(*p1,p2,p3,p4*) specifies the orthogonal generalized Crawford-Ferguson rotation with the four weights *p1*, *p2*, *p3*, and *p4*. See the definitions of weights in the section "Simplicity Functions for Rotations" on page 2337.
- **ORTHOMAX**<(p) > | **ORMAX**<(p) > specifies the orthomax rotation with orthomax weight p. If ROTATE=ORTHOMAX is used, the default p value is 1 unless specified otherwise in the GAMMA= option. Alternatively, ROTATE=ORTHOMAX(p) specifies p as the orthomax weight or the GAMMA= value. See the definition of the orthomax weight in the section "Simplicity Functions for Rotations" on page 2337.

PARSIMAX | PA specifies orthogonal parsimax rotation. This corresponds to the specification ROTATE=ORTHOMAX with

$$GAMMA = \frac{nvar \times (nfact - 1)}{nvar + nfact - 2}$$

where *nvar* is the number of variables and *nfact* is the number of factors.

QUARTIMAX | QMAX | Q specifies orthogonal quartimax rotation. This corresponds to the specification ROTATE=ORTHOMAX(0).

VARIMAX | V specifies orthogonal varimax rotation. This corresponds to the specification ROTATE=ORTHOMAX with GAMMA=1.

Valid *names* for oblique rotations are as follows:

BIQUARTIMIN | **BIQMIN** specifies biquartimin rotation. It corresponds to the specification ROTATE=OBLIMIN(.5) or ROTATE=OBLIMIN with TAU=0.5.

COVARIMIN | **CVMIN** specifies covarimin rotation. It corresponds to the specification ROTATE=OBLIMIN(1) or ROTATE=OBLIMIN with TAU=1.

HK<(p)> | **H**<(p)> specifies Harris-Kaiser case II orthoblique rotation. When specifying this option, you can use the HKPOWER= option to set the power of the square roots of the eigenvalues by which the eigenvectors are scaled, assuming that the factors are extracted by the principal factor method. For other extraction methods, the unrotated factor pattern is column normalized. The power is then applied to the column normalizing constants, instead of the eigenvalues. You can also use ROTATE=HK(p), with p representing the HKPOWER= value. The default associated orthogonal rotation with ROTATE=HK is the varimax rotation without Kaiser normalization. You might associate the Harris-Kaiser with other orthogonal rotations by using the ROTATE= option together with the HKPOWER= option.

OBBIQUARTIMAX | OBIQMAX specifies oblique biquartimax rotation.

OBEQUAMAX | **OE** specifies oblique equamax rotation.

OBFACTORPARSIMAX | OFPA specifies oblique factor parsimax rotation.

OBLICF(*p1,p2*) | **OBCF**(*p1,p2*) specifies the oblique Crawford-Ferguson rotation with the weights *p1* and *p2* for variable parsimony and factor parsimony, respectively. See the definitions of weights in the section "Simplicity Functions for Rotations" on page 2337.

OBLIGENCF(*p1*,*p2*,*p3*,*p4*) | **OBGENCF**(*p1*,*p2*,*p3*,*p4*) specifies the oblique generalized Crawford-Ferguson rotation with the four weights *p1*, *p2*, *p3*, and *p4*. See the definitions of weights in the section "Simplicity Functions for Rotations" on page 2337.

OBLIMIN<(p) > | **OBMIN**<(p) > specifies the oblimin rotation with oblimin weight p. If ROTATE=OBLIMIN is used, the default p value is zero unless specified otherwise in the TAU= option. Alternatively, ROTATE=OBLIMIN(p) specifies p as the oblimin weight or the TAU= value. See the definition of the oblimin weight in the section "Simplicity Functions for Rotations" on page 2337.

OBPARSIMAX | OPA specifies oblique parsimax rotation.

OBQUARTIMAX | **OQMAX** specifies oblique quartimax rotation. This is the same as the QUARTIMIN method.

OBVARIMAX | OV specifies oblique varimax rotation.

PROCRUSTES specifies oblique Procrustes rotation with the target pattern provided by the TAR-GET= data set. The unrestricted least squares method is used with factors scaled to unit variance after rotation.

PROMAX<(p)> | **P**<(p)> specifies oblique promax rotation. You can use the PREROTATE= option to set the desirable prerotation method, orthogonal or oblique. When used with ROTATE=PROMAX, the POWER= option lets you specify the power for forming the target. You can also use ROTATE=PROMAX(p), where p represents the POWER= value.

QUARTIMIN | **QMIN** specifies quartimin rotation. It is the same as the oblique quartimax method. It also corresponds to the specification ROTATE=OBLIMIN(0) or ROTATE=OBLIMIN with TAU=0.

ROUND

prints correlation and loading matrices with entries multiplied by 100 and rounded to the nearest integer. The exact values can be obtained from the OUTSTAT= and ODS output data sets. The ROUND option also flags absolute values larger than the FLAG= value with an asterisk in correlation and loading matrices (see the FLAG= option). If the FLAG= option is not specified, the root mean square of all the values in the matrix printed is used as the default FLAG= value. The ROUND option has no effect when standard errors or confidence intervals are also printed.

SCORE

displays the factor scoring coefficients. The squared multiple correlation of each factor with the variables is also displayed except in the case of unrotated principal components. The SCORE option also outputs the factor scoring coefficients in the _TYPE_=SCORE or _TYPE_=USCORE observations in the OUTSTAT= data set. Unless you specify the NOINT option in PROC FACTOR, the scoring coefficients should be applied to standardized variables—variables that are centered by subtracting the original variable means and then divided by the original variable standard deviations. With the NOINT option, the scoring coefficients should be applied to data without centering.

SCREE

displays a scree plot of the eigenvalues (Cattell 1966, 1978; Cattell and Vogelman 1977; Horn and Engstrom 1979). This option produces printer plots. High-quality scree plots can be requested with the PLOTS=SCREE option.

SE

STDERR

computes standard errors for various classes of unrotated and rotated solutions under the maximum likelihood estimation.

SIMPLE

S

displays means, standard deviations, and the number of observations.

SINGULAR=p

SING=p

specifies the singularity criterion, where 0 . The default value is 1E–8.

TARGET=SAS-data-set

specifies an input data set containing the target pattern for Procrustes rotation (see the description of the ROTATE= option). The TARGET= data set must contain variables with the same names as those being factored. Each observation in the TARGET= data set becomes one column of the target factor pattern. Missing values are treated as zeros. The _NAME_ and _TYPE_ variables are not required and are ignored if present.

TAU=p

specifies the oblimin weight used with the option ROTATE=OBLIMIN or PREROTATE=OBLIMIN. Alternatively, you can use ROTATE=OBLIMIN(p) with p representing the oblimin weight. There is no restriction on valid values for the oblimin weight, although for practical purposes a negative or zero value is recommended. The default TAU= value is 0, resulting in the quartimin rotation. See the section "Simplicity Functions for Rotations" on page 2337 for more details.

ULTRAHEYWOOD

ULTRA

allows communalities to exceed 1. The ULTRAHEYWOOD option can cause convergence problems because communalities can become extremely large, and ill-conditioned Hessians might occur. See the section "Heywood Cases and Other Anomalies about Communality Estimates" on page 2341 for a discussion of Heywood cases.

VARDEF=DF | N | WDF | WEIGHT | WGT

specifies the divisor used in the calculation of variances and covariances. The default value is VARDEF=DF. The values and associated divisors are displayed in the following table where i=0 if the NOINT option is used and i=1 otherwise, and where k is the number of partial variables specified in the PARTIAL statement.

Value	Description	Divisor
DF	degrees of freedom	n-k-i
N	number of observations	n-k
WDF	sum of weights DF	$\sum_i w_i - k - i$
WEIGHT WGT	sum of weights	$\sum_i w_i - k$

WEIGHT

factors a weighted correlation or covariance matrix. The WEIGHT option can be used only with the METHOD=PRINCIPAL, METHOD=PRINIT, METHOD=ULS, or METHOD=IMAGE option. The input data set must be of type CORR, UCORR, COV, UCOV, or FACTOR, and the variable weights are obtained from an observation with _TYPE_='WEIGHT'.

BY Statement

BY variables:

You can specify a BY statement with PROC FACTOR to obtain separate analyses of observations in groups that are defined by the BY variables. When a BY statement appears, the procedure expects the input data set to be sorted in order of the BY variables. If you specify more than one BY statement, only the last one specified is used.

If your input data set is not sorted in ascending order, use one of the following alternatives:

- Sort the data by using the SORT procedure with a similar BY statement.
- Specify the NOTSORTED or DESCENDING option in the BY statement for the FACTOR procedure. The NOTSORTED option does not mean that the data are unsorted but rather that the data are arranged in groups (according to values of the BY variables) and that these groups are not necessarily in alphabetical or increasing numeric order.
- Create an index on the BY variables by using the DATASETS procedure (in Base SAS software).

If you specify the TARGET= option and the TARGET= data set does not contain any of the BY variables, then the entire TARGET= data set is used as a Procrustean target for each BY group in the DATA= data set.

If the TARGET= data set contains some but not all of the BY variables, or if some BY variables do not have the same type or length in the TARGET= data set as in the DATA= data set, then PROC FACTOR displays an error message and stops.

If all the BY variables appear in the TARGET= data set with the same type and length as in the DATA= data set, then each BY group in the TARGET= data set is used as a Procrustean target for the corresponding BY group in the DATA= data set. The BY groups in the TARGET= data set must be in the same order as in the DATA= data set. If you specify the NOTSORTED option in the BY statement, there must be identical BY groups in the same order in both data sets. If you do not specify the NOTSORTED option, some BY groups can appear in one data set but not in the other.

For more information about BY-group processing, see the discussion in *SAS Language Reference: Concepts*. For more information about the DATASETS procedure, see the discussion in the *Base SAS Procedures Guide*.

FREQ Statement

FREQ variable;

If a variable in the data set represents the frequency of occurrence for the other values in the observation, include the variable's name in a FREQ statement. The procedure then treats the data set as if each observation appears n times, where n is the value of the FREQ variable for the observation. The total number of observations is considered to be equal to the sum of the FREQ variable when the procedure determines degrees of freedom for significance probabilities.

If the value of the FREQ variable is missing or is less than one, the observation is not used in the analysis. If the value is not an integer, the value is truncated to an integer.

The WEIGHT and FREQ statements have a similar effect, except in determining the number of observations for significance tests.

PARTIAL Statement

PARTIAL variables;

If you want the analysis to be based on a partial correlation or covariance matrix, use the PARTIAL statement to list the variables that are used to partial out the variables in the analysis.

PATHDIAGRAM Statement

PATHDIAGRAM < options > ;

You can use the PATHDIAGRAM statement to specify and modify the layout algorithm, to control the formatting of estimates, and to fine-tune many graphical and nongraphical features of path diagrams. You can use multiple PATHDIAGRAM statements to produce path diagrams that have different styles and graphical features.

Specifying a PATHDIAGRAM statement without any *options* has the same effect as specifying the PLOTS=PATHDIAGRAM option in the PROC FACTOR statement. Both produce a default path diagram for the last factor solution in a PROC FACTOR run. The default path diagrams show the links between factors and variables, the factor correlations, and the error variances in the model. For more information about the default path diagram, see the PLOTS=PATHDIAGRAM option.

The *options* in the PATHDIAGRAM statement can be classified into three categories, which are summarized in Table 37.2 through Table 37.4. The following three tables summarize these *options*. An alphabetical listing of these *options* that includes more details follows the tables.

Table 37.2 shows the *options* that you can use to specify the path diagram layout algorithm, to set the criteria for displaying the directed paths between variables and factors, and to specify the size of factors relative to the observed variables.

Table 37.2 Options for Controlling the Layout

Option	Description
ALPHA=	Specifies the significance level of the loading estimate that is required in order to
	display the corresponding link between a variable and a factor
ARRANGE=	Specifies the algorithm for laying out variables in the path diagram
COVER=	Specifies the salience criterion on the loading estimate
FACTORSIZE=	Specifies the size of latent factors relative to observed variables
FUZZ=	Specifies the magnitude of the loading estimate that is required in order to display
	the corresponding link between a variable and a factor

Table 37.3 Options for Displaying Parameter Estimates

Option	Description
DECP=	Specifies the number of decimal places in the estimates
NOESTIM	Disables the display of all numerical estimates
NOERRVAR	Disables the display of error variances
NOFACTORVAR	Disables the display of factor variances
NOVARIANCE	Disables the display of all variances

Table 37.4 shows the *options* that you can use to specify the title, the path diagram label, and the variable labels.

Table 37.4 Options for Specifying Titles and Labels

Option	Description
DIAGRAMLABEL=	Specifies the label of the diagram in the ODS
LABEL=	Specifies labels of the nodes that are shown in the path diagram
NODELABEL=	Specifies whether the variable names or labels are used to label nodes
NOTITLE	Suppresses the display of the title
TITLE=	Specifies the title to display in the output path diagram

$ALPHA=\alpha$

ALPHALOAD= α

specifies the significance level (α -level) of the loading estimate that is required in order to display the corresponding directed link (path) between a variable and a factor. If α is greater than 1, it is interpreted as a percentage and divided by 100. If the *p*-value of a loading estimate is greater than α , the loading estimate is insignificant and PROC FACTOR does not display the corresponding link in the path diagram. By default, $\alpha = 0.05$.

The ALPHA= option applies only when you specify the METHOD=ML option in the PROC FACTOR statement and when standard errors are computed in the analysis (for example, by specifying the SE option in the PROC FACTOR statement).

If you specify the ALPHA= option in the PROC FACTOR statement, all PATHDIAGRAM statements use the same α value that is specified in the ALPHA= option in the PROC FACTOR statement unless you respecify the ALPHA= option in individual PATHDIAGRAM statements.

NOTE: The *p*-value of a loading estimate is computed by using a reference sampling distribution that has a specific mean value. This mean value reflects the criterion for determining the salience of loading estimates. You can use the COVER= option or the SALIENCE= option to specify the salience criterion. By default, COVER=0; so PROC FACTOR displays all directed links between variables and factors that are significantly greater than 0.

ARRANGE=name

ARRANGEMENT=name

METHOD=name

specifies the algorithm for laying out the variables in the path diagram. You can specify the following *names*:

FLOW specifies the process-flow algorithm.

GRIP specifies the GRIP (graph drawing with intelligent placement) algorithm.

GROUPEDFLOW specifies the grouped-flow algorithm.

By default, ARRANGE=FLOW if the number of observed variables is less than 15; otherwise, the default is ARRANGE=GRIP. The reason for switching the default layout algorithm is that when the number of observed variables becomes large, the process-flow algorithm might run out of vertical space for aligning all observed variables in a vertical line. In that case, the GRIP algorithm might be a better choice because the observed variables tend to scatter around the space rather than being aligned vertically. See Example 37.5 for the use of the ARRANGE= option. For more information and for general uses of these layout algorithms, see the section "The Process-Flow, Grouped-Flow, and GRIP Layout Algorithms" on page 1440 in Chapter 29, "The CALIS Procedure."

COVER=p

SALIENCE=p

specifies the salience criterion, p, for the loading estimate. In order to display a loading estimate and its corresponding link between a variable and a factor in the path diagram, the magnitude of the loading estimate must be significantly greater than p. By default, p = 0 and the significance level (α -level) is 0.05. You can specify the significance level in the ALPHA= option.

The COVER= option applies only when you specify METHOD=ML in the PROC FACTOR statement and when standard errors are computed in the analysis (for example, by specifying the SE option in the PROC FACTOR statement).

If you specify the COVER= option in the PROC FACTOR statement, any PATHDIAGRAM statement that does not include a COVER= option uses the value that is specified in the PROC FACTOR statement.

DECP=i

sets the number of decimal places in the estimates that are displayed in the path diagram, where *i* is between 0 and 4. The displayed estimates are at most seven digits long, including the decimal point for the nonzero value of *i*. By default, DECP=2.

DIAGRAMLABEL=name

DLABEL=name

specifies the label of the path diagram. You can use any valid SAS name or quoted string of up to 256 characters for *name*. However, only up to 40 characters of the label are used by ODS. The following statements show two example label specifications:

```
pathdiagram diagramlabel=MyFactorModel;
pathdiagram diagramlabel="Varimax-Rotated Factor Solution";
```

If you do not specify this option, PROC FACTOR uses the *name* that is provided in the TITLE= option. If you specify neither the DIAGRAMLABEL= option nor the TITLE= option, PROC FACTOR uses "Path Diagram" for the label when there is only one path diagram. When there is more than one path diagram, a unique number is appended to the label of each path diagram. For example, "Path Diagram 3" is the third path diagram in the output.

FACTORSIZE=size

FACTSIZE=size

specifies the size of latent factors relative to the size of observed variables, where *size* is between 0.2 and 5. By default, FACTSIZE=1.5, which means that the size ratio of factors to observed variables is about 3 to 2.

FUZZ=p

specifies the magnitude, p > 0, of the factor loading estimate that is required in order to display the corresponding directed link between a variable and a factor. If the magnitude of a loading estimate is less than p, then PROC FACTOR does not display the corresponding directed link in the path diagram. By default, FUZZ=0.3.

If you specify the FUZZ= option in the PROC FACTOR statement, any PATHDIAGRAM statement that does not include a FUZZ= option uses the value that is specified in the PROC FACTOR statement.

If you specify METHOD=ML and standard errors are computed, PROC FACTOR displays only those directed links (paths) between variables and factors that are statistically significant in the path diagram. In this situation, only the criteria that are specified by the ALPHA= and COVER= options are used and the FUZZ= option is irrelevant. When METHOD=ML is not specified or standard errors are not computed, PROC FACTOR uses the criterion that is specified by the FUZZ= option.

LABEL= [varlabel < , varlabel ... >] | {varlabel < , varlabel ... >}

specifies the labels of variables to be displayed in path diagrams, where each *varlabel* has the following form:

variable=label

You can use any valid SAS names or quoted strings of up to 256 characters for *labels*. The *labels* identify the corresponding variables or factors in output path diagrams. For example, instead of using original variable names such as x1 and Factor1 in the path diagram, the following statement specifies the use of more meaningful labels:

```
pathdiagram label=[x1="Simple Math" Factor1="Math Ability"];
```

This option is not the only way that you can provide labels for variables. For example, you can also use the LABEL statement to specify labels for observed variables. PROC FACTOR uses the following rules to determine the label for a node (variable) in the path diagram:

- 1. If you specify the label for a variable or a factor by using the LABEL= option in the PATHDI-AGRAM statement, the associated node (variable) uses this label in the output path diagram. Proceed to the next rule if the label of a node is not resolved.
- 2. If the NODELABEL=VARNAME option is specified, the associated node uses the original variable name as its label in the output path diagram. Otherwise, proceed to the next rule.

- 3. If the label of a variable is specified in a LABEL statement, the associated node uses this label in the output path diagram. Otherwise, proceed to the next rule.
- 4. The associated node uses the original variable name as its label in the output path diagram.

NODELABEL=VARNAME | VARLABEL

specifies whether the variables (nodes) in path diagrams are labeled by the original variable names (VARNAME) or their variable labels (VARLABEL), which are provided by specifying the LABEL statement. If you provide variable labels (applicable only to observed variables) in the LABEL statement, PROC FACTOR uses those provided labels unless you specify this option.

This option is not the only determinant of the final labels of nodes in the path diagram. The specifications in the LABEL= option of the PATHDIAGRAM statement are also considered. For the rules that PROC FACTOR uses to determine the node labels, see the LABEL= option.

NOERRVAR

NOERRORVARIANCE

suppresses the default display of error variances, which are represented as double-headed paths that are attached to observed variables.

NOESTIM

NOEST

suppresses the default display of all numerical estimates in path diagrams.

NOFACTORVAR

NOFACTORVARIANCE

suppresses the default display of factor variances, which are represented as double-headed paths that are attached to factors.

NOTITLE

suppresses the display of the default title. You can use the TITLE= option to provide your own title.

NOVARIANCE

suppresses the default display of all variances. This option has the same effect as specifying both the NOFACTORVAR and NOERRVAR options.

TITLE=name

specifies the title of the path diagram. You can use any valid SAS name or a quoted string of up to 256 characters for *name*. If you do not specify this option, PROC FACTOR uses "Path Diagram" for the title when there is only one path diagram. A unique number (for example, "Path Diagram 3") is appended to the title of each path diagram when there is more than one path diagram.

PRIORS Statement

PRIORS communalities;

The PRIORS statement specifies numeric values between 0.0 and 1.0 for the prior communality estimates for each variable. The first numeric value corresponds to the first variable in the VAR statement, the second value to the second variable, and so on. The number of numeric values must equal the number of variables. For example:

```
proc factor;
  var  x y z;
  priors .7 .8 .9;
run;
```

You can specify various methods for computing prior communality estimates with the PRIORS= option in the PROC FACTOR statement. See the description of that option for more information about the default prior communality estimates.

VAR Statement

VAR variables;

The VAR statement specifies the numeric variables to be analyzed. If the VAR statement is omitted, all numeric variables not specified in other statements are analyzed.

WEIGHT Statement

WEIGHT variable;

If you want to use relative weights for each observation in the input data set, specify a variable containing weights in a WEIGHT statement. This is often done when the variance associated with each observation is different and the values of the weight variable are proportional to the reciprocals of the variances. If a variable value is negative or is missing, it is excluded from the analysis.

Details: FACTOR Procedure

Input Data Set

The FACTOR procedure can read an ordinary SAS data set containing raw data or a special data set specified as a TYPE=CORR, TYPE=UCORR, TYPE=SSCP, TYPE=COV, TYPE=UCOV, or TYPE=FACTOR data set containing previously computed statistics. A TYPE=CORR data set can be created by the CORR procedure or various other procedures such as the PRINCOMP procedure. It contains means, standard deviations, the sample size, the correlation matrix, and possibly other statistics if it is created by some procedure other than PROC CORR. A TYPE=COV data set is similar to a TYPE=CORR data set but contains a covariance matrix. A TYPE=UCORR or TYPE=UCOV data set contains a correlation or covariance matrix that is not corrected for the mean. The default VAR variable list does not include Intercept if the DATA= data set is TYPE=SSCP. If the Intercept variable is explicitly specified in the VAR statement with a TYPE=SSCP data set, the NOINT option is activated. A TYPE=FACTOR data set can be created by the FACTOR procedure and is described in the section "Output Data Sets" on page 2334.

If your data set has many observations and you plan to run FACTOR several times, you can save computer time by first creating a TYPE=CORR data set and using it as input to PROC FACTOR, as in the following statements:

The data set created by the CORR procedure is automatically given the TYPE=CORR data set option, so you do not have to specify TYPE=CORR. However, if you use a DATA step with a SET statement to modify the correlation data set, you must use the TYPE=CORR attribute in the new data set. You can use a VAR statement with PROC FACTOR when reading a TYPE=CORR data set to select a subset of the variables or change the order of the variables.

Problems can arise from using the CORR procedure when there are missing data. By default, PROC CORR computes each correlation from all observations that have values present for the pair of variables involved (pairwise deletion). The resulting correlation matrix might have negative eigenvalues. If you specify the NOMISS option with the CORR procedure, observations with any missing values are completely omitted from the calculations (listwise deletion), and there is no danger of negative eigenvalues.

PROC FACTOR can also create a TYPE=FACTOR data set, which includes all the information in a TYPE=CORR data set, and use it for repeated analyses. For a TYPE=FACTOR data set, the default value of the METHOD= option is PATTERN. The following PROC FACTOR statements produce the same results as the previous example:

```
proc factor data=raw method=ml outstat=fact; /* max. likelihood */
proc factor data=fact method=prin; /* principal components */
```

You can use a TYPE=FACTOR data set to try several different rotation methods on the same data without repeatedly extracting the factors. In the following example, the second and third PROC FACTOR statements use the data set fact created by the first PROC FACTOR statement:

```
proc factor data=raw outstat=fact; /* principal components */
proc factor rotate=varimax; /* varimax rotation */
proc factor rotate=quartimax; /* quartimax rotation */
```

You can create a TYPE=CORR, TYPE=UCORR, or TYPE=FACTOR data set in a DATA step for PROC FACTOR to read as input. For example, in the following a TYPE=CORR data set is created and is read as input data set by the subsequent PROC FACTOR statement:

```
data correl(type=corr);
    _TYPE_='CORR';
    input _NAME_ $ x y z;
    datalines;
x 1.0 . .
y .7 1.0 .
z .5 .4 1.0
;
proc factor;
run;
```

Be sure to specify the TYPE= option in parentheses after the data set name in the DATA statement and include the _TYPE_ and _NAME_ variables. In a TYPE=CORR data set, only the correlation matrix (_TYPE_='CORR') is necessary. It can contain missing values as long as every pair of variables has at least one nonmissing value.

You can also create a TYPE=FACTOR data set containing only a factor pattern (_TYPE_='PATTERN') and use the FACTOR procedure to rotate it, as these statements show:

```
data pat(type=factor);
    _TYPE_='PATTERN';
    input _NAME_ $ x y z;
    datalines;
factor1    .5    .7    .3
factor2    .8    .2    .8
;
proc factor rotate=promax prerotate=none;
run;
```

If the input factors are oblique, you must also include the interfactor correlation matrix with TYPE ='FCORR', as shown here:

```
data pat(type=factor);
   input _TYPE_ $ _NAME_ $ x y z;
   datalines;
pattern factor1   .5   .7   .3
pattern factor2   .8   .2   .8
fcorr   factor1   1.0   .2   .
fcorr   factor2   .2   1.0   .
;
proc factor rotate=promax prerotate=none;
run;
```

Some procedures, such as the PRINCOMP and CANDISC procedures, produce TYPE=CORR or TYPE=UCORR data sets containing scoring coefficients (_TYPE_='SCORE' or _TYPE_= 'USCORE'). These coefficients can be input to PROC FACTOR and rotated by using the METHOD=SCORE option, as in the following statements:

```
proc princomp data=raw n=2 outstat=prin;
run;
proc factor data=prin method=score rotate=varimax;
run;
```

Notice that the input data set prin must contain the correlation matrix as well as the scoring coefficients.

Output Data Sets

The OUT= Data Set

The OUT= data set contains all the data in the DATA= data set plus new variables called Factor1, Factor2, and so on, containing estimated factor scores. Each estimated factor score is computed as a linear combination of the standardized values of the variables that are factored. The coefficients are always displayed if the OUT= option is specified, and they are labeled "Standardized Scoring Coefficients."

If partial variables are specified in the PARTIAL statement, the factor analysis is on the residuals of the variables, which are regressed on the partial variables. In this case, the OUT= data set also contains the (unstandardized) residuals, which are prefixed by R_ by default. For example, the residual of variable X is named R_X in the OUT= data set. You might also assign the prefix by the PARPREFIX= option. Because the residuals are factor-analyzed, the estimated factor scores are computed as linear combinations of the standardized values of the residuals, but not the original variables.

The OUTSTAT= Data Set

The OUTSTAT= data set is similar to the TYPE=CORR or TYPE=UCORR data set produced by the CORR procedure, but it is a TYPE=FACTOR data set and it contains many results in addition to those produced by PROC CORR. The OUTSTAT= data set contains observations with _TYPE_='UCORR' and _TYPE_='USTD' if you specify the NOINT option.

The output data set contains the following variables:

- the BY variables, if any
- two new character variables, _TYPE_ and _NAME_
- the variables analyzed—those in the VAR statement, or, if there is no VAR statement, all numeric variables not listed in any other statement. If partial variables are specified in the PARTIAL statement, the residuals are included instead. By default, the residual variable names are prefixed by R_, unless you specify something different in the PARPREFIX= option.

Each observation in the output data set contains some type of statistic as indicated by the _TYPE_ variable. The _NAME_ variable is blank except where otherwise indicated. The values of the _TYPE_ variable are as follows:

MEAN means

STD standard deviations

USTD uncorrected standard deviations

N sample size

CORR correlations. The NAME variable contains the name of the variable corresponding to

each row of the correlation matrix.

UCORR uncorrected correlations. The NAME variable contains the name of the variable corre-

sponding to each row of the uncorrected correlation matrix.

IMAGE image coefficients. The NAME variable contains the name of the variable corresponding

to each row of the image coefficient matrix.

IMAGECOV image covariance matrix. The _NAME_ variable contains the name of the variable

corresponding to each row of the image covariance matrix.

COMMUNAL final communality estimates

PRIORS prior communality estimates, or estimates from the last iteration for iterative methods

WEIGHT variable weights

SUMWGT sum of the variable weights

EIGENVAL eigenvalues

UNROTATE unrotated factor pattern. The NAME variable contains the name of the factor.

SE_UNROT standard error estimates for the unrotated loadings. The NAME variable contains the

name of the factor.

RESIDUAL residual correlations. The NAME variable contains the name of the variable correspond-

ing to each row of the residual correlation matrix.

PRETRANS transformation matrix from prerotation. The NAME variable contains the name of the

factor.

PREFCORR prerotated interfactor correlations. The NAME variable contains the name of the factor.

SE_PREFC standard error estimates for prerotated interfactor correlations. The _NAME_ variable

contains the name of the factor.

PREROTAT prerotated factor pattern. The _NAME_ variable contains the name of the factor.

SE_PREPA standard error estimates for the prerotated loadings. The _NAME_ variable contains the

name of the factor.

PRERCORR prerotated reference axis correlations. The NAME variable contains the name of the

factor.

PREREFER prerotated reference structure. The _NAME_ variable contains the name of the factor.

PRESTRUC prerotated factor structure. The NAME variable contains the name of the factor.

SE PREST standard error estimates for prerotated structure loadings. The NAME variable contains

the name of the factor.

PRESCORE prerotated scoring coefficients. The NAME variable contains the name of the factor.

TRANSFOR transformation matrix from rotation. The NAME variable contains the name of the

factor.

FCORR interfactor correlations. The NAME variable contains the name of the factor.

SE_FCORR standard error estimates for interfactor correlations. The NAME variable contains the

name of the factor.

PATTERN factor pattern. The NAME variable contains the name of the factor.

SE_PAT standard error estimates for the rotated loadings. The _NAME_ variable contains the name

of the factor.

RCORR reference axis correlations. The _NAME_ variable contains the name of the factor.

REFERENC reference structure. The _NAME_ variable contains the name of the factor.

STRUCTUR factor structure. The _NAME_ variable contains the name of the factor.

SE_STRUC standard error estimates for structure loadings. The _NAME_ variable contains the name

of the factor.

SCORE scoring coefficients to be applied to standardized variables if the SCORE option is

specified on the PROC FACTOR statement. The _NAME_ variable contains the name of

the factor.

USCORE scoring coefficients to be applied without subtracting the mean from the raw variables if

the SCORE option is specified on the PROC FACTOR statement. The _NAME_ variable

contains the name of the factor.

Confidence Intervals and the Salience of Factor Loadings

The traditional approach to determining salient loadings (loadings that are considered large in absolute values) employs rules of thumb such as 0.3 or 0.4. However, this does not use the statistical evidence efficiently. The asymptotic normality of the distribution of factor loadings enables you to construct confidence intervals to gauge the salience of factor loadings. To guarantee the range-respecting properties of confidence intervals, a transformation procedure such as in CEFA (Browne et al. 2008) is used. For example, because the orthogonal rotated factor loading θ must be bounded between -1 and +1, the Fisher transformation

$$\varphi = \frac{1}{2}\log(\frac{1+\theta}{1-\theta})$$

is employed so that φ is an unbounded parameter. Assuming the asymptotic normality of $\hat{\varphi}$, a symmetric confidence interval for φ is constructed. Then, a back-transformation on the confidence limits yields an asymmetric confidence interval for θ . Applying the results of Browne (1982), a $(1-\alpha)100\%$ confidence interval for the orthogonal factor loading θ is

$$(\hat{\theta}_l = \frac{a/b - 1}{a/b + 1}, \ \hat{\theta}_u = \frac{a \times b - 1}{a \times b + 1})$$

where

$$a = \frac{1 + \hat{\theta}}{1 - \hat{\theta}}, \ b = \exp(z_{\alpha/2} \times \frac{2\hat{\sigma}}{1 - \hat{\theta}^2})$$

and $\hat{\theta}$ is the estimated factor loading, $\hat{\sigma}$ is the standard error estimate of the factor loading, and $z_{\alpha/2}$ is the $(1 - \alpha/2)100$ percentile point of a standard normal distribution.

Once the confidence limits are constructed, you can use the corresponding coverage displays for determining the salience of the variable-factor relationship. In a coverage display, the COVER= value is represented by an asterisk (*). The following table summarizes various displays and their interpretations.

Table 37.5 Interpretations of the Coverage Displays

Positive Estimate	Negative Estimate	COVER=0 Specified	Interpretation
[0]*	*[0]		The estimate is not significantly different from zero, and the CI covers a region of values that are smaller in magnitude than the COVER= value. This is strong statistical evidence for the nonsalience of the variable-factor relationship.
0[]*	*[]0		The estimate is significantly different from zero, but the CI covers a region of values that are smaller in magnitude than the COVER= value. This is strong statistical evidence for the nonsalience of the variable- factor relationship.
[0*]	[*0]	[0]	The estimate is not significantly different from zero or the COVER= value. The population value might have been larger or smaller in magnitude than the COVER= value. There is no statistical evidence for the salience of the variable-factor relationship.
0[*]	[*]0		The estimate is significantly different from zero but not from the COVER= value. This is marginal statistical evidence for the salience of the variable-factor relationship.
0*[]	[]*0	0[] or []0	The estimate is significantly different from zero, and the CI covers a region of values that are larger in magnitude than the COVER= value. This is strong statistical evidence for the salience of the variable-factor relationship.

See Example 37.4 for an illustration of the use of confidence intervals for interpreting factors.

Simplicity Functions for Rotations

To rotate a factor pattern is to apply a nonsingular linear transformation to the unrotated factor pattern matrix. An optimal transformation is usually defined as a minimum or maximum point of a simplicity function. Different rotation methods are based on different simplicity functions employed.

For the promax or the Procrustes rotation, the simplicity function used is the sum of squared differences between the rotated factor pattern and the target matrix. The optimal transformation is obtained by minimizing this simplicity function with respect to the choices of all possible transformation.

For the class of the generalized Crawford-Ferguson family Jennrich (1973), the simplicity function being optimized is

$$f = k_1 Z + k_2 H + k_3 V + k_4 Q$$

where

$$Z = (\sum_{i} \sum_{i} b_{ij}^{2})^{2}, \ H = \sum_{i} (\sum_{i} b_{ij}^{2})^{2}$$

$$V = \sum_{i} (\sum_{i} b_{ij}^{2})^{2}, \ \ Q = \sum_{i} \sum_{i} b_{ij}^{4}$$

 k_1, k_2, k_3 , and k_4 are constants, and b_{ij} represents an element of the rotated pattern matrix. Except for specialized research purposes, it is uncommon in practice to use this simplicity function directly for rotation. However, this simplicity function reduces to many well-known classes of rotations. One of these is the Crawford-Ferguson family Crawford and Ferguson (1970), which minimizes

$$f_{cf} = c_1(H - Q) + c_2(V - Q)$$

where c_1 and c_2 are constants, (H-Q) represents variable (row) parsimony, and (V-Q) represents factor (column) parsimony. Therefore, the relative importance of both the variable parsimony and of the factor parsimony is adjusted using the constants c_1 and c_2 . The orthomax class (see Harman 1976) maximizes the function

$$f_{or} = pQ - \gamma V$$

where γ is the orthomax weight and is usually between 0 and the number of variables p. The oblimin class minimizes the function

$$f_{ob} = p(H - Q) - \tau(Z - V)$$

where τ is the oblimin weight. For practical purposes, a negative or zero value for τ is recommended.

All of the preceding definitions are for rotations without row normalization. For rotations with Kaiser normalization, the definition of b_{ij} is replaced by b_{ij}/h_i , where h_i is the communality estimate of variable i.

Missing Values

If the DATA= data set contains data (rather than a matrix or factor pattern), then observations with missing values for any variables in the analysis are omitted from the computations. If a correlation or covariance matrix is read, it can contain missing values as long as every pair of variables has at least one nonmissing entry. Missing values in a pattern or scoring coefficient matrix are treated as zeros.

Cautions

• The amount of time that FACTOR takes is roughly proportional to the cube of the number of variables. Factoring 100 variables, therefore, takes about 1,000 times as long as factoring 10 variables. Iterative methods (PRINIT, ALPHA, ULS, ML) can also take 100 times as long as noniterative methods (PRINCIPAL, IMAGE, HARRIS).

- No computer program is capable of reliably determining the optimal number of factors, since the
 decision is ultimately subjective. You should not blindly accept the number of factors obtained by
 default; instead, use your own judgment to make a decision.
- Singular correlation matrices cause problems with the options PRIORS=SMC and METHOD=ML.
 Singularities can result from using a variable that is the sum of other variables, coding too many dummy variables from a classification variable, or having more variables than observations.
- If you use the CORR procedure to compute the correlation matrix and there are missing data and the NOMISS option is not specified, then the correlation matrix might have negative eigenvalues.
- If a TYPE=CORR, TYPE=UCORR, or TYPE=FACTOR data set is copied or modified using a DATA step, the new data set does not automatically have the same TYPE as the old data set. You must specify the TYPE= data set option in the DATA statement. If you try to analyze a data set that has lost its TYPE=CORR attribute, PROC FACTOR displays a warning message saying that the data set contains _NAME_ and _TYPE_ variables but analyzes the data set as an ordinary SAS data set.
- For a TYPE=FACTOR data set, the default is METHOD=PATTERN, not METHOD=PRIN.

Factor Scores

The FACTOR procedure can compute estimated factor scores directly if you specify the NFACTORS= and OUT= options, or indirectly using the SCORE procedure. The latter method is preferable if you use the FACTOR procedure interactively to determine the number of factors, the rotation method, or various other aspects of the analysis. To compute factor scores for each observation by using the SCORE procedure, do the following:

- Use the SCORE option in the PROC FACTOR statement.
- Create a TYPE=FACTOR output data set with the OUTSTAT= option.
- Use the SCORE procedure with both the raw data and the TYPE=FACTOR data set.
- Do not use the TYPE= option in the PROC SCORE statement.

For example, the following statements could be used:

```
proc factor data=raw score outstat=fact;
run;
proc score data=raw score=fact out=scores;
run;

Or

proc corr data=raw out=correl;
run;
proc factor data=correl score outstat=fact;
run;
proc score data=raw score=fact out=scores;
run;
```

For a more detailed example, see Example 88.1 in Chapter 88, "The SCORE Procedure."

A component analysis (principal, image, or Harris) produces scores with mean zero and variance one. If you have done a common factor analysis, the true factor scores have mean zero and variance one, but the computed factor scores are only estimates of the true factor scores. These estimates have mean zero but variance equal to the squared multiple correlation of the factor with the variables. The estimated factor scores might have small nonzero correlations even if the true factors are uncorrelated.

Variable Weights and Variance Explained

A principal component analysis of a covariance matrix gives more weight to variables with larger variances. A principal component analysis of a covariance matrix is equivalent to an analysis of a weighted correlation matrix, where the weight of each variable is equal to its variance. Variables with large weights tend to have larger loadings on the first component and smaller residual correlations than variables with small weights.

You might want to give weights to variables by using values other than their variances. Mulaik (1972) explains how to obtain a maximally reliable component by means of a weighted principal component analysis. With the FACTOR procedure, you can indirectly give arbitrary weights to the variables by using the COV option and rescaling the variables to have variance equal to the desired weight, or you can give arbitrary weights directly by using the WEIGHT option and including the weights in a TYPE=CORR data set.

Arbitrary variable weights can be used with the METHOD=PRINCIPAL, METHOD=PRINIT, METHOD=ULS, or METHOD=IMAGE option. Alpha and ML factor analyses compute variable weights based on the communalities (Harman 1976, pp. 217–218). For alpha factor analysis, the weight of a variable is the reciprocal of its communality. In ML factor analysis, the weight is the reciprocal of the uniqueness. Harris component analysis uses weights equal to the reciprocal of one minus the squared multiple correlation of each variable with the other variables.

For uncorrelated factors, the variance explained by a factor can be computed with or without taking the weights into account. The usual method for computing variance accounted for by a factor is to take the sum of squares of the corresponding column of the factor pattern, yielding an unweighted result. If the square of each loading is multiplied by the weight of the variable before the sum is taken, the result is the weighted variance explained, which is equal to the corresponding eigenvalue except in image analysis. Whether the weighted or unweighted result is more important depends on the purpose of the analysis.

In the case of correlated factors, the variance explained by a factor can be computed with or without taking the other factors into account. If you want to ignore the other factors, the variance explained is given by the weighted or unweighted sum of squares of the appropriate column of the factor structure since the factor structure contains simple correlations. If you want to subtract the variance explained by the other factors from the amount explained by the factor in question (the Type II variance explained), you can take the weighted or unweighted sum of squares of the appropriate column of the reference structure because the reference structure contains semipartial correlations. There are other ways of measuring the variance explained. For example, given a prior ordering of the factors, you can eliminate from each factor the variance explained by previous factors and compute a Type I variance explained. Harman (1976, pp. 268–270) provides another method, which is based on direct and joint contributions.

Heywood Cases and Other Anomalies about Communality Estimates

Since communalities are squared correlations, you would expect them always to lie between 0 and 1. It is a mathematical peculiarity of the common factor model, however, that final communality estimates might exceed 1. If a communality equals 1, the situation is referred to as a Heywood case, and if a communality exceeds 1, it is an ultra-Heywood case. An ultra-Heywood case implies that some unique factor has negative variance, a clear indication that something is wrong. Possible causes include the following:

- bad prior communality estimates
- too many common factors
- too few common factors
- not enough data to provide stable estimates
- the common factor model is not an appropriate model for the data

An ultra-Heywood case renders a factor solution invalid. Factor analysts disagree about whether or not a factor solution with a Heywood case can be considered legitimate.

With METHOD=PRINIT, METHOD=ULS, METHOD=ALPHA, or METHOD=ML, the FACTOR procedure, by default, stops iterating and sets the number of factors to 0 if an estimated communality exceeds 1. To enable processing to continue with a Heywood or ultra-Heywood case, you can use the HEYWOOD or ULTRAHEYWOOD option in the PROC FACTOR statement. The HEYWOOD option sets the upper bound of any communality to 1, while the ULTRAHEYWOOD option allows communalities to exceed 1.

Theoretically, the communality of a variable should not exceed its reliability. Violation of this condition is called a quasi-Heywood case and should be regarded with the same suspicion as an ultra-Heywood case.

Elements of the factor structure and reference structure matrices can exceed 1 only in the presence of an ultra-Heywood case. On the other hand, an element of the factor pattern might exceed 1 in an oblique rotation.

The maximum likelihood method is especially susceptible to quasi- or ultra-Heywood cases. During the iteration process, a variable with high communality is given a high weight; this tends to increase its communality, which increases its weight, and so on.

It is often stated that the squared multiple correlation of a variable with the other variables is a lower bound to its communality. This is true if the common factor model fits the data perfectly, but it is not generally the case with real data. A final communality estimate that is less than the squared multiple correlation can, therefore, indicate poor fit, possibly due to not enough factors. It is by no means as serious a problem as an ultra-Heywood case. Factor methods that use the Newton-Raphson method can actually produce communalities less than 0, a result even more disastrous than an ultra-Heywood case.

The squared multiple correlation of a factor with the variables might exceed 1, even in the absence of ultra-Heywood cases. This situation is also cause for alarm. Alpha factor analysis seems to be especially prone to this problem, but it does not occur with maximum likelihood. If a squared multiple correlation is negative, there are too many factors retained.

With data that do not fit the common factor model perfectly, you can expect some of the eigenvalues to be negative. If an iterative factor method converges properly, the sum of the eigenvalues corresponding to rejected factors should be 0; hence, some eigenvalues are positive and some negative. If a principal factor analysis fails to yield any negative eigenvalues, the prior communality estimates are probably too large. Negative eigenvalues cause the cumulative proportion of variance explained to exceed 1 for a sufficiently large number of factors. The cumulative proportion of variance explained by the retained factors should be approximately 1 for principal factor analysis and should converge to 1 for iterative methods. Occasionally, a single factor can explain more than 100 percent of the common variance in a principal factor analysis, indicating that the prior communality estimates are too low.

If a squared canonical correlation or a coefficient alpha is negative, there are too many factors retained.

Principal component analysis, unlike common factor analysis, has none of these problems if the covariance or correlation matrix is computed correctly from a data set with no missing values. Various methods for missing value correlation or severe rounding of the correlations can produce negative eigenvalues in principal components.

Time Requirements

n = number of observations

v = number of variables

f = number of factors

i = number of iterations during factor extraction

r = length of iterations during factor rotation

The time required to compute	is roughly proportional to
an overall factor analysis	iv^3
the correlation matrix	nv^2
PRIORS=SMC or ASMC	v^3
PRIORS=MAX	v^2
eigenvalues	v^3
final eigenvectors	fv^2
generalized Crawford-Ferguson family of rotations, PROMAX, or HK	fv^2 rvf^2
ROTATE=PROCRUSTES	vf^2

Each iteration in the PRINIT or ALPHA method requires computation of eigenvalues and f eigenvectors.

Each iteration in the ML or ULS method requires computation of eigenvalues and v-f eigenvectors.

The amount of time that PROC FACTOR takes is roughly proportional to the cube of the number of variables. Factoring 100 variables, therefore, takes about 1000 times as long as factoring 10 variables. Iterative methods (PRINIT, ALPHA, ULS, ML) can also take 100 times as long as noniterative methods (PRINCIPAL, IMAGE, HARRIS).

Displayed Output

PROC FACTOR output includes the following.

- Input data type, numbers of records read and used for raw data input, number of observations (NOBS=) set in the PROC FACTOR statements, and the number of observations used in significance tests
- Mean and Std Dev (standard deviation) of each variable and the number of observations, if you specify the SIMPLE option
- Correlations, if you specify the CORR option
- Inverse Correlation Matrix, if you specify the ALL option
- Partial Correlations Controlling all other Variables (negative anti-image correlations), if you specify
 the MSA option. If the data are appropriate for the common factor model, the partial correlations
 should be small.
- Kaiser's Measure of Sampling Adequacy (Kaiser 1970; Kaiser and Rice 1974; Cerny and Kaiser 1977), both overall and for each variable, if you specify the MSA option. The MSA is a summary of how small the partial correlations are relative to the ordinary correlations. Values greater than 0.8 can be considered good. Values less than 0.5 require remedial action, either by deleting the offending variables or by including other variables related to the offenders.
- Prior Communality Estimates, unless 1.0s are used or unless you specify the METHOD=IMAGE, METHOD=HARRIS, METHOD=PATTERN, or METHOD=SCORE option
- Squared Multiple Correlations of each variable with all the other variables, if you specify the METHOD=IMAGE or METHOD=HARRIS option
- Image Coefficients, if you specify the METHOD=IMAGE option
- Image Covariance Matrix, if you specify the METHOD=IMAGE option
- Preliminary Eigenvalues based on the prior communalities, if you specify the METHOD=PRINIT, METHOD=ALPHA, METHOD=ML, or METHOD=ULS option. The table produced includes the Total and the Average of the eigenvalues, the Difference between successive eigenvalues, the Proportion of variation represented, and the Cumulative proportion of variation.
- the number of factors that are retained, unless you specify the METHOD=PATTERN or METHOD=SCORE option
- the Scree Plot of Eigenvalues, if you specify the SCREE option. The preliminary eigenvalues are used if you specify the METHOD=PRINIT, METHOD=ALPHA, METHOD=ML, or METHOD=ULS option. You can request the corresponding high-quality graphical plot by using the PLOTS= option.
- the iteration history, if you specify the METHOD=PRINIT, METHOD=ALPHA, METHOD=ML, or METHOD=ULS option. The table produced contains the iteration number (Iter); the Criterion being optimized (Jöreskog 1977); the Ridge value for the iteration if you specify the METHOD=ML or METHOD=ULS option; the maximum Change in any communality estimate; and the Communalities.

- Significance tests, if you specify the option METHOD=ML, including Bartlett's chi-square, df, and Prob > χ^2 for H₀: No common factors and H₀: factors retained are sufficient to explain the correlations. The H₀ test for no common factors is equivalent to Bartlett's test of sphericity. The variables should have an approximate multivariate normal distribution for the probability levels to be valid. Lawley and Maxwell (1971) suggest that the number of observations should exceed the number of variables by 50 or more, although Geweke and Singleton (1980) claim that as few as 10 observations are adequate with five variables and one common factor. Certain regularity conditions must also be satisfied for Bartlett's χ^2 test to be valid (Geweke and Singleton 1980), but in practice these conditions usually are satisfied. The notation Prob>chi**2 means "the probability under the null hypothesis of obtaining a greater χ^2 statistic than that observed." The chi-square value is displayed with and without Bartlett's correction.
- Akaike's Information Criterion, if you specify the METHOD=ML option. Akaike's information criterion (AIC) (Akaike 1973, 1974, 1987) is a general criterion for estimating the best number of parameters to include in a model when maximum likelihood estimation is used. The number of factors that yields the smallest value of AIC is considered best. Like the chi-square test, AIC tends to include factors that are statistically significant but inconsequential for practical purposes.
- Schwarz's Bayesian Criterion, if you specify the METHOD=ML option. Schwarz's Bayesian Criterion
 (SBC) (Schwarz 1978) is another criterion, similar to AIC, for determining the best number of
 parameters. The number of factors that yields the smallest value of SBC is considered best; SBC seems
 to be less inclined to include trivial factors than either AIC or the chi-square test.
- Tucker and Lewis's Reliability Coefficient, if you specify the METHOD=ML option (Tucker and Lewis 1973)
- Squared Canonical Correlations, if you specify the METHOD=ML option. These are the same as the squared multiple correlations for predicting each factor from the variables.
- Coefficient Alpha for Each Factor, if you specify the METHOD=ALPHA option
- Eigenvectors, if you specify the EIGENVECTORS or ALL option, unless you also specify the METHOD=PATTERN or METHOD=SCORE option
- Eigenvalues of the (Weighted) (Reduced) (Image) Correlation or Covariance Matrix, unless you specify the METHOD=PATTERN or METHOD=SCORE option. Included are the Total and the Average of the eigenvalues, the Difference between successive eigenvalues, the Proportion of variation represented, and the Cumulative proportion of variation.
- the Factor Pattern, which is equal to both the matrix of standardized regression coefficients for
 predicting variables from common factors and the matrix of correlations between variables and
 common factors since the extracted factors are uncorrelated. Standard error estimates are included if
 the SE option is specified with METHOD=ML. Confidence limits and coverage displays are included
 if COVER= option is specified with METHOD=ML.
- Variance explained by each factor, both Weighted and Unweighted, if variable weights are used
- Final Communality Estimates, including the Total communality; or Final Communality Estimates and Variable Weights, including the Total communality, both Weighted and Unweighted, if variable weights are used. Final communality estimates are the squared multiple correlations for predicting the variables from the estimated factors, and they can be obtained by taking the sum of squares of each row of the factor pattern, or a weighted sum of squares if variable weights are used.

- Residual Correlations with Uniqueness on the Diagonal, if you specify the RESIDUAL or ALL option
- Root Mean Square Off-diagonal Residuals, both Over-all and for each variable, if you specify the RESIDUAL or ALL option
- Partial Correlations Controlling Factors, if you specify the RESIDUAL or ALL option
- Root Mean Square Off-diagonal Partials, both Over-all and for each variable, if you specify the RESIDUAL or ALL option
- Plots of Factor Pattern for unrotated factors, if you specify the PREPLOT option. The number of plots is determined by the NPLOT= option. You can request the corresponding high-quality graphical plots by using the PLOTS= option.
- Variable Weights for Rotation, if you specify the NORM=WEIGHT option
- Factor Weights for Rotation, if you specify the HKPOWER= option
- Orthogonal Transformation Matrix, if you request an orthogonal rotation
- Rotated Factor Pattern, if you request an orthogonal rotation. Standard error estimates are included if the SE option is specified with METHOD=ML. Confidence limits and coverage displays are included if COVER= option is specified with METHOD=ML.
- Variance explained by each factor after rotation. If you request an orthogonal rotation and if variable weights are used, both weighted and unweighted values are produced.
- Target Matrix for Procrustean Transformation, if you specify the ROTATE=PROMAX or ROTATE=PROCRUSTES option
- the Procrustean Transformation Matrix, if you specify the ROTATE=PROMAX or ROTATE=PROCRUSTES option
- the Normalized Oblique Transformation Matrix, if you request an oblique rotation, which, for the option ROTATE=PROMAX, is the product of the prerotation and the Procrustes rotation
- Inter-factor Correlations, if you specify an oblique rotation. Standard error estimates are included if the SE option is specified with METHOD=ML. Confidence limits and coverage displays are included if COVER= option is specified with METHOD=ML.
- Rotated Factor Pattern (Std Reg Coefs), if you specify an oblique rotation, giving standardized regression coefficients for predicting the variables from the factors. Standard error estimates are included if the SE option is specified with METHOD=ML. Confidence limits and coverage displays are included if COVER= option is specified with METHOD=ML.
- Reference Axis Correlations if you specify an oblique rotation. These are the partial correlations between the primary factors when all factors other than the two being correlated are partialed out.
- Reference Structure (Semipartial Correlations), if you request an oblique rotation. The reference structure is the matrix of semipartial correlations (Kerlinger and Pedhazur 1973) between variables and common factors, removing from each common factor the effects of other common factors. If the common factors are uncorrelated, the reference structure is equal to the factor pattern.

- Variance explained by each factor eliminating the effects of all other factors, if you specify an oblique rotation. Both Weighted and Unweighted values are produced if variable weights are used. These variances are equal to the (weighted) sum of the squared elements of the reference structure corresponding to each factor.
- Factor Structure (Correlations), if you request an oblique rotation. The (primary) factor structure is the matrix of correlations between variables and common factors. If the common factors are uncorrelated, the factor structure is equal to the factor pattern. Standard error estimates are included if the SE option is specified with METHOD=ML. Confidence limits and coverage displays are included if COVER= option is specified with METHOD=ML.
- Variance explained by each factor ignoring the effects of all other factors, if you request an oblique rotation. Both Weighted and Unweighted values are produced if variable weights are used. These variances are equal to the (weighted) sum of the squared elements of the factor structure corresponding to each factor.
- Final Communality Estimates for the rotated factors if you specify the ROTATE= option. The estimates should equal the unrotated communalities.
- Squared Multiple Correlations of the Variables with Each Factor, if you specify the SCORE or ALL option, except for unrotated principal components
- Standardized Scoring Coefficients, if you specify the SCORE or ALL option
- Plots of the Factor Pattern for rotated factors, if you specify the PLOT option and you request an orthogonal rotation. The number of plots is determined by the NPLOT= option. You can request the corresponding high-quality graphical plots by using the PLOTS= option.
- Plots of the Reference Structure for rotated factors, if you specify the PLOT option and you request an oblique rotation. The number of plots is determined by the NPLOT= option. Included are the Reference Axis Correlation and the Angle between the Reference Axes for each pair of factors plotted. You can request the corresponding high-quality graphical plots by using the PLOTS= option.
- A path diagram for the final factor solution if you specify the PLOTS=PATHDIAGRAM option or the PATHDIAGRAM statements.

If you specify the ROTATE=PROMAX option, the output includes results for both the prerotation and the Procrustes rotation.

ODS Table Names

PROC FACTOR assigns a name to each table it creates. You can use these names to reference the table when using the Output Delivery System (ODS) to select tables and create output data sets. These names are listed in the Table 37.6. For more information about ODS, see Chapter 20, "Using the Output Delivery System."

Table 37.6 ODS Tables Produced by PROC FACTOR

AlphaCoef CanCorr CanCorr CanCorr Conditional standard deviations ConvergenceStatus Correlations Eigenvalues Eigenvalues Eigenvectors Factor WeightRotate Factor Structure FinalCommun FinalCommunWgt Final communalities with weights FitMeasures ImageCoef Image Coor Image covariance matrix InputFactorPattern InputFactorPattern InputFactorOrr InvCorr InvCorr InvCorr InvCorr InvCorr InterFactorCorr InvCorr InvCorr NormObliqueTrans NormObliqueTrans OrthRotFactPat Ordor Conditional standard deviations METHOD=ML METHOD=PRINIT, ALPHA, ML, or ULS CORR default, SCREE Eigenvalues Eigenvalues default, SCREE Eigenvectors Eigenvectors Eigenvectors Eigenvectors Factor WeightRotate Factor structure Factor structure Factor structure Factor structure Factor structure Factor structure Final communalities default METHOD=ML METHOD=ML or ALPHA METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=PATTERN with PRINT or ALL METHOD=PATTERN with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=PATTERN with PRINT or ALL METHOD=PARRIS default METHOD=HARRIS default METHOD	Table 37.6 ODS Tables Produced by PROC FACTOR				
Factor CanCorr Conditional standard deviations ConvergenceStatus Corr Corr Corr Corr Correlations Eigenvalues Eigenvalues Eigenvectors Eigenvectors FactorPattern Factor structure FinalCommun Final communalities with weights FitMeasures Measures of fit ImageCoef Image coefficients InputSecreCoef InputSecreCoef InterFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr Inverse correlation matrix Nobs Number of records and oblique Trans ObliqueCrtans Orthacter Convergence status Convergence status METHOD=PRINIT, ALPHA, ML, or ULS CORR Eigenvalues	ODS Table Name	Description	Option		
CanCorr CondStdDev Conditional standard deviations ConvergenceStatus ConvergenceStatus Corr Corr Correlations Corr Eigenvalues Eigenvalues Eigenvectors FactorWeightRotate Factor pattern FactorStructure Final communalities Final communalities FitMeasures Measures of fit ImageCoef Image coefficients ImputFactorPattern InputFactorPattern InputFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr InterFactorCorr InterFactor Corr InterFactor Correlation NObs Number of records and observations ObliqueRotFactPat OrthRotFactPat OrthRotFactPat OrthRotFactPat OrthCort Ortnore OrthRotFactPat OrthCort OrthCort Ortic Date Conditional standard SIMPLE with PARTIAL Activitions CORR METHOD=PRINIT, ALPHA, ML, or ULS METHOD=NAGE METHOD=PRINIT, ALPHA, ML, or ULS METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS default ROTATE= any oblique rotation METHOD=HARRIS default ROTATE= any oblique rotation METHOD=HARRIS default ROTATE= any oblique rotation METHOD=HARRIS default ROTATE= any oblique rotation METHOD=HARRIS ROTATE= any oblique rotation	AlphaCoef	Coefficient alpha for each	METHOD=ALPHA		
Conditional standard deviations ConvergenceStatus Convergence status Corr Corr Corr Eigenvalues Eigenvalues Eigenvectors FactorWeightRotate Factor pattern Factor Structure FinalCommun Final communalities FinalCommun Final communalities Fitheasures ImageCoef Image coefficients ImputFactorPattern InputFactorPattern InputFactorOor Interfactor Correlations InterFactorCorr InterFactor Correlation InterFactorCorr InterFactor Correlation InvCorr InterFactor Correlation InvCorr InterFactor Correlation InvCorr InterFactor Correlation InvCorr Inverse correlation matrix IterHistory Nobs Number of records and observations, input data type NormObliqueTrans ObliqueRotFactPat OrthCort OrthCorr OrthCorr Correlations Notace Convergence status METHOD=PRINIT, ALPHA, ML, or ULS METHOD=ML METHOD=ML METHOD=ML METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=PATTERN with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=MC METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS ME		factor			
ConvergenceStatus Convergence status Corr Correlations COR Eigenvalues Eigenvalues Eigenvectors Eigenvectors Factor WeightRotate Factor pattern FactorStructure Final communalities Final communalities with weights FitMeasures Image Coef Image coefficients Image Factors Image factor pattern Input Factor pattern Input Factor pattern Input Factor pattern InterFactorCorr InterFactorCorr InterFactorCorr Inverse correlations InterFlatory InterFactorCorr Inverse correlations NObs Number of records and observations ObliqueRotFactPat OrthNotFactPat OrthGractPattern OrthnotFactPat Nothogonal transformation Orthogonal transformation Orthogonal rotation ROTATE= any oblique rotation HKPOWER= default HKPOWER= default HKPOWER= default HKPOWER= default METHOD=ML HKPOD=ML METHOD=ML METHOD=ML METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=IMAGE METHOD=MAGE METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=HAGE or METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS METHO	CanCorr	Squared canonical correlations	METHOD=ML		
Convergence Status Corr Correlations Corr Eigenvalues Eigenvalues Eigenvectors Eigenvectors Factor WeightRotate Factor Weight Rotate Factor Structure Factor Structure Final Commun Final Communalities Final Communalities with weights Fith Measures Measures of fit Image Coef Image coefficients Image Factor Pattern Input Factor Jatern Input Factor Jatern Input Score Coef Interfactor Correlation Inveorr Inveorr IterHistory Mormoblique Trans Normalized oblique Final Convergence status Correlations Eigenvalues Eigenvalues Eigenvectors ROTATE= any oblique rotation METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS METHOD=HARR	CondStdDev	Conditional standard	SIMPLE with PARTIAL		
CorrCorrelationsCORREigenvaluesEigenvaluesdefault, SCREEEigenvectorsEigenvectorsEIGENVECTORSFactorWeightRotateFactor weights for rotationHKPOWER=FactorPatternFactor patterndefaultFactorStructureFactor structureROTATE= any oblique rotationFinalCommunFinal communalities with weightsMETHOD=ML or ALPHAFitMeasuresMeasures of fitMETHOD=ML or ALPHAImageCoefImage coefficientsMETHOD=IMAGEImageFactorsImage covariance matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE orNOBsNumber of records and observations, input data typeMETHOD=HARRISNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPat Oblique transformation matrixROTATE= any oblique rotationOrthRotFactPat Orthgonal transformation matrixROTATE= any orthogonal rotationOrthRotFactPat Orthgogonal transformationROTATE= any orthogonal rotation		deviations			
EigenvaluesEigenvaluesdefault, SCREEEigenvectorsEigenvectorsEIGENVECTORSFactorWeightRotateFactor weights for rotationHKPOWER=FactorPatternFactor patterndefaultFactorStructureFactor structureROTATE= any oblique rotationFinalCommunFinal communalities with weightsMETHOD=ML or ALPHAFitMeasuresMeasures of fitMETHOD=MLImageCoefImage coefficientsMETHOD=IMAGEImageCofImage covariance matrixMETHOD=IMAGEImageFactorsImage factor matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=HARRISNObsNumber of records and observations, input data typeMETHOD=HARRISNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPat Oblique transformation matrixROTATE= any oblique rotationOrthRotFactPat OrthOgonal transformation matrixHKPOWER=OrthOgonal transformation OrthOgonal rotationROTATE= any orthogonal rotation	ConvergenceStatus	Convergence status	METHOD=PRINIT, ALPHA, ML, or ULS		
EigenvectorsEigenvectorsEIGENVECTORSFactorWeightRotateFactor weights for rotationHKPOWER=FactorPatternFactor patterndefaultFactorStructureFactor structureROTATE= any oblique rotationFinalCommunFinal communalitiesdefaultFinalCommunWgtFinal communalities with weightsMETHOD=ML or ALPHAFitMeasuresMeasures of fitMETHOD=MLImageCoefImage coefficientsMETHOD=IMAGEImageCovImage covariance matrixMETHOD=IMAGEImageFactorsImage factor matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInvrese correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typeMETHOD=HARRISNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPatRotated factor patternROTATE= any oblique rotationObliqueTransOblique transformation matrixHKPOWER=OrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthRotFactPatOrthogonal transformationROTATE= any orthogonal rotation<	Corr	Correlations	CORR		
FactorWeightRotate Factor Pattern Factor pattern Factor Structure Final Commun Final communalities Final Commun Final communalities with weights FitMeasures Measures of fit Image Coef Image covariance matrix InputFactorPattern InvCorr InvCorr InvCorr InvCorr Inverse correlation InvCorr Inverse correlation InvCorr InvCorr Inverse correlation InvCorr Squared multiple correlations NObs Number of records and observations, input data type NormObliqueTrans ObliqueRotFactPat OrthRotFactPat OrthRotFactPat Final communalities Final communalities ROTATE= any oblique rotation HETHOD=ML METHOD=ML METHOD=IMAGE METHOD=IMAGE METHOD=PATTERN with PRINT or ALL METHOD=PATTERN with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS default ROTATE= any oblique rotation METHOD=HARRIS AGTATE= any oblique rotation METHOD=HARRIS MOTATE= any oblique rotation METHOD=HARRIS MOTATE= any oblique rotation METHOD=HARRIS AGTATE= any oblique rotation METHOD=HARRIS MOTATE= any oblique rotation METHOD=HARRIS AGTATE= any oblique rotation METHOD=HARRIS AGTATE= any oblique rotation METHOD=MAGE METHOD=HARRIS MET	Eigenvalues	Eigenvalues	default, SCREE		
Factor Pattern Factor Structure Factor Structure Final Commun Final communalities Final Commun Final communalities Final CommunWgt Final communalities with weights FitMeasures Measures of fit Image Coef Image coefficients Image Goor Image covariance matrix Image Factors Image factor matrix Input factor pattern Input factor pattern Input factor correlations InterFactorCorr Interfactor correlation matrix IterHistory MultipleCorr Squared multiple correlations NObs Number of records and observations might with pressure of the factor pattern Oblique Trans Oblique Trans OrthRotFactPat Final communalities WETHOD=ML METHOD=IMAGE METHOD=IMAGE METHOD=PATTERN with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=SCORE with PRINT or ALL METHOD=PRINIT, ALPHA, ML, or ULS METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS METHOD=HARR	Eigenvectors	Eigenvectors	EIGENVECTORS		
FactorStructure FinalCommun Final communalities FinalCommunWgt Final communalities FinalCommunWgt Final communalities FinalCommunWgt Final communalities with weights FitMeasures Measures of fit Image Coef Image coefficients Image Cov Image covariance matrix ImageFactors Image factor matrix Input factor pattern Input factor pattern Input ScoreCoef InterFactorCorr Interfactor correlations InvCorr Inverse correlation matrix IterHistory Iteration history MultipleCorr Squared multiple correlations NObs Number of records and observations, input data type NormObliqueTrans ObliqueRotFactPat Oblique RotFactPat OrthRotFactPat OrthOponal transformation OrthOponal transformation OrthOponal transformation ROTATE= any oblique rotation METHOD=NAGE METHOD=PRINIT, ALPHA, ML, or ULS METHOD=HARRIS METHOD=METHON METHOD=MET	FactorWeightRotate	Factor weights for rotation	HKPOWER=		
FinalCommun Final communalities default FinalCommunWgt Final communalities with weights FitMeasures Measures of fit METHOD=ML ImageCoef Image coefficients METHOD=IMAGE ImageGov Image covariance matrix METHOD=IMAGE ImageFactors Image factor matrix METHOD=IMAGE ImputFactorPattern Input factor pattern METHOD=PATTERN with PRINT or ALL InputScoreCoef Standardized input scoring coefficients InterFactorCorr Interfactor correlations ROTATE= any oblique rotation InvCorr Inverse correlations METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=HARRIS NObs Number of records and observations, input data type NormObliqueTrans Normalized oblique ROTATE= any oblique rotation ObliqueRotFactPat Rotated factor pattern ROTATE= any oblique rotation ObliqueTrans Oblique transformation matrix OrthRotFactPat Rotated factor pattern OrthOgonal transformation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	FactorPattern	Factor pattern	default		
Final CommunWgt Final communalities with weights FitMeasures Measures of fit METHOD=ML ImageCoef Image coefficients METHOD=IMAGE ImageCov Image covariance matrix METHOD=IMAGE ImageFactors Image factor matrix METHOD=IMAGE InputFactorPattern Input factor pattern METHOD=PATTERN with PRINT or ALL InputScoreCoef Standardized input scoring coefficients InterFactorCorr Interfactor correlations ROTATE= any oblique rotation InvCorr Inverse correlations METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=HARRIS NObs Number of records and observations, input data type NormObliqueTrans Normalized oblique ROTATE= any oblique rotation ObliqueRotFactPat Rotated factor pattern ROTATE= any oblique rotation OthOthTrans Orthogonal transformation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	FactorStructure	Factor structure	ROTATE= any oblique rotation		
FitMeasures Measures of fit METHOD=ML ImageCoef Image coefficients METHOD=IMAGE ImageCov Image covariance matrix METHOD=IMAGE ImageFactors Image factor matrix METHOD=IMAGE InputFactorPattern Input factor pattern METHOD=SCORE with PRINT or ALL InputScoreCoef Standardized input scoring METHOD=SCORE with PRINT or ALL InputScoreCoef Interfactor correlations ROTATE= any oblique rotation InvCorr Inverse correlations METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=HARRIS NObs Number of records and observations, input data type NormObliqueTrans Normalized oblique ROTATE= any oblique rotation ObliqueRotFactPat Rotated factor pattern ROTATE= any oblique rotation ObliqueTrans Oblique transformation matrix ObliqueTrans Oblique transformation matrix OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthOffactPat Rotated factor pattern ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	FinalCommun	Final communalities	default		
FitMeasuresMeasures of fitMETHOD=MLImageCoefImage coefficientsMETHOD=IMAGEImageCovImage covariance matrixMETHOD=IMAGEImageFactorsImage factor matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPat ObliqueTransRotated factor patternROTATE= any oblique rotationOrthRotFactPat OrthOgonal transformationROTATE= any orthogonal rotationOrthTransOrthogonal transformationROTATE= any orthogonal rotation	FinalCommunWgt	Final communalities with	METHOD=ML or ALPHA		
ImageCoefImage coefficientsMETHOD=IMAGEImageFactorsImage factor matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPatRotated factor patternROTATE= any oblique rotationObliqueTransOblique transformation matrixHKPOWER=OrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthOgonal transformationROTATE= any orthogonal rotation		weights			
ImageCovImage covariance matrixMETHOD=IMAGEImageFactorsImage factor matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE orNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPatRotated factor patternROTATE= any oblique rotationObliqueTransOblique transformation matrixHKPOWER=OrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthTransOrthogonal transformationROTATE= any orthogonal rotation	FitMeasures	Measures of fit	METHOD=ML		
ImageFactorsImage factor matrixMETHOD=IMAGEInputFactorPatternInput factor patternMETHOD=PATTERN with PRINT or ALLInputScoreCoefStandardized input scoring coefficientsMETHOD=SCORE with PRINT or ALLInterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPat Oblique TransRotated factor patternROTATE= any oblique rotationObliqueTransOblique transformation matrixHKPOWER=OrthRotFactPat OrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthOgonal transformationROTATE= any orthogonal rotation	ImageCoef	Image coefficients	METHOD=IMAGE		
InputFactorPattern Input factor pattern METHOD=PATTERN with PRINT or ALL InputScoreCoef Standardized input scoring coefficients InterFactorCorr Interfactor correlations ROTATE= any oblique rotation InvCorr Inverse correlation matrix ALL IterHistory Iteration history METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=IMAGE or METHOD=HARRIS NObs Number of records and observations, input data type NormObliqueTrans Normalized oblique transformation matrix ObliqueRotFactPat Rotated factor pattern Oblique transformation matrix OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation	ImageCov	Image covariance matrix	METHOD=IMAGE		
InputScoreCoef Standardized input scoring coefficients InterFactorCorr Interfactor correlations InvCorr Inverse correlation matrix IterHistory Iteration history METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=IMAGE or METHOD=HARRIS NObs Number of records and observations, input data type NormObliqueTrans Normalized oblique transformation matrix ObliqueRotFactPat ObliqueTrans Oblique transformation matrix ObliqueTrans ObliqueTrans OrthRotFactPat Rotated factor pattern OrthRotFactPat Orthogonal transformation OrthOgonal transformation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	ImageFactors	Image factor matrix	METHOD=IMAGE		
InterFactorCorr Interfactor correlations ROTATE= any oblique rotation InvCorr Inverse correlation matrix ALL IterHistory Iteration history METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=IMAGE or METHOD=HARRIS NObs Number of records and default observations, input data type NormObliqueTrans Normalized oblique ROTATE= any oblique rotation transformation matrix ObliqueRotFactPat Rotated factor pattern ROTATE= any oblique rotation ObliqueTrans Oblique transformation matrix OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation	InputFactorPattern	Input factor pattern	METHOD=PATTERN with PRINT or ALL		
InterFactorCorrInterfactor correlationsROTATE= any oblique rotationInvCorrInverse correlation matrixALLIterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPatRotated factor patternROTATE= any oblique rotationObliqueTransOblique transformation matrixHKPOWER=OrthRotFactPatRotated factor patternROTATE= any orthogonal rotationOrthTransOrthogonal transformationROTATE= any orthogonal rotation	InputScoreCoef	,	METHOD=SCORE with PRINT or ALL		
InvCorr Inverse correlation matrix IterHistory Iteration history METHOD=PRINIT, ALPHA, ML, or ULS MultipleCorr Squared multiple correlations METHOD=IMAGE or METHOD=HARRIS NObs Number of records and observations, input data type NormObliqueTrans Normalized oblique rotation transformation matrix ObliqueRotFactPat Rotated factor pattern Oblique transformation matrix OrthRotFactPat Rotated factor pattern ROTATE= any oblique rotation HKPOWER= OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation	InterFactorCorr		ROTATE= any oblique rotation		
IterHistoryIteration historyMETHOD=PRINIT, ALPHA, ML, or ULSMultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPat ObliqueTransRotated factor pattern Oblique transformation matrixROTATE= any oblique rotationOrthRotFactPat OrthRotFactPatRotated factor patternHKPOWER=OrthRotFactPat OrthOgonal transformationROTATE= any orthogonal rotationROTATE= any orthogonal rotation			· -		
MultipleCorrSquared multiple correlationsMETHOD=IMAGE or METHOD=HARRISNObsNumber of records and observations, input data typedefaultNormObliqueTransNormalized oblique transformation matrixROTATE= any oblique rotationObliqueRotFactPat ObliqueTransRotated factor patternROTATE= any oblique rotationObliqueTransOblique transformation matrixHKPOWER=OrthRotFactPat Rotated factor patternROTATE= any orthogonal rotationOrthTransOrthogonal transformationROTATE= any orthogonal rotation					
NObs Number of records and default observations, input data type NormObliqueTrans Normalized oblique transformation matrix ObliqueRotFactPat ObliqueTrans Oblique transformation matrix ObliqueTrans Oblique transformation matrix ObliqueTrans OrthRotFactPat OrthRotFactPat OrthOgonal transformation OrthOgonal transformation OrthOgonal transformation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	· · · · · · · · · · · · · · · · · · ·				
NormObliqueTrans Normalized oblique ROTATE= any oblique rotation transformation matrix ObliqueRotFactPat ObliqueTrans ObliqueTrans Oblique transformation matrix ObliqueTrans OrthRotFactPat Rotated factor pattern OrthRotFactPat Orthogonal transformation Orthogonal transformation ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	1	1			
NormObliqueTrans Normalized oblique transformation matrix ObliqueRotFactPat ObliqueTrans Oblique transformation matrix ObliqueTrans OrthRotFactPat OrthRotFactPat OrthOgonal transformation OrthOgonal transformation OrthOgonal transformation ROTATE= any oblique rotation HKPOWER= ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	NObs	Number of records and	default		
transformation matrix ObliqueRotFactPat Rotated factor pattern ROTATE= any oblique rotation ObliqueTrans Oblique transformation matrix OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation		observations, input data type			
transformation matrix ObliqueRotFactPat Rotated factor pattern ROTATE= any oblique rotation ObliqueTrans Oblique transformation matrix OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation	NormObliqueTrans	Normalized oblique	ROTATE= any oblique rotation		
Oblique Trans Oblique transformation matrix OrthRotFactPat OrthTrans Orthogonal transformation OrthOgonal transformation HKPOWER= ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	•	transformation matrix	•		
Oblique Trans Oblique transformation matrix OrthRotFactPat OrthTrans Orthogonal transformation OrthOgonal transformation HKPOWER= ROTATE= any orthogonal rotation ROTATE= any orthogonal rotation	ObliqueRotFactPat	Rotated factor pattern	ROTATE= any oblique rotation		
OrthRotFactPat Rotated factor pattern ROTATE= any orthogonal rotation OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation	ObliqueTrans	•	• •		
OrthTrans Orthogonal transformation ROTATE= any orthogonal rotation	_	•	ROTATE= any orthogonal rotation		
maurx		_	•		

Table 37.6 continued

ODS Table Name	Description	Option
	<u> </u>	
ParCorrControlFactor	Partial correlations controlling	RESIDUAL
ParCorrControlVar	factors Doutiel completions controlling	MSA
Parconcontrol vai	Partial correlations controlling other variables	WSA
PartialCorr	Partial correlations	MSA, CORR with PARTIAL
PriorCommunalEst	Prior communality estimates	PRIORS=, METHOD=ML or ALPHA
Procrustes Target	Target matrix for Procrustean	ROTATE=PROCRUSTES,
1 Toctustes Target	transformation	ROTATE=PROMAX
ProcrustesTrans	Procrustean transformation	ROTATE=PROCRUSTES,
1 Toctustes Trains	matrix	ROTATE=PROMAX
RMSOffDiagPartials	Root mean square off-diagonal	RESIDUAL
	partials	
RMSOffDiagResids	Root mean square off-diagonal	RESIDUAL
Č	residuals	
ReferenceAxisCorr	Reference axis correlations	ROTATE= any oblique rotation
ReferenceStructure	Reference structure	ROTATE= any oblique rotation
ResCorrUniqueDiag	Residual correlations with	RESIDUAL
	uniqueness on the diagonal	
SamplingAdequacy	Kaiser's measure of sampling	MSA
	adequacy	
SignifTests	Significance tests	METHOD=ML
SimpleStatistics	Simple statistics	SIMPLE
StdScoreCoef	Standardized scoring	SCORE
	coefficients	
VarExplain	Variance explained	default
VarExplainWgt	Variance explained with	METHOD=ML, or ALPHA
	weights	9997
VarFactorCorr	Squared multiple correlations	SCORE
VariateDatate	of the variables with each factor	NODM WEIGHT DOTATE
VarWeightRotate	Variable weights for rotation	NORM=WEIGHT, ROTATE=

ODS Graphics

Statistical procedures use ODS Graphics to create graphs as part of their output. ODS Graphics is described in detail in Chapter 21, "Statistical Graphics Using ODS."

Before you create graphs, ODS Graphics must be enabled (for example, by specifying the ODS GRAPH-ICS ON statement). For more information about enabling and disabling ODS Graphics, see the section "Enabling and Disabling ODS Graphics" on page 606 in Chapter 21, "Statistical Graphics Using ODS."

The overall appearance of graphs is controlled by ODS styles. Styles and other aspects of using ODS Graphics are discussed in the section "A Primer on ODS Statistical Graphics" on page 605 in Chapter 21, "Statistical Graphics Using ODS."

The names of the graphs that PROC FACTOR generates are listed in Table 37.7, along with the required statements and options.

Table 37.7 Graphs Produced by PROC FACTOR

ODS Graph Name	Plot Description	Option
InitPatternPlot	Initial factor pattern	PLOTS=INITLOADINGS
InitRefStructurePlot	Initial reference structures	PLOTS=INITLOADINGS and
		PLOTREF
PathDiagram	Path diagram	PLOTS=PATHDIAGRAM or
		PATHDIAGRAM statement
PatternPlot	Rotated factor pattern	PLOTS=LOADINGS
PrePatternPlot	Prerotated factor pattern	PLOTS=PRELOADINGS
PreRefStructurePlot	Prerotated reference structures	PLOTS=PRELOADINGS and
		PLOTREF
RefStructurePlot	Rotated reference structures	PLOTS=LOADINGS and
		PLOTREF
ScreePlot	Scree and variance explained plots	PLOTS=SCREE
VariancePlot	Plot of explained variance	PLOTS=SCREE(UNPACK)

Examples: FACTOR Procedure

Example 37.1: Principal Component Analysis

This example analyzes socioeconomic data provided by Harman (1976). The five variables represent total population (Population), median school years (School), total employment (Employment), miscellaneous professional services (Services), and median house value (HouseValue). Each observation represents one of twelve census tracts in the Los Angeles Standard Metropolitan Statistical Area.

You conduct a principal component analysis by using the following statements:

```
data SocioEconomics;
   input Population School Employment Services HouseValue;
   datalines;
5700
         12.8
                    2500
                               270
                                         25000
         10.9
                               10
1000
                    600
                                         10000
3400
         8.8
                    1000
                               10
                                         9000
         13.6
                    1700
                              140
                                         25000
3800
         12.8
                              140
4000
                    1600
                                         25000
         8.3
                               60
8200
                    2600
                                         12000
         11.4
                              10
1200
                    400
                                         16000
         11.5
                               60
9100
                    3300
                                         14000
9900
         12.5
                    3400
                              180
                                         18000
         13.7
                               390
                                         25000
9600
                    3600
9600
         9.6
                    3300
                               80
                                         12000
9400
         11.4
                    4000
                               100
                                         13000
proc factor data=SocioEconomics simple corr;
```

run;

You begin with the specification of the raw data set with 12 observations. Then you use the DATA= option in the PROC FACTOR statement to specify the data set in the analysis. You also set the SIMPLE and CORR options for additional output results, which are shown in Output 37.1.2 and Output 37.1.3, respectively.

By default, PROC FACTOR assumes that all initial communalities are 1, which is the case for the current principal component analysis. If you intend to find common factors instead, use the PRIORS= option or the PRIORS statement to set initial communalities to values less than 1, which results in extracting the principal factors rather than the principal components. See Example 37.2 for the specification of a principal factor analysis.

For the current principal component analysis, the first output table is displayed in the Output 37.1.1.

Five Socioeconomic Variables See Page 14 of Harman: Modern Factor Analysis, 3rd Ed Principal Component Analysis

The FACTOR Procedure

Input Data Type	Raw Data
Number of Records Read	12
Number of Records Used	12
N for Significance Tests	12

In Output 37.1.1, the input data type is shown to be raw data. PROC FACTOR also accepts other data type such as correlations and covariances. See Example 37.4 for the use of correlations as input data. For the current raw data set, PROC FACTOR reads in 12 records and all these 12 records are used. When there are missing values in the data set, these two numbers might not match due to the dropping of the records with missing values. The last row of the table shows that N = 12 is used in the significance tests conducted in the analysis.

The SIMPLE option specified in the PROC FACTOR statement generates the means and standard deviations of all observed variables in the analysis, as shown in Output 37.1.2.

Output 37.1.2 Principal Component Analysis: Simple Statistics

Means and Standard Deviations from 12 Observations				
Variable Mean Std Dev				
Population	6241.667	3439.9943		
School	11.442	1.7865		
Employment	2333.333	1241.2115		
Services	120.833	114.9275		
HouseValue 17000.000 6367.5313				

The ranges of means and standard deviations for the analysis are quite large. Variables are measured on quite different scales. However, this is not an issue because PROC FACTOR basically analyzes the standardized scales (that is, the correlations) of the variables.

The CORR option specified in the PROC FACTOR statement generates the output of the observed correlations in Output 37.1.3.

Output 37.1.3 Principal Component Analysis: Correlations

Correlations					
	Population	School	Employment	Services	HouseValue
Population	1.00000	0.00975	0.97245	0.43887	0.02241
School	0.00975	1.00000	0.15428	0.69141	0.86307
Employment	0.97245	0.15428	1.00000	0.51472	0.12193
Services	0.43887	0.69141	0.51472	1.00000	0.77765
HouseValue	0.02241	0.86307	0.12193	0.77765	1.00000

The correlation matrix shown in Output 37.1.3 is analyzed by PROC FACTOR.

The first step of principal component analysis is to look at the eigenvalues of the correlation matrix. The larger eigenvalues are extracted first. Because there are five observed variables, five eigenvalues can be extracted, as shown in Output 37.1.4.

Output 37.1.4 Principal Component Analysis: Eigenvalues

Eigenvalues of the Correlation Matrix: Total = 5 Average = 1				
Eigenvalue	Difference	Proportion	Cumulative	
1 2.87331359	1.07665350	0.5747	0.5747	
2 1.79666009	1.58182321	0.3593	0.9340	
3 0.21483689	0.11490283	0.0430	0.9770	
4 0.09993405	0.08467868	0.0200	0.9969	
5 0.01525537		0.0031	1.0000	

In Output 37.1.4, the two largest eigenvalues are 2.8733 and 1.7967, which together account for 93.4% of the standardized variance. Thus, the first two principal components provide an adequate summary of the data for most purposes. Three components, which explain 97.7% of the variation, should be sufficient for almost any application. PROC FACTOR retains the first two components on the basis of the eigenvalues-greater-than-one rule since the third eigenvalue is only 0.2148.

To express the observed variables as functions of the components (or factors, in general), you consult the factor loading matrix as shown in Output 37.1.5.

Output 37.1.5 Principal Component Analysis: Factor Pattern

Factor Pattern				
	Factor1	Factor2		
Population	0.58096	0.80642		
School	0.76704	-0.54476		
Employment	0.67243	0.72605		
Services	0.93239	-0.10431		
HouseValue	0.79116	-0.55818		

The factor pattern is often referred to as the factor loading matrix in factor analysis. The elements in the loading matrix are called factor loadings. There are at least two ways you can interpret these factor loadings. First, you can use this table to express the observed variables as functions of the extracted factors (or components, as in the current analysis). Each row of the factor loadings tells you the linear combination of the factor or component scores that would yield the expected value of the associated variable. Second, you can interpret each loading as a correlation between an observed variable and a factor or component, provided that the factor solution is an orthogonal one (that is, factors are uncorrelated), such as the current initial factor solution. Hence, the factor loadings indicate how strongly the variables and the factors or components are related.

In Output 37.1.5, the first component (labeled "Factor1") has large positive loadings for all five variables. Its correlation with Services (0.9324) is especially high. The second component is basically a contrast of Population (0.8064) and Employment (0.7261) against School (-0.5448) and HouseValue (-0.5582), with a very small loading on Services (-0.1043).

The total variance explained by the two components are shown in Output 37.1.6.

Output 37.1.6 Principal Component Analysis: Total Variance Explained by Factors

Variance Explained by Each Factor Factor1 Factor2 2.8733136 1.7966601

The first and second component account for 2.8733 and 1.7967, respectively, of the total variance of 5. In the initial factor solution, the total variance explained by the factors or components are the same as the eigenvalues extracted. (Compare the total variance with the eigenvalues shown in Output 37.1.4.) Due to the dropping of the less important components, the sum of these two numbers is 4.6700, which is only a little bit less than total variance 5 of the original correlation matrix.

You can also look at the variance explained by the two components for each observed variables in Output 37.1.7.

Output 37.1.7 Principal Component Analysis: Final Communality Estimates

Fina	al Communa	lity Estimates:	Total = 4.66	9974
Population	School	Employment	Services	HouseValue
0.98782629	0.88510555	0.97930583	0.88023562	0.93750041

In Output 37.1.7, the final communality estimates show that all the variables are well accounted for by the two components, with final communality estimates ranging from 0.8802 for Services to 0.9878 for Population. The sum of the communalities is 4.6700, which is the same as the sum of the variance explained by the two components, as shown in Output 37.1.6.

Principal Component Analysis by PROC FACTOR and PROC PRINCOMP

The principal component analysis by PROC FACTOR emphasizes how the principal components explain the observed variables. The factor loadings in the factor pattern as shown in Output 37.1.5 are the coefficients for combining the factor/component scores to yield the observed variable scores when the expected error residuals are zero. For example, the predicted standardized value of Population given the factor/component scores for Factor1 and Factor2 is given by:

```
Population = 0.58096 \times \text{Factor1} + 0.80642 \times \text{Factor2}
```

If you are primarily interested in getting the component scores as linear combinations of the observed variables, the factor loading matrix table is not the right one for you. However, you might request the standardized scoring coefficients by adding the SCORE option in the FACTOR statement:

```
proc factor data=SocioEconomics n=5 score;
run;
```

In the preceding PROC FACTOR statement, N=5 is specified for retaining all five components. This is done for comparing the PROC FACTOR results with those of PROC PRINCOMP, which is described later. The SCORE option requests the display of the standardized scoring coefficients, which are shown in Output 37.1.8.

Output 37.1.8 Principal Component Analysis: Scoring Coefficients for Computing Component Scores

	Stand	lardized Sco	ring Coeffici	ents	
	Factor1	Factor2	Factor3	Factor4	Factor5
Population	0.20219065	0.44884459	0.1284067	0.64542101	5.58240225
School	0.26695219	-0.3032049	1.48611655	-1.1184573	1.41573501
Employment	0.23402646	0.40410834	0.53496241	0.07255759	-5.6513542
Services	0.32450082	-0.0580552	-1.432726	-1.5828806	-0.0010006
HouseValue	0.27534803	-0.3106762	-0.3012889	2.41418899	-0.6673445

In Output 37.1.8, each factor/component is expressed as a linear combination of the standardized observed variables. For example, the first principal component or Factor1 is computed as:

 $0.2022 \times Population + 0.2670 \times School + 0.2340 \times Employment + 0.3245 \times Services + 0.2753 \times House Value$

Again, when applying this formula you must use the standardized observed variables (with means 0 and standard deviations 1), but not the raw data.

Apart from some scaling differences, the set of scoring coefficients obtained from PROC FACTOR are equivalent to those obtained from PROC PRINCOMP, as specified by the following statement:

proc princomp data=SocioEconomics; run;

PROC PRINCOMP displays the scoring coefficients as eigenvectors, which are shown in Output 37.1.9.

Output 37.1.9 Principal Component Analysis by PROC PRINCOMP: Eigenvectors

		Eigenve	ctors		
	Prin1	Prin2	Prin3	Prin4	Prin5
Population	0.342730	0.601629	0.059517	0.204033	0.689497
School	0.452507	406414	0.688822	353571	0.174861
Employment	0.396695	0.541665	0.247958	0.022937	698014
Services	0.550057	077817	664076	500386	000124
HouseValue	0.466738	416429	139649	0.763182	082425

For example, to get the first principal component score, you use the following formula:

 $0.3427 \times Population + 0.4525 \times School + 0.3967 \times Employment + 0.5500 \times Services + 0.4667 \times House Value$

This formula is not exactly the same as the one shown by using PROC FACTOR. All scoring coefficients in PROC FACTOR are smaller, approximately a factor of 0.59 to those coefficients obtained from PROC PRINCOMP. The reason for the scalar difference is that PROC FACTOR assumes all factors/components to have variance of 1, while PROC PRINCOMP creates components that have variances equal to the eigenvalues. You can do a simple rescaling of the standardized scoring coefficients obtained from PROC FACTOR so that they match the associated eigenvectors from the PROC PRINCOMP. Basically, you need to rescale each column of the standardized scoring coefficients obtained from PROC FACTOR to have the sum of squares equaling one, which is a defining characteristic of eigenvectors. This could be accomplished by dividing each coefficient by the square root of the corresponding column sum of squares.

For the present example, you can use PROC STDIZE to do the rescaling, as shown in the following statements:

```
proc factor data=SocioEconomics n=5 score;
   ods output StdScoreCoef=Coef;
run;

proc stdize method=ustd mult=.44721 data=Coef out=eigenvectors;
   Var Factor1-Factor5;
run;

proc print data=eigenvectors;
run;
```

First, you create an output set Coef for the standardized scoring coefficients by the ODS OUTPUT statement. Note that "StdScoreCoef" is the ODS table that contains the standardized scoring coefficients as shown in Output 37.1.8. (See Table 37.6 for all ODS table names for PROC FACTOR.) Next, you use METHOD=USTD in the PROC STDIZE statement to divide the output coefficients by the corresponding uncorrected (for mean) standard deviations. The following formula shows the relationship between the uncorrected standard deviation and the sum of squares:

```
uncorrected standard deviation = \sqrt{\text{sum of squares}/N}
```

Recall that what you intend to divide from each coefficient is its square root of the corresponding column sum of squares. Therefore, to adjust for what PROC STDIZE does using METHOD=USTD, you have to multiply each variable by a constant term of $1/\sqrt{N}$ in the standardization. For the current example, this constant term is 0.44721 (= $1/\sqrt{5}$) and is specified through the MULT= option in the PROC STDIZE statement. With the OUT= option, the rescaled scoring coefficients are saved in the SAS data set eigenvectors. The printout of the data set in Output 37.1.10 shows the rescaled standardized scoring coefficients obtained from PROC FACTOR.

Output 37.1.10 Rescaled Standardized Scoring Coefficients

Obs	Variable	Factor1	Factor2	Factor3	Factor4	Factor5
1	Population	0.34272761	0.60162443	0.05951667	0.20403109	0.68949172
2	School	0.45250304	-0.4064112	0.68881691	-0.3535678	0.17485977
3	Employment	0.39669158	0.54166065	0.24795576	0.02293697	-0.6980081
4	Services	0.5500521	-0.0778162	-0.6640703	-0.5003817	-0.0001236
5	HouseValue	0.4667346	-0.4164256	-0.1396478	0.76317568	-0.0824248

As you can see, these standardized scoring coefficients are essentially the same as those obtained from PROC PRINCOMP, as shown in Output 37.1.9. This example shows that principal component analyses by PROC FACTOR and PROC PRINCOMP are indeed equivalent. PROC PRINCOMP emphasizes more the linear combinations of the variables to form the components, while PROC FACTOR expresses variables as linear combinations of the components in the output. If a principal component analysis of the data is all you need in a particular application, there is no reason to use PROC FACTOR instead of PROC PRINCOMP. Therefore, the following examples focus on common factor analysis for which that you can apply only PROC FACTOR, but not PROC PRINCOMP.

Example 37.2: Principal Factor Analysis

This example uses the data presented in Example 37.1 and performs a principal factor analysis with squared multiple correlations for the prior communality estimates. Unlike Example 37.1, which analyzes the principal components (with default PRIORS=ONE), the current analysis is based on a common factor model. To use a common factor model, you specify PRIORS=SMC in the PROC FACTOR statement, as shown in the following:

```
ods graphics on;
proc factor data=SocioEconomics
   priors=smc msa residual
   rotate=promax reorder
   outstat=fact_all
   plots=(scree initloadings preloadings loadings);
run;
ods graphics off;
```

In the PROC FACTOR statement, you include several other options to help you analyze the results. To help determine whether the common factor model is appropriate, you request the Kaiser's measure of sampling adequacy with the MSA option. You specify the RESIDUALS option to compute the residual correlations and partial correlations.

The ROTATE= and REORDER options are specified to enhance factor interpretability. ROTATE=PROMAX option produces an orthogonal varimax prerotation (default) followed by an oblique Procrustes rotation, and the REORDER option reorders the variables according to their largest factor loadings. An OUTSTAT= data set is created by PROC FACTOR and displayed in Output 37.2.15.

PROC FACTOR can produce high-quality graphs that are very useful for interpreting the factor solutions. To request these graphs, ODS Graphics must be enabled. All ODS graphs in PROC FACTOR are requested with the PLOTS= option. In this example, you request a scree plot (SCREE) and loading plots for the factor matrix during the following three stages: initial unrotated solution (INITLOADINGS), prerotated (varimax) solution (PRELOADINGS), and promax-rotated solution (LOADINGS). The scree plot helps you determine the number of factors, and the loading plots help you visualize the patterns of factor loadings during various stages of analyses.

Principal Factor Analysis: Kaiser's MSA and Factor Extraction Results

Output 37.2.1 displays the results of the partial correlations and Kaiser's measure of sampling adequacy.

Output 37.2.1 Principal Factor Analysis: Partial Correlations and Kaiser's MSA

Pa	rtial Correlat	ions Con	trolling all oth	er Variable	es
	Population	School	Employment	Services	HouseValue
Population	1.00000	-0.54465	0.97083	0.09612	0.15871
School	-0.54465	1.00000	0.54373	0.04996	0.64717
Employment	0.97083	0.54373	1.00000	0.06689	-0.25572
Services	0.09612	0.04996	0.06689	1.00000	0.59415
HouseValue	0.15871	0.64717	-0.25572	0.59415	1.00000

Output 37.2.1 continued

 Kaiser's Measure of Sampling Adequacy:

 Overall MSA = 0.57536759

 Population
 School
 Employment
 Services
 HouseValue

 0.47207897
 0.55158839
 0.48851137
 0.80664365
 0.61281377

If the data are appropriate for the common factor model, the partial correlations (controlling all other variables) should be small compared to the original correlations. For example, the partial correlation between the variables School and HouseValue is 0.65, slightly less than the original correlation of 0.86 (see Output 37.1.3). The partial correlation between Population and School is -0.54, which is much larger in absolute value than the original correlation; this is an indication of trouble. Kaiser's MSA is a summary, for each variable and for all variables together, of how much smaller the partial correlations are than the original correlations. Values of 0.8 or 0.9 are considered good, while MSAs below 0.5 are unacceptable. The variables Population, School, and Employment have very poor MSAs. Only the Services variable has a good MSA. The overall MSA of 0.58 is sufficiently poor that additional variables should be included in the analysis to better define the common factors. A commonly used rule is that there should be at least three variables per factor. In the following analysis, you determine that there are two common factors in these data. Therefore, more variables are needed for a reliable analysis.

Output 37.2.2 displays the results of the principal factor extraction.


Output 37.2.2 Principal Factor Analysis: Factor Extraction

	Prior Co	mmunality E	stimates: SN	IC
Populatio	n Schoo	ol Employm	ent Servic	es HouseValu
0.9685916	0.8222851	4 0.969180	082 0.785724	l40 0.8470192°
Ei	genvalues o			
	Total = 4.39	280116 Ave	rage = 0.8785	56023
	Eigenvalue	Difference	Proportion	Cumulative
1	2.73430084	1.01823217	0.6225	0.6225
2	1.71606867	1.67650586	0.3907	1.0131
3	0.03956281	0.06408626	0.0090	1.0221
4	02452345	0.04808427	-0.0056	1.0165
5	07260772		-0.0165	1.0000

The square multiple correlations are shown as prior communality estimates in Output 37.2.2. The PRI-ORS=SMC option basically replaces the diagonal of the original observed correlation matrix by these square multiple correlations. Because the square multiple correlations are usually less than one, the resulting correlation matrix for factoring is called the reduced correlation matrix. In the current example, the SMCs are all fairly large; hence, you expect the results of the principal factor analysis to be similar to those in the principal component analysis.

The first two largest positive eigenvalues of the reduced correlation matrix account for 101.31% of the common variance. This is possible because the reduced correlation matrix, in general, is not necessarily positive definite, and negative eigenvalues for the matrix are possible. A pattern like this suggests that you might not need more than two common factors. The scree and variance explained plots of Output 37.2.3 clearly support the conclusion that two common factors are present. Showing in the left panel of Output 37.2.3 is the scree plot of the eigenvalues of the reduced correlation matrix. A sharp bend occurs at the third eigenvalue,

reinforcing the conclusion that two common factors are present. These cumulative proportions of common variance explained by factors are plotted in the right panel of Output 37.2.3, which shows that the curve essentially flattens out after the second factor.



Output 37.2.3 Scree and Variance Explained Plots

Principal Factor Analysis: Initial Factor Solution

For the current analysis, PROC FACTOR retains two factors by certain default criteria. This decision agrees with the conclusion drawn by inspecting the scree plot. The principal factor pattern with the two factors is displayed in Output 37.2.4. This factor pattern is similar to the principal component pattern seen in Output 37.1.5 of Example 37.1. For example, the variable Services has the largest loading on the first factor, and the Population variable has the smallest. The variables Population and Employment have large positive loadings on the second factor, and the HouseValue and School variables have large negative loadings.

Output 37.2.4	initial factor Pattern Matrix and Communalities

Facto	or Pattern	า
	Factor1	Factor2
Services	0.87899	-0.15847
HouseValue	0.74215	-0.57806
Employment	0.71447	0.67936
School	0.71370	-0.55515
Population	0.62533	0.76621

Output 37.2.4 continued

Variance Explained by Each Factor Factor1 Factor2 2.7343008 1.7160687

Fina	al Communa	lity Estimates:	Total = 4.45	0370
Population	School	Employment	Services	HouseValue
0.97811334	0.81756387	0.97199928	0.79774304	0.88494998

Comparing the current factor loading matrix in Output 37.2.4 with that in Output 37.1.5 in Example 37.1, you notice that the variables are arranged differently in the two output tables. This is due to the use of the REORDER option in the current analysis. The advantage of using this option might not be very obvious in Output 37.2.4, but you can see its value when looking at the rotated solutions, as shown in Output 37.2.7 and Output 37.2.11.

The final communality estimates are all fairly close to the priors (shown in Output 37.2.2). Only the communality for the variable HouseValue increased appreciably, from 0.847 to 0.885. Therefore, you are sure that all the common variance is accounted for.

Output 37.2.5 shows that the residual correlations (off-diagonal elements) are low, the largest being 0.03. The partial correlations are not quite as impressive, since the uniqueness values are also rather small. These results indicate that the squared multiple correlations are good but not quite optimal communality estimates.

Output 37.2.5 Residual and Partial Correlations

Resid	ual Correlati	ons With	Uniqueness o	n the Diag	gonal
	Population	School	Employment	Services	HouseValue
Population	0.02189	-0.01118	0.00514	0.01063	0.00124
School	-0.01118	0.18244	0.02151	-0.02390	0.01248
Employment	0.00514	0.02151	0.02800	-0.00565	-0.01561
Services	0.01063	-0.02390	-0.00565	0.20226	0.03370
HouseValue	0.00124	0.01248	-0.01561	0.03370	0.11505

 Root Mean Square Off-Diagonal Residuals:

 Overall = 0.01693282

 Population
 School
 Employment
 Services
 HouseValue

 0.00815307
 0.01813027
 0.01382764
 0.02151737
 0.01960158


	Partial Co	rrelations	Controlling F	actors	
	Population	School	Employment	Services	HouseValue
Population	1.00000	-0.17693	0.20752	0.15975	0.02471
School	-0.17693	1.00000	0.30097	-0.12443	0.08614
Employment	0.20752	0.30097	1.00000	-0.07504	-0.27509
Services	0.15975	-0.12443	-0.07504	1.00000	0.22093
HouseValue	0.02471	0.08614	-0.27509	0.22093	1.00000

 Root Mean Square Off-Diagonal Partials: Overall = 0.18550132

 Population
 School
 Employment
 Services
 HouseValue

 0.15850824
 0.19025867
 0.23181838
 0.15447043
 0.18201538

As displayed in Output 37.2.6, the unrotated factor pattern reveals two tight clusters of variables, with the variables HouseValue and School at the negative end of Factor2 axis and the variables Employment and Population at the positive end. The Services variable is in between but closer to the HouseValue and School variables. A good rotation would place the axes so that most variables would have zero loadings on most factors. As a result, the axes would appear as though they are put through the variable clusters.



Output 37.2.6 Unrotated Factor Loading Plot

Principal Factor Analysis: Varimax Prerotation

In Output 37.2.7, the results of the varimax prerotation are shown. To yield the varimax-rotated factor loading (pattern), the initial factor loading matrix is postmultiplied by an orthogonal transformation matrix. This orthogonal transformation matrix is shown in Output 37.2.7, followed by the varimax-rotated factor pattern. This rotation or transformation leads to small loadings of Population and Employment on the first factor and small loadings of HouseValue and School on the second factor. Services appears to have a larger loading on the first factor than it has on the second factor, although both loadings are substantial. Hence, Services appears to be factorially complex.

With the REORDER option in effect, you can see the variable clusters clearly in the factor pattern. The first factor is associated more with the first three variables (first three rows of variables): HouseValue, School, and Services. The second factor is associated more with the last two variables (last two rows of variables): Population and Employment.

For orthogonal factor solutions such as the current varimax-rotated solution, you can also interpret the values in the factor loading (pattern) matrix as correlations. For example, HouseValue and Factor 1 have a high correlation at 0.94, while Population and Factor 1 have a low correlation at 0.02.

Output 37.2.7 Varimax Rotation: Transform Matrix and Rotated Pattern

	Trans	Orth sforn	ogor natio		atrix	
			1		2	2
	1	0.78	8895	0.6	51446	5
	2	-0.6	1446	0.7	8895	5
	Rotat	ted F	actor	Pa	ttern	
		ı	Facto	or1	Fac	tor2
	HouseVa	lue	0.940	72	-0.00	0004
	School	(0.904	19	0.00	0055
	Services		0.790	85	0.4	1509
	Populatio	on	0.022	55	0.98	3874
	Employm	nent	0.146	25	0.97	7499
		riance y Eac				
	Fa	actor	1 F	-ac	tor2	
	2.34	9856	7 2.1	005	128	
Final	l Communali	ity Es	stima	tes	Tota	al = 4.
Population	School	Emp	loym	ent	S	ervic
0.97811334	0.81756387	0.97	71999	928	0.79	7743

The variance explained by the factors are more evenly distributed in the varimax-rotated solution, as compared with that of the unrotated solution. Indeed, this is a typical fact for any kinds of factor rotation. In the current example, before the varimax rotation the two factors explain 2.73 and 1.72, respectively, of the common variance (see Output 37.2.4). After the varimax rotation the two rotated factors explain 2.35 and 2.10, respectively, of the common variance. However, the total variance accounted for by the factors remains unchanged after the varimax rotation. This invariance property is also observed for the communalities of the variables after the rotation, as evidenced by comparing the current communality estimates in Output 37.2.7 with those in Output 37.2.4.

Output 37.2.8 shows the graphical plot of the varimax-rotated factor loadings. Clearly, HouseValue and School cluster together on the Factor 1 axis, while Population and Employment cluster together on the Factor 2 axis. Service is closer to the cluster of HouseValue and School.


Prerotated Factor Pattern Employment Population 1.0 8.0 0.6 Services 0.4 Factor 2 (47.2%) 0.2 0.0 -0.2 -0.4 -0.6 -0.8 -1.0 -0.8 -0.6 -0.4 -0.2 0.0 0.2 0.4 0.6 0.8 1.0 Factor 1 (52.8%)

Output 37.2.8 Varimax-Rotated Factor Loadings

An alternative to the scatter plot of factor loadings is the so-called vector plot of loadings, which is shown in Output 37.2.9. The vector plot is requested with the suboption VECTOR in the PLOTS= option. That is:

plots=preloadings(vector)

This generates the vector plot of loadings in Output 37.2.9.



Output 37.2.9 Varimax-Rotated Factor Loadings: Vector Plot

Principal Factor Analysis: Oblique Promax Rotation

For some researchers, the varimax-rotated factor solution in the preceding section might be good enough to provide them useful and interpretable results. For others who believe that common factors are seldom orthogonal, an obliquely rotated factor solution might be more desirable, or at least should be attempted.

PROC FACTOR provides a very large class of oblique factor rotations. The current example shows a particular one—namely, the promax rotation as requested by the ROTATE=PROMAX option.

The results of the promax rotation are shown in Output 37.2.10 and Output 37.2.11. The corresponding plot of factor loadings is shown in Output 37.2.12.

Output 37.2.10 Promax Rotation: Procrustean Target and Transformation

Target Matrix for Procrustean Transformation					
		Factor	l Facto	r2	
Ho	useValue	1.00000	0.000	00	
Sch	nool	1.00000	0.000	00	
Ser	vices	0.6942	0.100	45	
Pop	oulation	0.0000	1 1.000	00	
Em	ployment	0.00326	0.967	93	
				_	
Pr	ocrustean	ı Transf Matrix	ormatio	n	
		1		2	
1	1 0411		0.098653		
2			.963030 ⁻	-	
_	0.103	7220 0.	.505050	_	
Normalized Oblique Transformation Matrix					
1 2					
	1 0	73803 (
	-	70555 (
		, 0555	7.00320		

Output 37.2.10 shows the Procrustean target, to which the varimax factor pattern is rotated, followed by the display of the Procrustean transformation matrix. This is the matrix that transforms the varimax factor pattern so that the rotated pattern is as close as possible to the Procrustean target. However, because the variances of factors have to be fixed at 1 during the oblique transformation, a normalized version of the Procrustean transformation matrix is the one that is actually used in the transformation. This normalized transformation matrix is shown at the bottom of Output 37.2.10. Using this transformation matrix leads to the promax-rotated factor solution, as shown in Output 37.2.11.

Output 37.2.11 Promax Rotation: Factor Correlations and Factor Pattern


Inter-Factor Correlations			
	Factor1	Factor2	
Factor1	1.00000	0.20188	
Factor2	0.20188	1.00000	

Rotated Factor Pattern (Standardized Regression Coefficients)				
	Factor1	Factor2		
HouseValue	0.95558485	-0.0979201		
School	0.91842142	-0.0935214		
Services	0.76053238	0.33931804		
Population	-0.0790832	1.00192402		
Employment	0.04799	0.97509085		

After the promax rotation, the factors are no longer uncorrelated. As shown in Output 37.2.11, the correlation of the two factors is now 0.20. In the (initial) unrotated and the varimax solutions, the two factors are not correlated.

In addition to allowing the factors to be correlated, in an oblique factor solution you seek a pattern of factor loadings that is more "differentiated" (referred to as the "simple structures" in the literature). The more differentiated the loadings, the easier the interpretation of the factors.

For example, factor loadings of Services and Population on Factor 2 are 0.415 and 0.989, respectively, in the (orthogonal) varimax-rotated factor pattern (see Output 37.2.7). With the (oblique) promax rotation (see Output 37.2.11), these two loadings become even more differentiated with values 0.339 and 1.002, respectively. Overall, however, the factor patterns before and after the promax rotation do not seem to differ too much. This fact is confirmed by comparing the graphical plots of factor loadings. The plots in Output 37.2.12 (promax-rotated factor loadings) and Output 37.2.8 (varimax-rotated factor loadings) show very similar patterns.



Output 37.2.12 Promax Rotation: Factor Loading Plot

Unlike the orthogonal factor solutions where you can interpret the factor loadings as correlations between variables and factors, in oblique factor solutions such as the promax solution, you have to turn to the factor structure matrix for examining the correlations between variables and factors. Output 37.2.13 shows the factor structures of the promax-rotated solution.

Output 37.2.13 Promax Rotation: Factor Structures and Final Communalities

Factor Structure (Correlations)			
	Factor1	Factor2	
HouseValue	0.93582	0.09500	
School	0.89954	0.09189	
Services	0.82903	0.49286	
Population	0.12319	0.98596	
Employment	0.24484	0.98478	

Variance Explained by Each Factor Ignoring Other Factors

Factor1 Factor2 2.4473495 2.2022803

 Final Communality Estimates: Total = 4.450370

 Population
 School
 Employment
 Services
 HouseValue

 0.97811334
 0.81756387
 0.97199928
 0.79774304
 0.88494998

Basically, the factor structure matrix shown in Output 37.2.13 reflects a similar pattern to the factor pattern matrix shown in Output 37.2.11. The critical difference is that you can have the correlation interpretation only by using the factor structure matrix. For example, in the factor structure matrix shown in Output 37.2.13, the correlation between Population and Factor 2 is 0.986. The corresponding value shown in the factor pattern matrix in Output 37.2.11 is 1.002, which certainly cannot be interpreted as a correlation coefficient.

Common variance explained by the promax-rotated factors are 2.447 and 2.202, respectively, for the two factors. Unlike the orthogonal factor solutions (for example, the prerotated varimax solution), variance explained by these promax-rotated factors do not sum up to the total communality estimate 4.45. In oblique factor solutions, variance explained by oblique factors cannot be partitioned for the factors. Variance explained by a common factor is computed while ignoring the contributions from the other factors.

However, the communalities for the variables, as shown in the bottom of Output 37.2.13, do not change from rotation to rotation. They are still the same set of communalities in the initial, varimax-rotated, and promax-rotated solutions. This is a basic fact about factor rotations: they only redistribute the variance explained by the factors; the total variance explained by the factors for any variable (that is, the communality of the variable) remains unchanged.

In the literature of exploratory factor analysis, reference axes had been an important tool in factor rotation. Nowadays, rotations are seldom done through the uses of the reference axes. Despite that, results about reference axes do provide additional information for interpreting factor analysis results. For the current example of the promax rotation, PROC FACTOR shows the relevant results about the reference axes in Output 37.2.14.

Output 37.2.14 Promax Rotation: Reference Axis Correlations and Reference Structures

			_
Reference Axis			
	relatior		_
F	actor1	Facto	r2
Factor1 1	.00000	-0.2018	38
Factor2 -0.	.20188	1.0000	00
Referen			
(Semipartia	al Corre	elations	5)
	Facto	1 Fac	to
HouseValue	0.9359	91 -0.09	959
School	0.8995	51 -0.09	916
Services	0.7448	37 0.33	323
Population	-0.0774	5 0.98	312
Employment	0.0470	0.95	55(
Varian	ce Expl	ained	
-	ach Fac		
Eliminating Other Factors			
Facto		actor2	
Facto	rı F	actorz	
2.24808			

To explain the results in the reference-axis system, some geometric interpretations of the factor axes are needed. Consider a single factor in a system of n common factors in an oblique factor solution. Taking away the factor under consideration, the remaining n-1 factors span a hyperplane in the factor space of n-1 dimensions. The vector that is orthogonal to this hyperplane is the reference axis (reference vector) of the factor under consideration. Using the same definition for the remaining factors, you have n reference vectors for n factors.

A factor in an oblique factor solution can be considered as the sum of two independent components: its associated reference vector and a component that is overlapped with all other factors. In other words, the reference vector of a factor is a unique part of the factor that is not predictable from all other factors. Thus, the loadings on a reference vector are the unique effects of the corresponding factor, partialling out the effects from all other factors. The variances explained by a reference vector are the unique variances explained by the corresponding factor, partialling out the variances explained by all other factors.

The last table shown in Output 37.2.14 are the variances explained by the reference vectors. As explained previously, these are also unique variances explained by the factors, partialling out the variances explained by all other factors (or eliminating all other factors, as suggested by the title of the table). In the current example, Factor 1 explains 2.248 of the variable variances, partialling out all variable variances explained by Factor 2.

Notice that factor pattern (shown in Output 37.2.11), factor structures (correlations, shown in Output 37.2.13), and reference structures (semipartial correlations, shown in Output 37.2.14) give you different information about the oblique factor solutions such as the promax-rotated solution. However, for orthogonal factor solutions such as the varimax-rotated solution, factor structures and reference structures are all the same as the factor pattern.

Principal Factor Analysis: Factor Rotations with Factor Pattern Input

The promax rotation is one of the many rotations that PROC FACTOR provides. You can specify many different rotation algorithms by using the ROTATE= options. In this section, you explore different rotated factor solutions from the initial principal factor solution. Specifically, you want to examine the factor patterns yielded by the quartimax transformation (an orthogonal transformation) and the Harris-Kaiser (an oblique transformation), respectively.

Rather than analyzing the entire problem again with new rotations, you can simply use the OUTSTAT= data set from the preceding factor analysis results.

First, the OUTSTAT= data set is printed using the following statements:

```
proc print data=fact_all;
run;
```

The output data set is displayed in Output 37.2.15.

Output 37.2.15 Output Data Set

Factor Output Data Set

Obs	_TYPE_	_NAME_	Population	School	Employment	Services	HouseValue
1	MEAN		6241.67	11.4417	2333.33	120.833	17000.00
2	STD		3439.99	1.7865	1241.21	114.928	6367.53
3	N		12.00	12.0000	12.00	12.000	12.00
4	CORR	Population	1.00	0.0098	0.97	0.439	0.02
5	CORR	School	0.01	1.0000	0.15	0.691	0.86
6	CORR	Employment	0.97	0.1543	1.00	0.515	0.12
7	CORR	Services	0.44	0.6914	0.51	1.000	0.78
8	CORR	HouseValue	0.02	0.8631	0.12	0.778	1.00
9	COMMUNAL	-	0.98	0.8176	0.97	0.798	0.88
10	PRIORS		0.97	0.8223	0.97	0.786	0.85
11	EIGENVAL		2.73	1.7161	0.04	-0.025	-0.07
12	UNROTATE	Factor1	0.63	0.7137	0.71	0.879	0.74
13	UNROTATE	Factor2	0.77	-0.5552	0.68	-0.158	-0.58
14	RESIDUAL	Population	0.02	-0.0112	0.01	0.011	0.00
15	RESIDUAL	School	-0.01	0.1824	0.02	-0.024	0.01
16	RESIDUAL	Employment	0.01	0.0215	0.03	-0.006	-0.02
17	RESIDUAL	Services	0.01	-0.0239	-0.01	0.202	0.03
18	RESIDUAL	HouseValue	0.00	0.0125	-0.02	0.034	0.12
19	PRETRANS	Factor1	0.79	-0.6145			
20	PRETRANS	Factor2	0.61	0.7889			
21	PREROTAT	Factor1	0.02	0.9042	0.15	0.791	0.94
22	PREROTAT	Factor2	0.99	0.0006	0.97	0.415	-0.00
23	TRANSFOR	Factor1	0.74	-0.7055		•	
24	TRANSFOR	Factor2	0.54	0.8653		•	
25	FCORR	Factor1	1.00	0.2019		•	
26	FCORR	Factor2	0.20	1.0000	•	•	
27	PATTERN	Factor1	-0.08	0.9184	0.05	0.761	0.96
28	PATTERN	Factor2	1.00	-0.0935	0.98	0.339	-0.10
29	RCORR	Factor1	1.00	-0.2019	•	•	
30	RCORR	Factor2	-0.20	1.0000			
31	REFERENC	Factor1	-0.08	0.8995	0.05	0.745	0.94
32	REFERENC	Factor2	0.98	-0.0916	0.96	0.332	-0.10
33	STRUCTUR	Factor1	0.12	0.8995	0.24	0.829	0.94
34	STRUCTUR	Factor2	0.99	0.0919	0.98	0.493	0.09

Various results from the previous factor analysis are saved in this data set, including the initial unrotated solution (its factor pattern is saved in observations with _TYPE_=UNROTATE), the prerotated varimax solution (its factor pattern is saved in observations with _TYPE_=PREROTAT), and the oblique promax solution (its factor pattern is saved in observations with _TYPE_=PATTERN).

When PROC FACTOR reads in an input data set with TYPE=FACTOR, the observations with _TYPE_=PATTERN are treated as the initial factor pattern to be rotated by PROC FACTOR. Hence, it is important that you provide the correct initial factor pattern for PROC FACTOR to read in.

In the current example, you need to provide the unrotated solution from the preceding analysis as the input factor pattern. The following statements create a TYPE=FACTOR data set fact2 from the preceding OUTSTAT= data set fact all:

```
data fact2(type=factor);
   set fact_all;
   if _TYPE_ in('PATTERN' 'FCORR') then delete;
   if _TYPE_='UNROTATE' then _TYPE_='PATTERN';
   run:
```

In these statements, you delete observations with _TYPE_=PATTERN or _TYPE_=FCORR, which are for the promax-rotated factor solution, and change observations with _TYPE_=UNROTATE to _TYPE_=PATTERN in the new data set fact2. In this way, the initial orthogonal factor pattern matrix is saved in the observations with _TYPE_=PATTERN.

You use this new data set and rotate the initial solution to another oblique solution with the ROTATE=QUARTIMAX option, as shown in the following statements:

```
proc factor data=fact2 rotate=quartimax reorder;
run:
```

As shown in Output 37.2.16, the input data set is of the FACTOR type for the new rotation.

Output 37.2.16 Quartimax Rotation With Input Factor Pattern

Quartimax Rotation From a TYPE=FACTOR Data Set

The FACTOR Procedure

Input Data Type	FACTOR
N Set/Assumed in Data Set	12
N for Significance Tests	12

The quartimax-rotated factor pattern is displayed in Output 37.2.17.

Output 37.2.17 Quartimax-Rotated Factor Pattern

Orthogonal Transformation Matrix			
		1	2
	1	0.80138	0.59815
	2	-0.59815	0.80138

Rotated Factor Pattern			
	Factor1	Factor2	
HouseValue	0.94052	-0.01933	
School	0.90401	-0.01799	
Services	0.79920	0.39878	
Population	0.04282	0.98807	
Employment	0.16621	0.97179	

Output 37.2.17 continued

Variance Explained by Each Factor Factor1 Factor2 2.3699941 2.0803754

The quartimax rotation produces an orthogonal transformation matrix shown at the top of Output 37.2.17. After the transformation, the factor pattern is shown next. Compared with the varimax-rotated factor pattern (see Output 37.2.7), the quartimax-rotated factor pattern shows some differences. The loadings of HouseValue and School on Factor 1 drop only slightly in the quartimax factor pattern, while the loadings of Services, Population, and Employment on Factor 1 gain relatively larger amounts. The total variance explained by Factor 1 in the varimax-rotated solution (see Output 37.2.7) is 2.350, while it is 2.370 after the quartimax-rotation. In other words, more variable variances are explained by the first factor in the quartimax factor pattern than in the varimax factor pattern. Although not very strongly demonstrated in the current example, this illustrates a well-known property about the quartimax rotation: it tends to produce a general factor for all variables.

Another oblique rotation is now explored. The Harris-Kaiser transformation weighted by the Cureton-Mulaik technique is applied to the initial factor pattern. To achieve this, you use the ROTATE=HK and NORM=WEIGHT options in the following PROC FACTOR statement:

```
ods graphics on;
proc factor data=fact2 rotate=hk norm=weight reorder
    plots=loadings;
run;
ods graphics off;
```

Output 37.2.18 shows the variable weights in the rotation.

Output 37.2.18 Harris-Kaiser Rotation: Weights

Variable Weights for Rotation				
Population	School	Employment	Services	HouseValue
0.95982747	0.93945424	0.99746396	0.12194766	0.94007263

While all other variables have weights at least as large as 0.93, the weight for Services is only 0.12. This means that due to its small weight, Services is not as important as the other variables for determining the rotation (transformation). This makes sense when you look at the initial unrotated factor pattern plot in Output 37.2.6. In the plot, there are two main clusters of variables, and Services does not seem to fall into either of the clusters. In order to yield a Harris-Kaiser rotation (transformation) that would gear towards to two clusters, the Cureton-Mulaik weighting essentially downweights the contribution from Services in the factor rotation.

The results of the Harris-Kaiser factor solution are displayed in Output 37.2.19, with a graphical plot of rotated loadings displayed in Output 37.2.20.

Output 37.2.19 Harris-Kaiser Rotation: Factor Correlations and Factor Pattern


Inter-Factor Correlations			
	Factor1	Factor2	
Factor1	1.00000	0.08358	
Factor2	0.08358	1.00000	

Rotated Factor Pattern (Standardized Regression Coefficients)				
	Factor1	Factor2		
HouseValue	0.94048	0.00279		
School	0.90391	0.00327		
Services	0.75459	0.41892		
Population	-0.06335	0.99227		
Employment	0.06152	0.97885		

Because the Harris-Kaiser produces an oblique factor solution, you compare the current results with that of the promax (see Output 37.2.11), which also produces an oblique factor solution. The correlation between the factors in the Harris-Kaiser solution is 0.084; this value is much smaller than the same correlation in the promax solution, which is 0.201. However, the Harris-Kaiser rotated factor pattern shown in Output 37.2.19 is more or less the same as that of the promax-rotated factor pattern shown in Output 37.2.11. Which solution would you consider to be more reasonable or interpretable?

From the statistical point of view, the Harris-Kaiser and promax factor solutions are equivalent. They explain the observed variable relationships equally well. From the simplicity point of view, however, you might prefer to interpret the Harris-Kaiser solution because the factor correlation is smaller. In other words, the factors in the Harris-Kaiser solution do not overlap that much conceptually; hence they should be more distinctive to interpret. However, in practice simplicity in factor correlations might not the only principle to consider. Researchers might actually expect to have some factors to be highly correlated based on theoretical or substantive grounds.

Although the Harris-Kaiser and the promax factor patterns are very similar, the graphical plots of the loadings from the two solutions paint slightly different pictures. The plot of the promax-rotated loadings is shown in Output 37.2.12, while the plot of the loadings for the current Harris-Kaiser solution is shown in Output 37.2.20.



Output 37.2.20 Harris-Kaiser Rotation: Factor Loading Plot

The two factor axes in the Harris-Kaiser rotated pattern (Output 37.2.20) clearly cut through the centers of the two variable clusters, while the Factor 1 axis in the promax solution lies above a variable cluster (Output 37.2.12). The reason for this subtle difference is that in the Harris-Kaiser rotation, the Services is a "loner" that has been downweighted by the Cureton-Mulaik technique (see its relatively small weight in Output 37.2.18). As a result, the rotated axes are basically determined by the two variable clusters in the Harris-Kaiser rotation.

As far as the current discussion goes, it is not recommending one rotation method over another. Rather, it simply illustrates how you could control certain types of characteristics of factor rotation through the many options supported by PROC FACTOR. Should you prefer an orthogonal rotation to an oblique rotation? Should you choose the oblique factor solution with the smallest factor correlations? Should you use a weighting scheme that would enable you to find independent variable clusters? While PROC FACTOR enables you to explore all these alternatives, you must consult advanced textbooks and published articles to get satisfactory and complete answers to these questions.

Example 37.3: Maximum Likelihood Factor Analysis

This example uses maximum likelihood factor analyses for one, two, and three factors. It is already apparent from the principal factor analysis that the best number of common factors is almost certainly two. The one-and three-factor ML solutions reinforce this conclusion and illustrate some of the numerical problems that can occur. The following statements produce Output 37.3.1 through Output 37.3.3:

```
title3 'Maximum Likelihood Factor Analysis with One Factor';
proc factor data=SocioEconomics method=ml heywood n=1;
run;

title3 'Maximum Likelihood Factor Analysis with Two Factors';
proc factor data=SocioEconomics method=ml heywood n=2;
run;

title3 'Maximum Likelihood Factor Analysis with Three Factors';
proc factor data=SocioEconomics method=ml heywood n=3;
run;
```

Output 37.3.1 displays the results of the analysis with one factor.

Output 37.3.1 Maximum Likelihood Factor Analysis

Maximum Likelihood Factor Analysis with One Factor

The FACTOR Procedure

Input Data Type	Raw Data
Number of Records Read	12
Number of Records Used	12
N for Significance Tests	12

Maximum Likelihood Factor Analysis with One Factor

The FACTOR Procedure Initial Factor Method: Maximum Likelihood

Prior Communality Estimates: SMC				
Population	School	Employment	Services	HouseValue
0.96859160	0.82228514	0.96918082	0.78572440	0.84701921

Preliminary Eigenvalues: Total = 76.1165859 Average = 15.2233172					
	Eigenvalue	Difference	Proportion	Cumulative	
1	63.7010086	50.6462895	0.8369	0.8369	
2	13.0547191	12.7270798	0.1715	1.0084	
3	0.3276393	0.6749199	0.0043	1.0127	
4	-0.3472805	0.2722202	-0.0046	1.0081	
5	-0.6195007		-0.0081	1.0000	

1 factor will be retained by the NFACTOR criterion.

Iteration	Criterion	Ridge	Change		Co	mmunali	ties	
1	6.5429218	0.0000	0.1033	0.93828	0.72227	1.00000	0.71940	0.74371
2	3.1232699	0.0000	0.7288	0.94566	0.02380	1.00000	0.26493	0.01487

Convergence criterion satisfied.

Significance Tests Based on 12 Observations

			Pr >
Test	DF	Chi-Square	ChiSq
H0: No common factors	10	54.2517	<.0001
HA: At least one common factor			
H0: 1 Factor is sufficient	5	24.4656	0.0002
HA: More factors are needed			

Chi-Square without Bartlett's Correction	34.355969
Akaike's Information Criterion	24.355969
Schwarz's Bayesian Criterion	21.931436
Tucker and Lewis's Reliability Coefficient	0.120231

Squared Canonical Correlations

Factor1

1.0000000

Eigenvalues of the Weighted Reduced Correlation Matrix: Total = 0 Average = 0

Eigenvalue	Difference

1	Infty	Infty
2	1.92716032	2.15547340
3	22831308	0.56464322
4	79295630	0.11293464

Factor Pattern

5 -.90589094

	Factor1	
Population	0.97245	
School	0.15428	
Employment	1.00000	
Services	0.51472	
HouseValue	0.12193	

Variance Explained by Each Factor

Factor Weighted Unweighted Factor 17.8010629 2.24926004

Output 37.3.1 continued

Final Communality Estimates and Variable Weights **Total Communality:** Weighted = 17.801063 Unweighted = 2.249260

Variable	Communality	Weight
Population	0.94565561	18.4011648
School	0.02380349	1.0243839
Employment	1.00000000	Infty
Services	0.26493499	1.3604239
HouseValue	0.01486595	1.0150903

The solution on the second iteration is so close to the optimum that PROC FACTOR cannot find a better solution; hence you receive this message:

Convergence criterion satisfied.

When this message appears, you should try rerunning PROC FACTOR with different prior communality estimates to make sure that the solution is correct. In this case, other prior estimates lead to the same solution or possibly to worse local optima, as indicated by the information criteria or the chi-square values.

The variable Employment has a communality of 1.0 and, therefore, an infinite weight that is displayed next to the final communality estimate as a missing/infinite value. The first eigenvalue is also infinite. Infinite values are ignored in computing the total of the eigenvalues and the total final communality.

Output 37.3.2 displays the results of the analysis with two factors. The analysis converges without incident. This time, however, the Population variable is a Heywood case.

Output 37.3.2 Maximum Likelihood Factor Analysis: Two Factors

Input Data Type	Raw Data
Number of Records Read	12
Number of Records Used	12
N for Significance Tests	12

Prior Communality Estimates: SMC				
Population	School	Employment	Services	HouseValue
0.96859160	0.82228514	0.96918082	0.78572440	0.84701921

	Preliminary Eigenvalues: Total = 76.1165859 Average = 15.2233172							
	Eigenvalue	Difference	Proportion	Cumulative				
1	63.7010086	50.6462895	0.8369	0.8369				
2	13.0547191	12.7270798	0.1715	1.0084				
3	0.3276393	0.6749199	0.0043	1.0127				
4	-0.3472805	0.2722202	-0.0046	1.0081				
5	-0.6195007		-0.0081	1.0000				

2 factors will be retained by the NFACTOR criterion.

Iteration	Criterion	Ridge	Change		Co	mmunali	ties	
1	0.3431221	0.0000	0.0471	1.00000	0.80672	0.95058	0.79348	0.89412
2	0.3072178	0.0000	0.0307	1.00000	0.80821	0.96023	0.81048	0.92480
3	0.3067860	0.0000	0.0063	1.00000	0.81149	0.95948	0.81677	0.92023
4	0.3067373	0.0000	0.0022	1.00000	0.80985	0.95963	0.81498	0.92241
5	0.3067321	0.0000	0.0007	1.00000	0.81019	0.95955	0.81569	0.92187

Convergence criterion satisfied.

Significance '	Tests	Based	on 12	Observa	tions
----------------	-------	-------	-------	---------	-------

			Pr >			
Test	DF	Chi-Square	ChiSq			
H0: No common factors	10	54.2517	<.0001			
HA: At least one common factor						
H0: 2 Factors are sufficient	1	2.1982	0.1382			
HA: More factors are needed						

Chi-Square without Bartlett's Correction3.3740530Akaike's Information Criterion1.3740530Schwarz's Bayesian Criterion0.8891463Tucker and Lewis's Reliability Coefficient0.7292200

Squared Canonical Correlations

Factor1Factor21.00000000.9518891

Eigenvalues of the Weighted Reduced Correlation Matrix: Total = 19.7853157 Average = 4.94632893

	Eigenvalue	Difference	Proportion	Cumulative
1	Infty	Infty		
2	19.7853143	19.2421292	1.0000	1.0000
3	0.5431851	0.5829564	0.0275	1.0275
4	-0.0397713	0.4636411	-0.0020	1.0254
5	-0.5034124		-0.0254	1.0000

Factor Pattern						
	Factor1 Factor					
Population	1.00000	0.00000				
School	0.00975	0.90003				
Employment	0.97245	0.11797				
Services	0.43887	0.78930				
HouseValue	0.02241	0.95989				

Variance Explained by Each	
Factor	

Factor	Weighted	Unweighted
Factor1	24.4329707	2.13886057
Factor2	19.7853143	2.36835294

Final Communality Estimates and Variable Weights

Total Communality: Weighted = 44.218285 Unweighted = 4.507214

Variable	Communality	Weight
Population	1.00000000	Infty
School	0.81014489	5.2682940
Employment	0.95957142	24.7246669
Services	0.81560348	5.4256462
HouseValue	0.92189372	12.7996793

The results of the three-factor analysis are shown in Output 37.3.3.

Output 37.3.3 Maximum Likelihood Factor Analysis: Three Factors

Input Data Type	Raw Data
Number of Records Read	12
Number of Records Used	12
N for Significance Tests	12

Prior Communality Estimates: SMC							
Population	School	Employment	Services	HouseValue			
0.96859160	0.82228514	0.96918082	0.78572440	0.84701921			

Preliminary Eigenvalues: Total = 76.1165859 Average = 15.2233172						
	Eigenvalue	Difference	Proportion	Cumulative		
1	63.7010086	50.6462895	0.8369	0.8369		
2	13.0547191	12.7270798	0.1715	1.0084		
3	0.3276393	0.6749199	0.0043	1.0127		
4	-0.3472805	0.2722202	-0.0046	1.0081		
5	-0.6195007		-0.0081	1.0000		

3 factors will be retained by the NFACTOR criterion.

Warning: Too many factors for a unique solution.

Iteration	Criterion	Ridge	Change		Co	mmunali	ties	
1	0.1798029	0.0313	0.0501	0.96081	0.84184	1.00000	0.80175	0.89716
2	0.0016405	0.0313	0.0678	0.98081	0.88713	1.00000	0.79559	0.96500
3	0.0000041	0.0313	0.0094	0.98195	0.88603	1.00000	0.80498	0.96751
4	0.0000000	0.0313	0.0006	0.98202	0.88585	1.00000	0.80561	0.96735

ERROR: Converged, but not to a proper optimum.

Try a different 'PRIORS' statement.

Significance Tests Based on 12 Observations

Significance resis based on 12 Observations				
			Pr >	
Test	DF	Chi-Square	ChiSq	
H0: No common factors	10	54.2517	<.0001	
HA: At least one common factor				
H0: 3 Factors are sufficient	-2	0.0000		
HA: More factors are needed				

Chi-Square without Bartlett's Correction0.0000003Akaike's Information Criterion4.0000003Schwarz's Bayesian Criterion4.9698136Tucker and Lewis's Reliability Coefficient0.0000000

Squared Canonical Correlations

 Factor1
 Factor2
 Factor3

 1.0000000
 0.9751895
 0.6894465

Eigenvalues of the Weighted Reduced Correlation Matrix: Total = 41.5254193 Average = 10.3813548

	Eigenvalue	Difference	Proportion	Cumulative
•	I Infty	Infty		
:	2 39.3054826	37.0854258	0.9465	0.9465
:	2.2200568	2.2199693	0.0535	1.0000
4	1 0.0000875	0.0002949	0.0000	1.0000
	5 -0.0002075		-0.0000	1.0000

Factor Pattern			
	Factor1	Factor2	Factor3
Population	0.97245	-0.11233	-0.15409
School	0.15428	0.89108	0.26083
Employment	1.00000	0.00000	0.00000
Services	0.51472	0.72416	-0.12766
HouseValue	0.12193	0.97227	-0.08473

 Variance Explained by Each Factor

 Factor
 Weighted
 Unweighted

 Factor1
 54.6115241
 2.24926004

 Factor2
 39.3054826
 2.27634375

 Factor3
 2.2200568
 0.11525433

Output 37.3.3 continued

Final Communality Estimates and Variable Weights **Total Communality:** Weighted = 96.137063Unweighted = 4.640858

Variable	Communality	Weight
Population	0.98201660	55.6066901
School	0.88585165	8.7607194
Employment	1.00000000	Infty
Services	0.80564301	5.1444261
HouseValue	0.96734687	30.6251078

In the results, a warning message is displayed:

WARNING: Too many factors for a unique solution.

The number of parameters in the model exceeds the number of elements in the correlation matrix from which they can be estimated, so an infinite number of different perfect solutions can be obtained. The criterion approaches zero at an improper optimum, as indicated by this message:

Converged, but not to a proper optimum.

The degrees of freedom for the chi-square test are -2, so a probability level cannot be computed for three factors. Note also that the variable Employment is a Heywood case again.

The probability levels for the chi-square test are 0.0001 for the hypothesis of no common factors, 0.0002 for one common factor, and 0.1382 for two common factors. Therefore, the two-factor model seems to be an adequate representation. Akaike's information criterion and Schwarz's Bayesian criterion attain their minimum values at two common factors, so there is little doubt that two factors are appropriate for these data.

Example 37.4: Using Confidence Intervals to Locate Salient Factor Loadings

This example illustrates how you can use the standard errors and confidence intervals to understand the pattern of factor loadings under the maximum likelihood estimation. There are nine tests and you want a three-factor solution (N=3) for a correlation matrix based on 200 observations. The following statements define the input data set and specify the desirable analysis by the FACTOR procedure:

```
data test(type=corr);
  title 'Quartimin-Rotated Factor Solution with Standard Errors';
  input _name_ $ test1-test9;
  _type_ = 'corr';
  datalines;
       1 .561 .602 .290 .404 .328 .367 .179 -.268
Test1
Test2
       .561
            1 .743 .414 .526
                                  .442 .523 .289 -.399
       .602 .743 1 .286 .343 .361 .679 .456 -.532
Test3
       .290 .414 .286 1 .677 .446 .412 .400 -.491
Test4
       .404 .526 .343 .677
                             1 .584 .408 .299 -.466
Test5
       .328 .442 .361 .446 .584
                                     1
Test 6
                                        . 333
                                              .178 - .306
Test7 .367 .523 .679 .412 .408 .333
                                           1
                                             .711 -.760
Test8
       .179 .289 .456 .400 .299 .178 .711
                                                1 - .725
Test9 -.268 -.399 -.532 -.491 -.466 -.306 -.760 -.725
title2 'A nine-variable-three-factor example';
proc factor data=test method=ml reorder rotate=quartimin
  nobs=200 n=3 se cover=.45 alpha=.1;
run;
```

In the PROC FACTOR statement, you apply quartimin rotation with (default) Kaiser normalization. You define loadings with magnitudes greater than 0.45 to be salient (COVER=0.45) and use 90% confidence intervals (ALPHA=0.1) to judge the salience. The REORDER option is specified so that variables that have similar loadings with factors are clustered together.

After the quartimin rotation, the correlation matrix for factors is shown in Output 37.4.1.

Output 37.4.1 Quartimin-Rotated Factor Correlations with Standard Errors

Inter-Factor Correlations With 90% confidence limits Estimate/StdErr/LowerCL/UpperCL				
	Factor1	Factor2	Factor3	
Factor1	1.00000 0.00000	0.41283 0.06267 0.30475 0.51041	0.38304 0.06060 0.27919 0.47804	
Factor2	0.41283 0.06267 0.30475 0.51041	1.00000 0.00000	0.47006 0.05116 0.38177 0.54986	
Factor3	0.38304 0.06060 0.27919 0.47804	0.47006 0.05116 0.38177 0.54986	1.00000 0.00000	

The factors are medium to highly correlated. The confidence intervals seem to be very wide, suggesting that the estimation of factor correlations might not be very accurate for this sample size. For example, the 90% confidence interval for the correlation between Factor1 and Factor2 is (0.30, 0.51), a range of 0.21. You might need a larger sample to get a narrower interval, or you might need a better estimation.

Next, coverage displays for factor loadings are shown in Output 37.4.2.

Output 37.4.2 Using the Rotated Factor Pattern to Interpret the Factors

Rotated Factor Pattern (Standardized Regression Coefficients) With 90% confidence limits; Cover |*| = 0.45? Estimate/StdErr/LowerCL/UpperCL/Coverage Display

	Factor1	Factor2	Factor3
test8	0.86810	-0.05045	0.00114
	0.03282	0.03185	0.03087
	0.80271	-0.10265	-0.04959
	0.91286	0.00204	0.05187
	0*[]	*[0]	[0]*
test7	0.73204	0.27296	0.01098
	0.04434	0.05292	0.03838
	0.65040 0.79697	0.18390 0.35758	-0.05211 0.07399
	0.73037	0.55750	[0]*
test9	-0.79654	-0.01230	-0.17307
lesis	0.03948	0.04225	0.04420
	-0.85291	-0.08163	-0.24472
	-0.72180	0.05715	-0.09955
	[]*0	*[0]	*[]0
test3	0.27715	0.91156	-0.19727
	0.05489	0.04877	0.02981
	0.18464	0.78650	-0.24577
	0.36478	0.96481	-0.14778
	0[]*	0*[]	*[]0
test2	0.01063	0.71540	0.20500
	0.05060	0.05148	0.05496
	-0.07248 0.09359	0.61982 0.79007	0.11310 0.29342
	*[0]	0:73007	0.23542
test1	-0.07356	0.63815	0.13983
testi	0.04245	0.05380	0.05597
	-0.14292	0.54114	0.04682
	-0.00348	0.71839	0.23044
	[]0	0[]	0[]*
test5	0.00863	0.03234	0.91282
	0.04394	0.04387	0.04509
	-0.06356	-0.03986	0.80030
	0.08073	0.10421	0.96323
	[0]*	[0]*	0*[]
test4	0.22357	-0.07576	0.67925
	0.05956 0.12366	0.03640 -0.13528	0.05434 0.57955
	0.12300	-0.13526	0.75891
	0.51900	-0.01309 0[]*	0.73091
test6	-0.04295	0.21911	0.53183
	0.05114	0.07481	0.06905
	-0.12656	0.09319	0.40893
	0.04127	0.33813	0.63578
	[0]	0[]	0[*]

The coverage displays in Output 37.4.2 show that Test8, Test7, and Test9 have salient relationships with Factor1. The coverage displays are either '0*[]' or '[]*0', indicating that the entire 90% confidence intervals for the corresponding loadings are beyond the salience value at 0.45. On the other hand, the coverage display for Test3 on Factor1 is '0[]*'. This indicates that even though the loading estimate is significantly larger than zero, it is not large enough to be salient. Similarly, Test3, Test2, and Test1 have salient relationships with Factor2, while Test5 and Test4 have salient relationships with Factor3. For Test6, its relationship with Factor3 is a little bit ambiguous; the 90% confidence interval approximately covers values between 0.40 and 0.64. This means that the population value might have been smaller or larger than 0.45. It is marginal evidence for a salient relationship.

For oblique factor solutions, some researchers prefer to examine the factor structure loadings, which represent correlations, for determining salient relationships. In Output 37.4.3, the factor structure loadings and the associated standard error estimates and coverage displays are shown.

Output 37.4.3 Using the Factor Structure to Interpret the Factors

With 90	Factor Structure (Correlations) With 90% confidence limits; Cover * = 0.45? Estimate/StdErr/LowerCL/UpperCL/Coverage Display			
	Factor1	Factor2	Factor3	
test8	0.84771	0.30847	0.30994	
	0.02871	0.06593	0.06263	
	0.79324	0.19641	0.20363	
	0.88872	0.41257	0.40904	
	0*[]	0[]*	0[]*	
test7	0.84894	0.58033	0.41970	
	0.02688	0.05265	0.06060	
	0.79834	0.48721	0.31523	
	0.88764	0.66041	0.51412	
	0*[]	0*[]	0[*]	
test9	-0.86791	-0.42248	-0.48396	
	0.02522	0.06187	0.05504	
	-0.90381	-0.51873	-0.56921	
	-0.81987	-0.31567	-0.38841	
	[]*0	[*]0	[*]0	
test3	0.57790	0.93325	0.33738	
	0.05069	0.02953	0.06779	
	0.48853	0.86340	0.22157	
	0.65528	0.96799	0.44380	
	0*[]	0*[]	0[]*	
test2	0.38449	0.81615	0.54535	
	0.06143	0.03106	0.05456	
	0.27914	0.75829	0.44946	
	0.48070	0.86126	0.62883	
	0[*]	0*[]	0[*]	
test1	0.24345	0.67351	0.41162	
	0.06864	0.04284	0.05995	
	0.12771	0.59680	0.30846	
	0.35264	0.73802	0.50522	
	0[]*	0*[]	0[*]	
test5	0.37163	0.46498	0.93132	
	0.06092	0.04979	0.03277	
	0.26739	0.37923	0.85159	
	0.46727	0.54282	0.96894	
	0[*]	0[*]	0*[]	
test4	0.45248	0.33583	0.72927	
	0.05876	0.06289	0.04061	
	0.35072	0.22867	0.65527	
	0.54367	0.43494	0.78941	
	0[*]	0[]*	0*[]	
test6	0.25122	0.45137	0.61837	
	0.07140	0.05858	0.05051	
	0.13061	0.34997	0.52833	
	0.36450	0.54232	0.69465	
	0[]*	0[*]	0*[]	

The interpretations based on the factor structure matrix do not change much from that based on the factor loadings except for Test3 and Test9. Test9 now has a salient correlation with Factor3. For Test3, it has salient correlations with both Factor1 and Factor2. Fortunately, there are still tests that have salient correlations only with either Factor1 or Factor2 (but not both). This would make interpretations of factors less problematic.

Example 37.5: Creating Path Diagrams for Factor Solutions

The section "Getting Started: FACTOR Procedure" on page 2304 analyzes a data set that contains 14 ratings of 103 police officers to demonstrate some basic techniques in factor analysis. To illustrate the creation and uses of path diagrams, this example analyzes this data set again by using the following statements:

```
ods graphics on;
proc factor data=jobratings(drop='Overall Rating'n)
    priors=smc rotate=quartimin plots=pathdiagram;
run;
```

The PRIORS=SMC option specifies that the squared multiple correlations are to be used as the prior communality estimates. As a result, the factors are extracted by the principal factor method. The ROTATE=QUARTIMIN option requests the use of the quartimin rotation to obtain the final factor solution. The PLOTS=PATHDIAGRAM option requests a path diagram for the final solution.

Except for the PLOTS=PATHDIAGRAM option, previous examples have already described the FACTOR options that are used in this example. Therefore, this example focuses only on the creation of path diagrams.

Output 37.5.1 and Output 37.5.2 show the quartimin-rotated factor correlations and factor pattern, respectively.

Output 37.5.1 Quartimin-Rotated Factor Correlations


Inter-Factor Correlations				
	Factor1	Factor2	Factor3	
Factor1	1.00000	0.36103	0.34823	
Factor2	0.36103	1.00000	0.55721	
Factor3	0.34823	0.55721	1.00000	

Output 37.5.2 Quartimin-Rotated Factor Pattern

Rotated Factor Pattern (Standardized Regression Coefficients)					
	Factor1	Factor2	Factor3		
Communication Skills	0.21280	0.13541	0.61091		
Problem Solving	0.17222	0.01424	0.68767		
Learning Ability	-0.09904	0.24961	0.65430		
Judgment under Pressure	0.49876	-0.02005	0.48879		
Observational Skills	-0.15748	0.67661	0.30273		
Willingness to Confront Problems	-0.19106	0.66639	0.31135		
Interest in People	0.84249	0.12734	-0.00710		
Interpersonal Sensitivity	0.87832	-0.12964	0.15116		
Desire for Self-Improvement	0.19078	0.49891	0.23297		
Appearance	0.05254	0.53846	0.10857		
Dependability	0.39241	0.50035	0.12032		
Physical Ability	0.14404	0.63901	-0.15220		
Integrity	0.68277	0.32719	-0.01887		

Output 37.5.3 shows the path diagram for the quartimin-rotated factor solution. The path diagram represents correlations among factors by double-headed links or paths. For example, Output 37.5.3 represents the correlation between Factor1 and Factor2 by a curved doubled-headed link. The numerical value, 0.36, is the correlation between the two factors, as can be verified from the table in Output 37.5.1. Similarly, Output 37.5.3 shows other factor correlations by curved doubled-headed links.

Output 37.5.3 Default Path Diagram for the Quartimin-Rotated Solution



The path diagram in Output 37.5.3 also represents factor variances and error variances by double-headed links. However, each of these links points to an individual variable, rather than to a pair of variables as the double-headed links for correlations do. The path diagram also displays the numerical values of factor variances or error variances next to the associated links.

The directed links from factors to variables in the path diagram represent the effects of factors on the variables. The path diagram displays the numerical values of these effects, which are the loading estimates that are shown in Output 37.5.2. However, to aid the interpretation of the factors, the path diagram does not show all factor loadings or their corresponding links. By default, the path diagram displays only the links that have loadings greater than 0.3 in magnitude. For example, instead of associating Factor1 with all variables, the path diagram in Output 37.5.3 displays only five directed links from Factor1 to the variables. The weaker links that have loadings less than 0.3 are not shown.

The use of the 0.3 loading value (or greater in magnitude) for relating factors to variables is referred to as the "0.3-rule" in the field of factor analysis. However, this is only a convention, and sometimes you might want to use a different criterion to interpret the factors. For example, the path diagram in Output 37.5.3 shows that variables Dependability, Integrity, and Observational Skills are all associated with more than one factor. Hence, factors might not be interpreted unambiguously.

One way to tackle this interpretation problem is to set a stricter criterion for interpreting factors. You can use the FUZZ= option to set such a criterion. For example, you specify the following PATHDIAGRAM statement to display only the strong directed links that are associated with a 0.4 or greater magnitude in the loading estimates:

pathdiagram fuzz=0.4 title='Directed Paths with Loadings Greater Than 0.4';

The preceding statement also uses the TITLE= option to specify a customized title for the path diagram. Output 37.5.4 shows the resulting path diagram. In this path diagram, only one observed variable is linked to two factors. All other observed variables link to unique factors. Therefore, compared to the path diagram in Output 37.5.3, the path diagram in Output 37.5.4 provides a much "cleaner" picture for interpreting the factors.


Output 37.5.4 Path Diagram Showing Strong Links **Directed Paths with Loadings Greater Than 0.4** 0.20 Interpersonal Sensitivity 0.88 0.20 Interest in 0.84 People Factor1 0.28 0.68 0.50 Integrity 0.36 0.35 Judgment under... 0.49 0.40 Problem 0.69 Solving Factor3 0.36 0.61 Communicati on Skills 0.65 0.36 Learning Ability 0.32 0.56 Willingness to Confron... 0.43 0.67 Desire for Self-... 0.50 0.31 Observationa 0.68 I Skills Factor2 0.34 0.50 Dependabilit 0.54 0.61 0.64 Appearance 0.60 **Physical** Ability

The current example has 13 observed variables in the path diagram. By default, PROC FACTOR uses the process-flow algorithm to lay out the variables. However, when the number of observed variables becomes large, the process-flow algorithm needs a lot of vertical space to align all observed variables in a vertical line. Displaying such a "long" path diagram in limited space (for example, in a page) might compromise the clarity of the path diagram.

To handle this issue, PROC FACTOR switches to the GRIP algorithm when the number of variables is greater than 14. However, you can override the layout algorithm whenever you find it useful to do so. For example, the ARRANGE=GRIP option in the following PATHDIAGRAM statement requests that the GRIP algorithm be used:

pathdiagram fuzz=.4 arrange=grip notitle;

The NOTITLE option suppresses the display of the title for the path diagram. Output 37.5.5 shows the resulting path diagram, which spreads out the variables instead of aligning them vertically, as it does when it uses the process-flow algorithm in Output 37.5.4.



Output 37.5.5 Path Diagram Showing Strong Links by Using the ARRANGE=GRIP Algorithm

For more information about the options for customizing path diagrams, see the PATHDIAGRAM statement.

References

- Akaike, H. (1973), "Information Theory and an Extension of the Maximum Likelihood Principle," in B. N. Petrov and F. Csáki, eds., Proceedings of the Second International Symposium on Information Theory, 267–281, Budapest: Akademiai Kiado.
- Akaike, H. (1974), "A New Look at the Statistical Model Identification," IEEE Transactions on Automatic Control, AC-19, 716–723.
- Akaike, H. (1987), "Factor Analysis and AIC," Psychometrika, 52, 317–332.
- Archer, C. O. and Jennrich, R. I. (1973), "Standard Errors for Orthogonally Rotated Factor Loadings," Psychometrika, 38, 581-592.
- Bickel, P. J. and Doksum, K. A. (1977), *Mathematical Statistics*, San Francisco: Holden-Day.
- Browne, M. W. (1982), "Covariance Structures," in D. M. Hawkins, ed., Topics in Applied Multivariate Analysis, 72–141, Cambridge: Cambridge University Press.
- Browne, M. W., Cudeck, R., Tateneni, K., and Mels, G. (2008), "CEFA: Comprehensive Exploratory Factor Analysis, Version 3.02," retrieved from: http://faculty.psy.ohio-state.edu/browne/ programs.htm.
- Cattell, R. B. (1966), "The Scree Test for the Number of Factors," Multivariate Behavioral Research, 1, 245-276.
- Cattell, R. B. (1978), *The Scientific Use of Factor Analysis*, New York: Plenum.
- Cattell, R. B. and Vogelman, S. (1977), "A Comprehensive Trial of the Scree and KG Criteria for Determining the Number of Factors," Multivariate Behavioral Research, 12, 289–325.
- Cerny, B. A. and Kaiser, H. F. (1977), "A Study of a Measure of Sampling Adequacy for Factor-Analytic Correlation Matrices," Multivariate Behavioral Research, 12, 43–47.
- Crawford, C. B. and Ferguson, G. A. (1970), "A General Rotation Criterion and Its Use in Orthogonal Rotation," Psychometrika, 35, 321–332.
- Cureton, E. E. (1968), A Factor Analysis of Project TALENT Tests and Four Other Test Batteries, Palo Alto, CA: Project TALENT Office, American Institutes for Research and University of Pittsburgh, interim Report 4 to the U.S. Office of Education, Cooperative Research Project No. 3051.
- Cureton, E. E. and Mulaik, S. A. (1975), "The Weighted Varimax Rotation and the Promax Rotation," Psychometrika, 40, 183-195.
- Dziuban, C. D. and Harris, C. W. (1973), "On the Extraction of Components and the Applicability of the Factor Model," American Educational Research Journal, 10, 93–99.
- Fuller, W. A. (1987), Measurement Error Models, New York: John Wiley & Sons.
- Geweke, J. and Singleton, K. J. (1980), "Interpreting the Likelihood Ratio Statistic in Factor Models When Sample Size Is Small," Journal of the American Statistical Association, 75, 133–137.

- Gorsuch, R. L. (1974), Factor Analysis, Philadelphia: W. B. Saunders.
- Harman, H. H. (1976), Modern Factor Analysis, 3rd Edition, Chicago: University of Chicago Press.
- Harris, C. W. (1962), "Some Rao-Guttman Relationships," *Psychometrika*, 27, 247–263.
- Hayashi, K. and Yung, Y.-F. (1999), "Standard Errors for the Class of Orthomax-Rotated Factor Loadings: Some Matrix Results," *Psychometrika*, 64, 451–460.
- Horn, J. L. and Engstrom, R. (1979), "Cattell's Scree Test in Relation to Bartlett's Chi-Square Test and Other Observations on the Number of Factors Problem," *Multivariate Behavioral Research*, 14, 283–300.
- Jennrich, R. I. (1973), "Standard Errors for Obliquely Rotated Factor Loadings," *Psychometrika*, 38, 593–604.
- Jennrich, R. I. (1974), "Simplified Formulae for Standard Errors in Maximum-Likelihood Factor Analysis," *British Journal of Mathematical and Statistical Psychology*, 27, 122–131.
- Jöreskog, K. G. (1977), "Factor Analysis by Least-Squares and Maximum Likelihood Methods," in K. Enslein, A. Ralston, and H. Wilf, eds., *Statistical Methods for Digital Computers*, New York: John Wiley & Sons.
- Kaiser, H. F. (1963), "Image Analysis," in C. W. Harris, ed., *Problems in Measuring Change*, Madison: University of Wisconsin Press.
- Kaiser, H. F. (1970), "A Second Generation Little Jiffy," *Psychometrika*, 35, 401–415.
- Kaiser, H. F. and Rice, J. (1974), "Little Jiffy, Mark IV," *Educational and Psychological Measurement*, 34, 111–117.
- Kerlinger, F. N. and Pedhazur, E. J. (1973), *Multiple Regression in Behavioral Research*, New York: Holt, Rinehart & Winston.
- Kim, J. O. and Mueller, C. W. (1978a), *Factor Analysis: Statistical Methods and Practical Issues*, Sage University Paper Series on Quantitative Applications in the Social Sciences, 07-014, Beverly Hills, CA: Sage Publications.
- Kim, J. O. and Mueller, C. W. (1978b), *Introduction to Factor Analysis: What It Is and How to Do It*, Sage University Paper Series on Quantitative Applications in the Social Sciences, 07-013, Beverly Hills, CA: Sage Publications.
- Lawley, D. N. and Maxwell, A. E. (1971), Factor Analysis as a Statistical Method, New York: Macmillan.
- Lee, H. B. and Comrey, A. L. (1979), "Distortions in a Commonly Used Factor Analytic Procedure," *Multivariate Behavioral Research*, 14, 301–321.
- Mardia, K. V., Kent, J. T., and Bibby, J. M. (1979), *Multivariate Analysis*, London: Academic Press.
- Morrison, D. F. (1976), Multivariate Statistical Methods, 2nd Edition, New York: McGraw-Hill.
- Mulaik, S. A. (1972), The Foundations of Factor Analysis, New York: McGraw-Hill.
- Rao, C. R. (1955), "Estimation and Tests of Significance in Factor Analysis," *Psychometrika*, 20, 93–111.
- Schwarz, G. (1978), "Estimating the Dimension of a Model," *Annals of Statistics*, 6, 461–464.

- - Spearman, C. (1904), "General Intelligence Objectively Determined and Measured," American Journal of Psychology, 15, 201-293.
 - Stewart, D. W. (1981), "The Application and Misapplication of Factor Analysis in Marketing Research," Journal of Marketing Research, 18, 51–62.
 - Tucker, L. R. and Lewis, C. (1973), "A Reliability Coefficient for Maximum Likelihood Factor Analysis," Psychometrika, 38, 1–10.
 - Yung, Y.-F. and Hayashi, K. (2001), "A Computationally Efficient Method for Obtaining Standard Error Estimates for the Promax and Related Solutions," British Journal of Mathematical and Statistical Psychology, 54, 125–138.

Subject Index

alpha factor analysis, 2296, 2313	OUT= data sets, 2320
analyzing data in groups	output data sets, 2301, 2320
FACTOR procedure, 2325	path diagram, 2326
	simplicity functions, 2298, 2321, 2337
biquartimax method, 2296, 2321, 2322	time requirements, 2338
biquartimin method, 2296, 2322	variances, 2324
	Factor rotation
canonical factor solution, 2301	with FACTOR procedure, 2302
coefficient	factor rotation methods, 2296
alpha (FACTOR), 2344	factor structure, 2302
common factor	
defined for factor analysis, 2297	generalized Crawford-Ferguson family, 2296
common factor analysis	generalized Crawford-Ferguson method, 2321, 232
common factor rotation, 2298	
communality, 2298	Harris component analysis, 2296, 2298, 2313
compared with principal component analysis,	Harris-Kaiser method, 2296, 2322
2297	Heywood cases
Harris component analysis, 2298	FACTOR procedure, 2341
image component analysis, 2298	Howe's solution, 2301
interpreting, 2298	,
salience of loadings, 2298	image component analysis, 2296, 2298, 2314
uniqueness, 2298	interpretation
computational resources	factor rotation, 2298
FACTOR procedure, 2342	interpreting factors, elements to consider, 2299
confidence intervals, FACTOR procedure, 2336	iterated factor analysis, 2296
confidence limits, FACTOR procedure, 2336	• ,
covarimin method, 2296, 2322	matrix
coverage displays	factor, defined for factor analysis (FACTOR),
FACTOR procedure, 2337	2297
Crawford-Ferguson family, 2296	maximum likelihood factor analysis, 2296, 2314
•	with FACTOR procedure, 2301, 2302
Crawford-Ferguson method, 2321, 2322	memory requirements
degrees of freedom	FACTOR procedure, 2342
FACTOR procedure, 2324	ML factor analysis
TACTOR procedure, 2324	and computer time, 2301
equamax method, 2296, 2321, 2322	and confidence intervals, 2299, 2301, 2336
equalitizari inetifod, 2250, 2321, 2322	and multivariate normal distribution, 2301
factor	and standard errors, 2301
defined for factor analysis, 2297	and test of sphericity, 2301
factor analysis	and test of sphericity, 2501
compared to component analysis, 2296, 2297	oblimin method, 2296, 2322
factor parsimax method, 2296, 2321, 2322	oblique transformation, 2299, 2302
FACTOR procedure	ODS graph names
computational resources, 2342	FACTOR procedure, 2349
coverage displays, 2337	orthogonal transformation, 2299, 2302
degrees of freedom, 2324	orthomax method, 2296, 2321
Heywood cases, 2341	OUT= data sets
number of factors extracted, 2314	FACTOR procedure, 2320, 2334
ODS graph names, 2349	output data sets
ODO ETADII HAIHOS, 4947	outout uata sets

```
FACTOR procedure, 2301, 2320, 2334
OUTSTAT= data sets
    FACTOR procedure, 2334
parsimax method, 2296, 2322
path diagram
    path diagram (FACTOR), 2326
principal component analysis, 2296
    compared with common factor analysis, 2297
    with FACTOR procedure, 2299
principal factor analysis
    with FACTOR procedure, 2300
Procrustes method, 2296
Procrustes rotation, 2323
promax method, 2296, 2323
quartimax method, 2296, 2322, 2323
quartimin method, 2296, 2323
reference structure, 2302
salience of loadings, FACTOR procedure, 2298, 2336
scree plot, 2343
simplicity functions
    FACTOR procedure, 2298, 2321, 2337
time requirements
    FACTOR procedure, 2338, 2342
transformations
    oblique, 2299, 2302
    orthogonal, 2299, 2302
Tucker and Lewis's Reliability Coefficient, 2344
TYPE= data sets
    FACTOR procedure, 2334
ultra-Heywood cases, FACTOR procedure, 2341
unique factor
    defined for factor analysis, 2297
unweighted least squares factor analysis, 2296
variances
    FACTOR procedure, 2324
varimax method, 2296, 2322, 2323
weighting variables
    FACTOR procedure, 2340
```

Syntax Index

ALL option	NOEXOGVAR option, 2330
PROC FACTOR statement, 2311	NOTITLE option, 2330
ALPHA= option	NOVARIANCE option, 2330
PATHDIAGRAM statement, 2327	SALIENCE= option, 2328
PROC FACTOR statement, 2311	TITLE= option, 2330
ARRANGE= option	FACTOR procedure, PRIORS statement, 2331
PATHDIAGRAM statement, 2328	FACTOR procedure, PROC FACTOR statement, 2309
	ALL option, 2311
BY statement	ALPHA= option, 2311
FACTOR procedure, 2325	CONVERGE= option, 2312
	CORR option, 2312
CONVERGE= option	COVARIANCE option, 2312
PROC FACTOR statement, 2312	COVER= option, 2312
CORR option	DATA= option, 2312
PROC FACTOR statement, 2312	EIGENVECTORS option, 2312
COVARIANCE option	FLAG= option, 2312
PROC FACTOR statement, 2312	FUZZ= option, 2313
COVER= option	GAMMA= option, 2313
PATHDIAGRAM statement, 2328	HEYWOOD option, 2313
PROC FACTOR statement, 2312	HKPOWER= option, 2313
DATE.	MAXITER= option, 2313
DATA= option	METHOD= option, 2313
PROC FACTOR statement, 2312	MINEIGEN= option, 2314
DECP= option	MSA option, 2314
PATHDIAGRAM statement, 2328	NFACTORS= option, 2315
DIAGRAMLABEL= option	NOBS= option, 2315
PATHDIAGRAM statement, 2328	NOCORR option, 2315
EIGENVECTORS option	NOINT option, 2315
PROC FACTOR statement, 2312	NOPRINT option, 2315
FROC PACTOR statement, 2312	NOPROMAXNORM option, 2315
FACTOR procedure, 2309	NORM= option, 2315
syntax, 2309	NPLOTS= option, 2315
FACTOR procedure, BY statement, 2325	OUT= option, 2316
FACTOR procedure, FREQ statement, 2325	OUTSTAT= option, 2316
FACTOR procedure, PARTIAL statement, 2326	PARPREFIX= option, 2316
FACTOR procedure, PATHDIAGRAM statement,	PLOT option, 2316
2326	PLOTREF option, 2316
ALPHA= option, 2327	PLOTS= option, 2316
ARRANGE= option, 2328	POWER= option, 2319
COVER= option, 2328	PREFIX= option, 2319
DECP= option, 2328	PREPLOT option, 2319
DIAGRAMLABEL= option, 2328	PREROTATE= option, 2319
FACTORSIZE= option, 2329	PRINT option, 2319
FUZZ= option, 2329	PRIORS= option, 2319
LABEL= option, 2329	PROPORTION= option, 2320
NODELABEL= option, 2330	RANDOM= option, 2320
NOERRVAR option, 2330	RCONVERGE= option, 2320
NOESTIM ontion 2330	REORDER option, 2321

RESIDUALS option, 2321	PATHDIAGRAM statement, 2330
RITER= option, 2321	NOESTIM option
ROTATE= option, 2321	PATHDIAGRAM statement, 2330
ROUND option, 2323	NOEXOGVAR option
SCORE option, 2323	PATHDIAGRAM statement, 2330
SCREE option, 2323	NOINT option
SE option, 2323	PROC FACTOR statement, 2315
SIMPLE option, 2323	NOPRINT option
SINGULAR= option, 2324	PROC FACTOR statement, 2315
TARGET= option, 2324	NOPROMAXNORM option
TAU= option, 2324	PROC FACTOR statement, 2315
ULTRAHEYWOOD option, 2324	NORM= option
VARDEF= option, 2324	PROC FACTOR statement, 2315
WEIGHT option, 2324	NOTITLE option
FACTOR procedure, VAR statement, 2331	PATHDIAGRAM statement, 2330
FACTOR procedure, WEIGHT statement, 2331	NOVARIANCE option
FACTORSIZE= option	PATHDIAGRAM statement, 2330
PATHDIAGRAM statement, 2329	NPLOTS= option
	PROC FACTOR statement, 2315
FLAG= option PROC FACTOR statement, 2312	FROC FACTOR statement, 2313
PROC FACTOR statement, 2312	OUT= option
FREQ statement	PROC FACTOR statement, 2316
FACTOR procedure, 2325	OUTSTAT= option
FUZZ= option	PROC FACTOR statement, 2316
PATHDIAGRAM statement, 2329	TROCTACTOR statement, 2310
PROC FACTOR statement, 2313	PARPREFIX= option
GAMMA= option	PROC FACTOR statement, 2316
<u>*</u>	PARTIAL statement
PROC FACTOR statement, 2313	FACTOR procedure, 2326
HEYWOOD option	PATHDIAGRAM statement
PROC FACTOR statement, 2313	FACTOR procedure, 2326
HKPOWER= option	PLOT option
PROC FACTOR statement, 2313	PROC FACTOR statement, 2316
FROCTACTOR statement, 2313	PLOTREF option
LABEL= option	PROC FACTOR statement, 2316
PATHDIAGRAM statement, 2329	PLOTS= option
	PROC FACTOR statement, 2316
MAXITER= option	POWER= option
PROC FACTOR statement, 2313	1
METHOD= option	PROC FACTOR statement, 2319
PROC FACTOR statement, 2313	PREFIX= option
MINEIGEN= option	PROC FACTOR statement, 2319
PROC FACTOR statement, 2314	PREPLOT option
MSA option	PROC FACTOR statement, 2319
PROC FACTOR statement, 2314	PREROTATE= option
	PROC FACTOR statement, 2319
NFACTORS= option	PRINT option
PROC FACTOR statement, 2315	PROC FACTOR statement, 2319
NOBS= option	PRIORS statement
PROC FACTOR statement, 2315	FACTOR procedure, 2331
NOCORR option	PRIORS= option
PROC FACTOR statement, 2315	PROC FACTOR statement, 2319
NODELABEL= option	PROC FACTOR statement, see FACTOR procedure
PATHDIAGRAM statement, 2330	PROPORTION= option
NOERRVAR option	PROC FACTOR statement, 2320
A 1 C AND A 1 A 1 A 1 A 1 A 1 A 1 A 1 A 1 A 1 A	

RANDOM= option
PROC FACTOR statement, 2320
RCONVERGE= option
PROC FACTOR statement, 2320
REORDER option
PROC FACTOR statement, 2321
RESIDUALS option
PROC FACTOR statement, 2321
RITER= option
PROC FACTOR statement, 2321
ROTATE= option
PROC FACTOR statement, 2321
ROUND option
PROC FACTOR statement, 2323
SALIENCE= option
PATHDIAGRAM statement, 2328
SCORE option
PROC FACTOR statement, 2323
SCREE option
PROC FACTOR statement, 2323
SE option
PROC FACTOR statement, 2323
SIMPLE option
PROC FACTOR statement, 2323
SINGULAR= option
PROC FACTOR statement, 2324
TARGET= option
PROC FACTOR statement, 2324
TAU= option
PROC FACTOR statement, 2324
TITLE= option
PATHDIAGRAM statement, 2330
ULTRAHEYWOOD option
PROC FACTOR statement, 2324
VAD and a second
VAR statement
FACTOR procedure, 2331
VARDEF= option
PROC FACTOR statement, 2324
WEIGHT
WEIGHT option
PROC FACTOR statement, 2324
WEIGHT statement

FACTOR procedure, 2331