



SAS Publishing



Information Maps and Public Views in SAS[®] Activity-Based Management

The correct bibliographic citation for this manual is as follows: SAS Institute Inc. 2006. *Information Maps and Public Views in SAS® Activity-Based Management*. Cary, NC: SAS Institute Inc.

Information Maps and Public Views in SAS® Activity-Based Management

Copyright © 2006, SAS Institute Inc., Cary, NC, USA

All rights reserved. Produced in the United States of America.

For a hard-copy book: No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, or otherwise, without the prior written permission of the publisher, SAS Institute Inc.

For a Web download or e-book: Your use of this publication shall be governed by the terms established by the vendor at the time you acquire this publication.

U.S. Government Restricted Rights Notice. Use, duplication, or disclosure of this software and related documentation by the U.S. government is subject to the Agreement with SAS Institute and the restrictions set forth in FAR 52.227-19 Commercial Computer Software-Restricted Rights (June 1987).


SAS Institute Inc., SAS Campus Drive, Cary, North Carolina 27513.

1st printing, May 2006

SAS Publishing provides a complete selection of books and electronic products to help customers use SAS software to its fullest potential. For more information about our e-books, e-learning products, CDs, and hard-copy books, visit the SAS Publishing Web site at support.sas.com/pubs or call 1-800-727-3228.

SAS® and all other SAS Institute Inc. product or service names are registered trademarks or trademarks of SAS Institute Inc. in the USA and other countries. ® indicates USA registration.

Other brand and product names are registered trademarks or trademarks of their respective companies.



Information Maps and Public Views in SAS Activity-Based Management

<i>Information Maps</i>	1
<i>Table Column Descriptions</i>	1
<i>Account IMAP Schema</i>	2
<i>Assignment IMAP Schema</i>	7
<i>Public Views</i>	9
<i>Table Column Descriptions</i>	11
<i>M*_PublicAccount View</i>	11
<i>M*_PublicAssignment View</i>	13
<i>M*_PublicAssignmentExt View</i>	14
<i>M*_PublicAttributeValue View</i>	15
<i>M*_PublicDim1000Activities View</i>	15
<i>M*_PublicDimCostElement View</i>	16
<i>M*_PublicDimension View</i>	16
<i>M*_PublicDimMember View</i>	16
<i>M*_PublicDimModule View</i>	17
<i>M*_PublicDimYesNo View</i>	17
<i>M*_PublicDriver View</i>	17
<i>M*_PublicEnteredCE View</i>	18
<i>M*_PublicFactMSC View</i>	18
<i>M*_PublicFactRC View</i>	19
<i>PublicModel View</i>	20
<i>PublicModelStatus View</i>	20
<i>PublicPeriod View</i>	20
<i>PublicScenario View</i>	21

Information Maps

SAS Activity-Based Management provides two types of information maps: Account information maps and Assignment information maps. The tables in this section describe the schema for the Account information map and Assignment information map. Refer to the SAS Activity-Based Management online Help for a description of individual properties.

Table Column Descriptions

Public View Name:	The name of the view that is provided in the OEModel database and the source for the particular information map property
Field Name:	The field name that is provided in the information map
Field Type:	The definition of each field type (numeric or text field)
Join Field:	The specific ID fields to join between tables - these fields define keys that can be used to link multiple tables for reporting. This column identifies the corresponding join field for this information map.

Properties Reference: The specific corresponding property to reference in the SAS Activity-Based Management online Help for an explanation of the field's content

Model View Columns: The specific property that is displayed in the model column view

Account IMAP Schema

The following table contains the schema for the AccountIMAP information map. M*_**<ModelName>**_AccountMap (where * is the internal model database ID and **<ModelName>** is the name of the model) is the name of the information map that is provided in SAS Management Console -- for example, M1195_Inflight_AccountMap. This name is generated in the Register Metadata step for every model in SAS Activity-Based Management.

Table 1.1 Account IMAP schema

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Dim1000Activities	Act_L2	Text			Specific model dimension (Example: Activity)
Dim1000Activities	All_Activities	Text			Specific model dimension (Example - Activity)
Account	AllocatedCost	Number		Allocated Cost	Allocated Cost
Account	AssignedCost	Number		Assigned Cost	Assigned Cost
Account	AssignedIdleCost	Number		Assigned Idle Cost	Assigned Idle Cost
Account	AssignedIdleQuantity	Number		Assigned Idle Quantity	Assigned Idle Quantity
Account	AssignedNonReciprocalCost	Number		Assigned Non-Reciprocal Cost	Assigned Non-Reciprocal Cost
AttributeValue	Attribute	Text		Name	Name
ModelStatus	CalculationStatus	Text			Calculation status - not viewable in the user interface
Account	Cost	Number		Cost	Cost
Account	CostReceived	Number		Received Cost	Received Cost
Account	CostReceivedAssigned	Number		Received Assignment Cost	Received Assignment Cost
Account	CostReceivedBOC	Number		Received BOC Cost	Received BOC Cost


Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
ModelStatus	CubeStatus	Text			Cube status - not viewable in the user interface
Model	DefaultModelID	Number			ID values - not viewable in the user interface
Period	Description	Text			Description
Scenario	Description	Text			Description
Account	Dim1000	Number			Specific dimensions in the model
Account	DrivableCost	Number		Drivable Cost	Drivable Cost
Account	DrivenCost	Number		Driven Cost	Driven Cost
Account	DrivenQuantity	Number		Driven Quantity	Driven Quantity
Account	DriverId	Number	Driver.Id		ID values - not viewable in the user interface
Account	DriverRate	Number		Driver Rate	Driver Rate
Period	EndDate	Number			EndDate
Driver	Formula	Text		Driver Formula	Formula
Account	HasAssignments	Number		Has Assignments	Has assignments
Account	HasBOC	Number		Has BOC	Has BOC
Account	HasEnteredCost	Number		Has Entered Cost	Has Entered Cost
Account	HasIdleCost	Number		Has Idle Cost	Has Idle Cost
Account	HasNotes	Number		Has Notes	Has notes
Account	HasUsedCost	Number		Has Used Costs	Has Used Costs
Account	Id	Number			ID values - not viewable in the user interface
Dim1000Activities	Id	Number	Account.Dim1000		ID values - not viewable in the user interface
Dimension	Id	Number			ID values - not viewable in the user interface
DimMember	Id	Number			ID values - not viewable in the user interface
Driver	Id	Number	Driver.Id		ID values - not viewable in the user interface
Period	Id	Number	Period.Id		ID values - not viewable in the user interface
Scenario	Id	Number	Scenario.ID		ID values - not viewable in the user interface

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Account	IdleCost	Number		Idle Cost	Idle Cost
Account	IdlePercentage	Number		Idle Percentage	Idle Percentage
Account	IdleQuantity	Number		Idle Quantity	Idle Quantity
Driver	ImplementationType	Text		Driver Type	Driver Type
Account	InventoryCost	Number		Inventory Cost	Inventory Cost
Account	InventoryQuantity	Number		Inventory Quantity	Inventory Quantity
AttributeValue	ItemId	Number	Account.Id		ID values - not viewable in the user interface
Dim1000Activities	Level1	Text		Dimension Level Name	Dimension Level Name
DimMember	Levelid	Number		Dimension Level Number	Dimension Level Number
DimMember	LevelName	Text		Dimension Level Name	Dimension Level Name
Account	Measure	Text		Unit of Measure	Unit of measure
ModelStatus	ModelId	Number			ID values - not viewable in the user interface
Account	ModuleId	Number			ID values - not viewable in the user interface
Account	ModuleType	Text		Module Type	Module Type
DimMember	Name	Text		Dimension Member Name	Dimension Member Name
Dimension	Name	Text		Dimension Name	Dimension Name
Driver	Name	Text		Driver Name	Driver Name
Account	Name	Text		Name	Name
Period	Name	Text		Name	Name
Scenario	Name	Text		Name	Name
Model	Name	Text			Model
Account	Note	Text		Periodic Note	Periodic Note
AttributeValue	NumericValue	Number			Specific Attribute Value
Account	OutputQuantity	Number		Output Quantity	Output Quantity
DimMember	ParentId	Number			ID values - not viewable in the user interface

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Period	ParentId	Number	Period.Id		ID values - not viewable in the user interface
Scenario	ParentId	Number	Scenario.ID		ID values - not viewable in the user interface
ModelStatus	Period	Text		Name	Name
Account	PeriodId	Number	Period.Id		ID values - not viewable in the user interface
AttributeValue	PeriodId	Number	Period.Id		ID values - not viewable in the user interface
Account	Profit	Number		Profit	Profit
Account	PublishName	Text			ID values - not viewable in the user interface
Driver	QuantityType	Text			Driver checkbox: Shared or Unique
DimMember	Reference	Text		Dimension Member Reference	Dimension Member Reference
Account	Reference	Text		Reference	Reference
Period	Reference	Text		Reference	Reference
Scenario	Reference	Text		Reference	Reference
Account	Revenue	Number		Revenue	Revenue
ModelStatus	Scenario	Text		Name	Name
Account	ScenarioID	Number	Scenario.ID		ID values - not viewable in the user interface
AttributeValue	ScenarioId	Number	Scenario.ID		ID values - not viewable in the user interface
Account	SoldQuantity	Number		Sold Quantity	Sold Quantity
Period	StartDate	Number			StartDate
AttributeValue	StringValue	Text			Specific attribute value
Account	TotalDriverQuantity	Number		Total Driver Quantity (TDQ)	Total Driver Quantity (TDQ)
Account	TotalDriverQuantityBasic	Number		Total Driver Quantity Basic (TDQBasic)	Total Driver Quantity Basic (TDQBasic)
Account	TotalDriverQuantityCalculated	Number		Total Driver Quantity Calculated (TDQCalc)	Total Driver Quantity Calculated (TDQCalc)
Account	Type	Text		Type	Type
Account	UnassignedCost	Number		Unassigned Cost	Unassigned Cost
Account	UnassignedQuantity	Number		Unassigned Quantity	Unassigned Quantity

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Account	UnitCost	Number		Unit Cost	Unit Cost
Account	UnitCostEntered	Number		Unit Cost	Unit Cost - external units only
Account	UnitProfit	Number		Unit Profit	Unit Profit
Account	UnitRevenue	Number		Unit Revenue	Unit Revenue
Account	UsedCost	Number		Used Cost	Used Cost
Account	UsedQuantity	Number		Used Quantity	Used Quantity
Account	UserOutputQuantity	Number		Output Quantity UE	Output Quantity UE
Account	UserTotalDriverQuantity	Number		Total Driver Quantity UE (TDQUE)	Total Driver Quantity UE (TDQUE)

IMAP: Account Schema



Assignment IMAP Schema

The following table contains the schema for the AssignmentIMAP information map. M*_<ModelName>_AssignmentMap (where * is the internal model database ID and <ModelName> is the name of the model) is the name of the information map that is provided in SAS Management Console -- for example, M1195_Inflight_AssignmentMap. This name is generated in the **Register Metadata** step for every model in SAS Activity-Based Management.


Table 1.2 Assignment IMAP schema

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
AssignmentExt	AllocatedCost	Number		Allocated Cost	Allocated Cost
AssignmentExt	AssignedIdleQuantity	Number		Assigned Idle Quantity	Assigned Idle Quantity
AssignmentExt	Cost	Number		Cost	Cost
Period	Description	Text			Description
Scenario	Description	Text			Description

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
AssignmentExt	DestinationId	Number	Account.ID		ID values - not viewable in the user interface
AssignmentExt	DestinationName	Text		Name	Name
AssignmentExt	DestinationReference	Text		Reference	Reference
AssignmentExt	DrivenCost	Number		Driven Cost	Driven Cost
AssignmentExt	DrivenQuantity	Number		Driven Quantity	Driven Quantity
AssignmentExt	DriverId	Number	Driver.Id		ID values - not viewable in the user interface
Period	EndDate	Number			EndDate
AssignmentExt	FixedQuantity	Number		Driver Quantity Fixed	Driver Quantity Fixed
AssignmentExt	FixedWeight	Number		Driver Weight Fixed	Driver Weight Fixed
Driver	Formula	Text		Driver Formula	Formula
Driver	Id	Number	Driver.Id		ID values - not viewable in the user interface
Period	Id	Number	Period.Id		ID values - not viewable in the user interface
Scenario	Id	Number	Scenario.ID		ID values - not viewable in the user interface
AssignmentExt	IdleCost	Number		Idle Cost	Idle Cost
Driver	ImplementationType	Text		Driver Type	Driver Type
Driver	Name	Text		Driver Name	Driver Name
Period	Name	Text		Name	Name
Scenario	Name	Text		Name	Name
Period	ParentId	Number	Period.Id		ID values - not viewable in the user interface
Scenario	ParentId	Number	Scenario.ID		ID values - not viewable in the user interface
AssignmentExt	PeriodId	Number	Period.Id		ID values - not viewable in the user interface
AssignmentExt	QuantityBasic	Number		Driver Quantity Basic	Driver Quantity Basic
AssignmentExt	QuantityCalculated	Number		Driver Quantity Calculated	Driver Quantity Calculated
Driver	QuantityType	Text			Driver checkbox: Shared or Unique
Period	Reference	Text		Reference	Reference
Scenario	Reference	Text		Reference	Reference
AssignmentExt	ScenarioId	Number	Scenario.ID		ID values - not viewable in the user interface
AssignmentExt	SourceId	Number	Account.ID		ID values - not viewable in the user interface
AssignmentExt	SourceName	Text		Name	Name
AssignmentExt	SourceReference	Text		Reference	Reference
Period	StartDate	Number			StartDate

Public View Name	Field Name	Field Type	Join Field	Properties Reference	Model View Columns
AssignmentExt	UsedCost	Number		Used Cost	Used Cost
AssignmentExt	UserIdleQuantity	Number		Idle Driver Quantity UE	Idle Driver Quantity UE
AssignmentExt	VariableQuantity	Number		Driver Quantity Variable	Driver Quantity Variable
AssignmentExt	VariableWeight	Number		Driver Weight Variable	Driver Weight Variable

IMAP:Assignment Schema



Public Views

SAS Activity-Based Management creates public views for each model in the database. As an example, using Microsoft SQL Server Enterprise Manager, open the **Databases** folder and expand the OEModels database. Under OEModels, double-click the **Views** icon to display the database views for the various models in the right pane. Right-click the PublicModel view and select **Open View > Return all rows** to display the table view that maps a model ID to a model name. In this example, the Inflight model maps

to model ID 1195. The group of views that begin with M1195_* (where * is the internal database model ID that is found in the PublicModel view) specifically pertain to the Inflight model.

Listed below are the four non-model-specific views, followed by the model-specific views. Notice that some of these views are automatically created when the model is created, while others are created after you calculate the model.

Non-model specific view tables:

- PublicModel
- PublicModelStatus
- PublicPeriod
- PublicScenario

Model Specific view tables created when the model is created:

- M*_PublicAssignment
- M*_PublicAssignmentExt
- M*_PublicAttributeValue
- M*_PublicDimension
- M*_PublicDimMember
- M*_PublicDriver
- M*_PublicEnteredCE

Model Specific view tables created by calculating the model and selecting only **Calculate Costs**:

- M*_PublicAccount
- M*_PublicDim# (per # of dimensions in the model; includes both structural and attribute dimensions)
- M*_PublicDimCostElement
- M*_PublicDimDriver
- M*_PublicDimModule
- M*_PublicDimPeriod
- M*_PublicDimScenario
- M*_PublicDimYesNo

Model Specific view tables created by calculating the model and selecting **Generate Fact Tables**:

- M*_PublicFactMSC
- M*_PublicFactRC

These public view names can be found in the OEModel database and are automatically provided for every model in SAS Activity-Based Management. The tables in this section (arranged by public view name) describe the schema for each of the public views. Refer to the SAS Activity-Based Management online Help for a description of individual properties.

Table Column Descriptions

- Field Name: The field name that is provided in the public view
- Field Type: The definition of each field type (numeric or text field)
- Join Field: The specific ID fields to join between tables - these fields define keys that can be used to link multiple tables for reporting. This column identifies the corresponding join field.
- Properties Reference: The specific corresponding property to reference in the SAS Activity-Based Management online Help for an explanation of the field's content
- Model View Columns: The specific property that is displayed in the model column view

M*_PublicAccount View

Table 1.3 PublicAccount View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
AllocatedCost	Number		Allocated Cost	Allocated Cost
AssignedCost	Number		Assigned Cost	Assigned Cost
AssignedIdleCost	Number		Assigned Idle Cost	Assigned Idle Cost
AssignedIdleQuantity	Number		Assigned Idle Quantity	Assigned Idle Quantity
AssignedNonReciprocalCost	Number		Assigned Non-Reciprocal Cost	Assigned Non-Reciprocal Cost
Cost	Number		Cost	Cost
CostReceived	Number		Received Cost	Received Cost
CostReceivedAssigned	Number		Received Assignment Cost	Received Assignment Cost
CostReceivedBOC	Number		Received BOC Cost	Received BOC Cost
Dim1000	Number			Specific dimensions in the model
DrivableCost	Number		Drivable Cost	Drivable Cost
DrivenCost	Number		Driven Cost	Driven Cost
DrivenQuantity	Number		Driven Quantity	Driven Quantity
DriverId	Number	Driver.Id		ID values - not viewable in the user interface
DriverRate	Number		Driver Rate	Driver Rate
HasAssignments	Number		Has Assignments	Has Assignments
HasBOC	Number		Has BOC	Has BOC
HasEnteredCost	Number		Has Entered Cost	Has Entered Cost
HasIdleCost	Number		Has Idle Cost	Has Idle Cost

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
HasNotes	Number		Has Notes	Has Notes
HasUsedCost	Number		Has Used Costs	Has Used Costs
Id	Number			ID values - not viewable in the user interface
IdleCost	Number		Idle Cost	Idle Cost
IdlePercentage	Number		Idle Percentage	Idle Percentage
IdleQuantity	Number		Idle Quantity	Idle Quantity
InventoryCost	Number		Inventory Cost	Inventory Cost
InventoryQuantity	Number		Inventory Quantity	Inventory Quantity
Measure	Text		Unit of Measure	Unit of Measure
ModuleID	Number			ID values - not viewable in the user interface
ModuleType	Text		Module Type	Module Type
Name	Text		Name	Name
Note	Text		Periodic Note	Periodic Note
OutputQuantity	Number		Output Quantity	Output Quantity
PeriodId	Number	Period.Id		ID values - not viewable in the user interface
Profit	Number		Profit	Profit
PublishName	Text			ID values - not viewable in the user interface
Reference	Text		Reference	Reference
Revenue	Number		Revenue	Revenue
ScenarioID	Number	Scenario.ID		ID values - not viewable in the user interface
SoldQuantity	Number		Sold Quantity	Sold Quantity
TotalDriverQuantity	Number		Total Driver Quantity (TDQ)	Total Driver Quantity (TDQ)
TotalDriverQuantityBasic	Number		Total Driver Quantity Basic (TDQBasic)	Total Driver Quantity Basic (TDQBasic)
TotalDriverQuantityCalculated	Number		Total Driver Quantity Calculated (TDQCalc)	Total Driver Quantity Calculated (TDQCalc)
Type	Text		Type	Type
UnassignedCost	Number		Unassigned Cost	Unassigned Cost
UnassignedQuantity	Number		Unassigned Quantity	Unassigned Quantity
UnitCost	Number		Unit Cost	Unit Cost
UnitCostEntered	Number		Unit Cost	Unit Cost - external units only
UnitProfit	Number		Unit Profit	Unit Profit
UnitRevenue	Number		Unit Revenue	Unit Revenue
UsedCost	Number		Used Cost	Used Cost
UsedQuantity	Number		Used Quantity	Used Quantity
UserOutputQuantity	Number		Output Quantity UE	Output Quantity UE

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
UserTotalDriverQuantity	Number		Total Driver Quantity UE (TDQUE)	Total Driver Quantity UE (TDQUE)

M*_PublicAssignment View

Table 1.4 PublicAssignment View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
AllocatedCost	Number		Allocated Cost	Allocated Cost
AssignedIdleQuantity	Number		Assigned Idle Quantity	Assigned Idle Quantity
Cost	Number		Cost	Cost
DestinationId	Number	Account.ID		ID values - not viewable in the user interface
DestinationName	Text		Name	Name
DestinationReference	Text		Reference	Reference
DrivenCost	Number		Driven Cost	Driven Cost
DrivenQuantity	Number		Driven Quantity	Driven Quantity
DriverId	Number	Driver.Id		ID values - not viewable in the user interface
FixedQuantity	Number		Driver Quantity Fixed	Driver Quantity Fixed
FixedWeight	Number		Driver Weight Fixed	Driver Weight Fixed
IdleCost	Number		Idle Cost	Idle Cost
PeriodId	Number	Period.Id		ID values - not viewable in the user interface
QuantityBasic	Number		Driver Quantity Basic	Driver Quantity Basic
QuantityCalculated	Number		Driver Quantity Calculated	Driver Quantity Calculated
ScenarioId	Number	Scenario.ID		ID values - not viewable in the user interface
SourceId	Number	Account.ID		ID values - not viewable in the user interface
SourceName	Text		Name	Name
SourceReference	Text		Reference	Reference
UsedCost	Number		Used Cost	Used Cost
UserIdleQuantity	Number		Idle Driver Quantity UE	Idle Driver Quantity UE
VariableQuantity	Number		Driver Quantity Variable	Driver Quantity Variable
VariableWeight	Number		Driver Weight Variable	Driver Weight Variable

M*_PublicAssignmentExt View

Table 1.5 PublicAssignmentExt View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
AllocatedCost	Number		Allocated Cost	Allocated Cost
AssignedIdleQuantity	Number		Assigned Idle Quantity	Assigned Idle Quantity
Cost	Number		Cost	Cost
DestinationId	Number	Account.ID		ID values - not viewable in the user interface
DestinationName	Text		Name	Name
DestinationReference	Text		Reference	Reference
DrivenCost	Number		Driven Cost	Driven Cost
DriverId	Number			ID values - not viewable in the user interface
DriverQuantity	Number			Driver Quantity
FixedQuantity	Number		Driver Quantity Fixed	Driver Quantity Fixed
FixedWeight	Number		Driver Weight Fixed	Driver Weight Fixed
IdleCost	Number		Idle Cost	Idle Cost
PeriodID	Number	Period.Id		ID values - not viewable in the user interface
QuantityBasic	Number		Driver Quantity Basic	Driver Quantity Basic
QuantityCalculated	Number		Driver Quantity Calculated	Driver Quantity Calculated
ScenarioID	Number	Scenario.ID		ID values - not viewable in the user interface
SourceID	Number	Account.ID		ID values - not viewable in the user interface
SourceName	Text		Name	Name
SourceReference	Text		Reference	Reference
UsedCost	Number		Used Cost	Used Cost
UserIdleQuantity	Number		Idle Driver Quantity UE	Idle Driver Quantity UE
VariableQuantity	Number		Driver Quantity Variable	Driver Quantity Variable
VariableWeight	Number		Driver Weight Variable	Driver Weight Variable

M*_PublicAttributeValue View

Table 1.6 AttributeValue View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Attribute	Text		Name	Name
ItemId	Number	Account.Id		ID values - not viewable in the user interface
NumericValue	Number			Specific Attribute Value
PeriodId	Number	Period.Id		ID values - not viewable in the user interface
ScenarioId	Number	Scenario.ID		ID values - not viewable in the user interface
StringValue	Text			Specific attribute value

M*_PublicDim1000Activities View

Table 1.7 Dim1000Activities View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Act_L2	Text			Specific model dimension (Example: Activity)
All_Activities	Text			Specific model dimension (Example: Activity)
Id	Number	Account.Dim1000		ID values - not viewable in the user interface
Level1	Text		Dimension Level Name	Dimension Level Name

M*_PublicDimCostElement View

Table 1.8 DimCostElement View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
CostElementName	Number		Name	Name
ID	Number			ID values - not viewable in the user interface

M*_PublicDimension View

Table 1.9 Dimension View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Id	Number			ID values - not viewable in the user interface
Name	Text		Dimension Name	Dimension Name

M*_PublicDimMember View

Table 1.10 DimMember View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Id	Number			ID values - not viewable in the user interface
LevelId	Number		Dimension Level Number	Dimension Level Number
LevelName	Text		Dimension Level Name	Dimension Level Name
Name	Text		Dimension Member Name	Dimension Member Name
ParentId	Number			ID values - not viewable in the user interface
Reference	Text		Dimension Member Reference	Dimension Member Reference

M*_PublicDimModule View

Table 1.11 DimModule View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
ID	Number			ID values - not viewable in the user interface
ModuleName	Text		Module Type	Module

M*_PublicDimYesNo View

Table 1.12 DimYesNo View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
ID	Number			ID values - not viewable in the user interface
YesNoName	Text			Yes or No value

M*_PublicDriver View

Table 1.13 Driver View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Formula	Text		Driver Formula	Formula
Id	Number	Account.DriverId and Assignment.DriverId		ID values - not viewable in the user interface
ImplementationType	Text		Driver Type	Driver Type
Name	Text		Driver Name	Driver Name
QuantityType	Text			Driver checkbox: Shared or Unique

M*_PublicEnteredCE View

Table 1.14 EnteredCE View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Cost	Number		Cost	Cost
Name	Text		Name	Name
ParentId	Number	Account.ID		ID values - not viewable in the user interface
PeriodID	Number	Period.Id		ID values - not viewable in the user interface
Reference	Text		Reference	Reference
ScenarioId	Number	Scenario.ID		ID values - not viewable in the user interface

M*_PublicFactMSC View

Table 1.15 FactMSC View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
All_PeriodID	Number	Period.Id		ID values - not viewable in the user interface
All_ScenarioID	Number	Scenario.ID		ID values - not viewable in the user interface
Cost	Number		Cost	Cost
OutputQuantity	Number		Output Quantity	Output Quantity
Revenue	Number		Revenue	Revenue
S1Dim1004	Number	Join Dim Table		ID values - not viewable in the user interface
S2Dim1001	Number	Join Dim Table		ID values - not viewable in the user interface
S2Dim1002	Number	Join Dim Table		ID values - not viewable in the user interface
S3Dim1001	Number	Join Dim Table		ID values - not viewable in the user interface
S3Dim1003	Number	Join Dim Table		ID values - not viewable in the user interface
S4Dim1005	Number	Join Dim Table		ID values - not viewable in the user interface

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
S4Dim1006	Number	Join Dim Table		ID values - not viewable in the user interface
SoldQuantity	Number		Sold Quantity	Sold Quantity

M*_PublicFactRC View

Table 1.16 FactRC View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
All_PeriodID	Number	Period.Id		ID values - not viewable in the user interface
All_ReciprocalID	Number			ID values - not viewable in the user interface
All_ScenarioID	Number	Scenario.ID		ID values - not viewable in the user interface
All_Type	Number			ID values - not viewable in the user interface
Cost	Number		Cost	Cost
DriverQuantityCalculated	Number		Driver Quantity Calculated	Driver Quantity Calculated
Dst_Dim1005	Number	Join Dim Table		ID values - not viewable in the user interface
Dst_Dim1006	Number	Join Dim Table		ID values - not viewable in the user interface
Dst_DriverId	Number	Driver.Id		ID values - not viewable in the user interface
Dst_ModuleId	Number	Module.Id		ID values - not viewable in the user interface
OutputQuantity_I	Number		Output Quantity	Output Quantity
Revenue_I	Number		Revenue	Revenue
SoldQuantity_I	Number		Sold Quantity	Sold Quantity
Src_Dim1001	Number	Join Dim Table		ID values - not viewable in the user interface
Src_Dim1002	Number	Join Dim Table		ID values - not viewable in the user interface
Src_Dim1004	Number	Join Dim Table		ID values - not viewable in the user interface
Src_DriverID	Number	Driver.Id		ID values - not viewable in the user interface
Src_ModuleId	Number	Module.Id		ID values - not viewable in the user interface

PublicModel View

Table 1.17 Model View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
DefaultModelID	Number			ID values - not viewable in the user interface
Name	Text			Model

PublicModelStatus View

Table 1.18 ModelStatus View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
CalculationStatus	Text			Calculation status - not viewable in the user interface
CubeStatus	Text			Cube status - not viewable in the user interface
ModelId	Number			ID values - not viewable in the user interface
Period	Text		Name	Name
Scenario	Text		Name	Name

PublicPeriod View

Table 1.19 Period View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Description	Text			Description
EndDate	Number			EndDate
Id	Number	PeriodId		ID values - not viewable in the user interface
Name	Text		Name	Name
ParentId	Number	PeriodId		ID values - not viewable in the user interface
Reference	Text		Reference	Reference
StartDate	Number			StartDate

PublicScenario View

Table 1.20 Scenario View

Field Name	Field Type	Join Field	Properties Reference	Model View Columns
Description	Text			Description
Id	Number	ScenarioID		ID values - not viewable in the user interface
Name	Text		Name	Name
ParentId	Number	ScenarioID		ID values - not viewable in the user interface
Reference	Text		Reference	Reference