

# SAS/STAT® 9.22 User's Guide The STEPDISC Procedure (Book Excerpt)



This document is an individual chapter from SAS/STAT® 9.22 User's Guide.

The correct bibliographic citation for the complete manual is as follows: SAS Institute Inc. 2010. SAS/STAT® 9.22 User's Guide. Cary, NC: SAS Institute Inc.

Copyright © 2010, SAS Institute Inc., Cary, NC, USA

All rights reserved. Produced in the United States of America.

For a Web download or e-book: Your use of this publication shall be governed by the terms established by the vendor at the time you acquire this publication.

**U.S. Government Restricted Rights Notice**: Use, duplication, or disclosure of this software and related documentation by the U.S. government is subject to the Agreement with SAS Institute and the restrictions set forth in FAR 52.227-19, Commercial Computer Software-Restricted Rights (June 1987).

SAS Institute Inc., SAS Campus Drive, Cary, North Carolina 27513.

1st electronic book, May 2010

SAS® Publishing provides a complete selection of books and electronic products to help customers use SAS software to its fullest potential. For more information about our e-books, e-learning products, CDs, and hard-copy books, visit the SAS Publishing Web site at **support.sas.com/publishing** or call 1-800-727-3228.

 $SAS^{\scriptsize @}$  and all other SAS Institute Inc. product or service names are registered trademarks or trademarks of SAS Institute Inc. in the USA and other countries.  $\tiny @$  indicates USA registration.

Other brand and product names are registered trademarks or trademarks of their respective companies.

# Chapter 83

# The STEPDISC Procedure

Contents		
C	Overview: STEPDISC Procedure	7021
C	Getting Started: STEPDISC Procedure	7023
S	Syntax: STEPDISC Procedure	7027
	PROC STEPDISC Statement	7028
	BY Statement	7032
	CLASS Statement	7032
	FREQ Statement	7033
	VAR Statement	7033
	WEIGHT Statement	7033
Γ	Details: STEPDISC Procedure	7034
	Missing Values	7034
	Input Data Sets	7034
	Computational Resources	7035
	Displayed Output	7036
	ODS Table Names	7038
E	Example: STEPDISC Procedure	7039
	Example 83.1: Performing a Stepwise Discriminant Analysis	7039
R	References	7046

# **Overview: STEPDISC Procedure**

Given a classification variable and several quantitative variables, the STEPDISC procedure performs a stepwise discriminant analysis to select a subset of the quantitative variables for use in discriminating among the classes. The set of variables that make up each class is assumed to be multivariate normal with a common covariance matrix. The STEPDISC procedure can use forward selection, backward elimination, or stepwise selection (Klecka 1980). The STEPDISC procedure is a useful prelude to further analyses with the CANDISC procedure or the DISCRIM procedure.

With PROC STEPDISC, variables are chosen to enter or leave the model according to one of two criteria:

- the significance level of an F test from an analysis of covariance, where the variables already chosen act as covariates and the variable under consideration is the dependent variable
- the squared partial correlation for predicting the variable under consideration from the CLASS variable, controlling for the effects of the variables already selected for the model

Forward selection begins with no variables in the model. At each step, PROC STEPDISC enters the variable that contributes most to the discriminatory power of the model as measured by Wilks' lambda, the likelihood ratio criterion. When none of the unselected variables meet the entry criterion, the forward selection process stops.

Backward elimination begins with all variables in the model except those that are linearly dependent on previous variables in the VAR statement. At each step, the variable that contributes least to the discriminatory power of the model as measured by Wilks' lambda is removed. When all remaining variables meet the criterion to stay in the model, the backward elimination process stops.

Stepwise selection begins, like forward selection, with no variables in the model. At each step, the model is examined. If the variable in the model that contributes least to the discriminatory power of the model as measured by Wilks' lambda fails to meet the criterion to stay, then that variable is removed. Otherwise, the variable not in the model that contributes most to the discriminatory power of the model is entered. When all variables in the model meet the criterion to stay and none of the other variables meet the criterion to enter, the stepwise selection process stops. Stepwise selection is the default method of variable selection.

It is important to realize that, in the selection of variables for entry, only one variable can be entered into the model at each step. The selection process does not take into account the relationships between variables that have not yet been selected. Thus, some important variables could be excluded in the process. Also, Wilks' lambda might not be the best measure of discriminatory power for your application. However, if you use PROC STEPDISC carefully, in combination with your knowledge of the data and careful cross validation, it can be a valuable aid in selecting variables for a discrimination model.

As with any stepwise procedure, it is important to remember that when many significance tests are performed, each at a level of, for example, 5% (0.05), the overall probability of rejecting at least one true null hypothesis is much larger than 5%. If you want to prevent including any variables that do not contribute to the discriminatory power of the model in the population, you should specify a very small significance level. In most applications, all variables considered have some discriminatory power, however small. To choose the model that provides the best discrimination by using the sample estimates, you need only to guard against estimating more parameters than can be reliably estimated with the given sample size.

Costanza and Afifi (1979) use Monte Carlo studies to compare alternative stopping rules that can be used with the forward selection method in the two-group multivariate normal classification problem. Five different numbers of variables, ranging from 10 to 30, are considered in the studies. The comparison is based on conditional and estimated unconditional probabilities of correct classification. They conclude that the use of a moderate significance level, in the range of 10 to 25 percent, often performs better than the use of a much larger or a much smaller significance level.

The significance level and the squared partial correlation criteria select variables in the same order, although they might select different numbers of variables. Increasing the sample size tends to increase the number of variables selected when you are using significance levels, but it has little effect on the number selected by using squared partial correlations.

See Chapter 10, "Introduction to Discriminant Procedures," for more information about discriminant analysis.

# **Getting Started: STEPDISC Procedure**

The data in this example are measurements of 159 fish caught in Finland's lake Laengelmavesi; this data set is available from the Puranen. For each of the seven species (bream, roach, whitefish, parkki, perch, pike, and smelt) the weight, length, height, and width of each fish are tallied. Three different length measurements are recorded: from the nose of the fish to the beginning of its tail, from the nose to the notch of its tail, and from the nose to the end of its tail. The height and width are recorded as percentages of the third length variable. PROC STEPDISC will select a subset of the six quantitative variables that might be useful for differentiating between the fish species. This subset is used in conjunction with PROC CANDISC and PROC DISCRIM to develop discrimination models.

The following steps create the data set fish and use PROC STEPDISC to select a subset of potential discriminator variables. By default, PROC STEPDISC uses stepwise selection on all numeric variables that are not listed in other statements, and the significance levels for a variable to enter the subset and to stay in the subset are set to 0.15. The following statements produce Figure 83.1 through Figure 83.5:

```
title 'Fish Measurement Data';
proc format;
   value specfmt
      1='Bream'
      2='Roach'
      3='Whitefish'
      4='Parkki'
      5='Perch'
      6='Pike'
      7='Smelt';
run;
data fish (drop=HtPct WidthPct);
   input Species Weight Length1 Length2 Length3 HtPct WidthPct @@;
   Height=HtPct*Length3/100;
   Width=WidthPct *Length3/100;
   format Species specfmt.;
   datalines;
  242.0 23.2 25.4 30.0 38.4 13.4 1 290.0 24.0 26.3 31.2 40.0 13.8
1 340.0 23.9 26.5 31.1 39.8 15.1 1 363.0 26.3 29.0 33.5 38.0 13.3
  430.0 26.5 29.0 34.0 36.6 15.1 1 450.0 26.8 29.7 34.7 39.2 14.2
   ... more lines ...
7
    19.7 13.2 14.3 15.2 18.9 13.6 7 19.9 13.8 15.0 16.2 18.1 11.6
proc stepdisc data=fish;
   class Species;
run;
```

PROC STEPDISC begins by displaying summary information about the analysis (see Figure 83.1). This information includes the number of observations with nonmissing values, the number of classes in the classification variable (specified by the CLASS statement), the number of quantitative variables under consideration, the significance criteria for variables to enter and to stay in the model, and the method of variable selection being used. The frequency of each class is also displayed.

Figure 83.1 Summary Information

	Fish		aca		
	The S	STEPDISC Proce	dure		
The	Method for Sel	lecting Variab	les is STEPW	IISE	
Total Sample Siz	ze 158	Variable	(s) in the A	malysis	6
Class Levels	7	Variable	(s) Will Be	Included	0
		Signific	ance Level t	o Enter	0.15
		Signific	ance Level t	o Stay	0.15
ľ	Number of Obser	rvations kead		.59	
=	Number of Obser		1	.58	
=	Number of Obser	rvations Used	1		
=	Number of Obser	rvations Used	1	.58	on
ī	Number of Obser Class Variable	rvations Used Level Informa	1	Proportion	
Species	Number of Obser Class Variable Name	rvations Used  Level Informa  Frequency	tion Weight 34.0000	Proportion 0.2151	90
Species Bream	Number of Obser Class Variable Name Bream	rvations Used  Level Informa  Frequency  34	1 tion Weight 34.0000 11.0000	Proportion 0.2151: 0.0696	90 20
Species Bream Parkki	Number of Obser Class Variable Name Bream Parkki	rvations Used  Level Informa  Frequency  34 11	Tion  Weight  34.0000  11.0000  56.0000	Proportion 0.2151 0.06962 0.3544	90 20 30
Species Bream Parkki Perch Pike	Variable Name Bream Parkki Perch	rvations Used  Level Informa  Frequency  34  11  56	Weight 34.0000 11.0000 56.0000 17.0000	Proportion 0.2151 0.0696 0.3544 0.1075	90 20 30 95
Species Bream Parkki Perch Pike	Variable Name Bream Parkki Perch Pike Roach	rvations Used  Level Informa  Frequency  34  11  56  17	Weight 34.0000 11.0000 56.0000 17.0000 20.0000	Proportion 0.21519 0.06969 0.35440 0.10759 0.12656	90 20 30 95

For each entry step, the statistics for entry are displayed for all variables not currently selected (see Figure 83.2). The variable selected to enter at this step (if any) is displayed, as well as all the variables currently selected. Next are multivariate statistics that take into account all previously selected variables and the newly entered variable.

Figure 83.2 Step 1: Variable HEIGHT Selected for Entry

	Fish 1	Measurement D	ata			
	The S	TEPDISC Proce	dure			
	Stepwis	e Selection:	Step 1			
	<b>G</b> +-+:-+:	f 8 DB	_ ( 151			
	Statistics	for Entry, DF	= 6, 151			
Variable	R-Square	F Value	Pr > F	Toleran	ce	
Weight	0.3750	15.10	<.0001	1.00	00	
Length1	0.6017	38.02	<.0001	1.00	00	
Length2	0.6098	39.32	<.0001	1.00	00	
Length3	0.6280	42.49		1.00	00	
Height	0.7553	77.69	<.0001	1.00	00	
Width	0.4806	23.29	<.0001	1.00	00	
	Variable H	eight will be	entered.			
	Variable(s)	That Have Be	en Entered			
		Height				
	Multiva	ariate Statis	tics			
Statistic		Value	F Value	Num DF	Den DF	Pr > F
Wilks' Lambda		0.244670	77.69	6	151	<.0001
Pillai's Trace		0.755330	77.69	6	151	<.0001
Average Squared Canon:	ical	0.125888				
Correlation						

For each removal step (Figure 83.3), the statistics for removal are displayed for all variables currently entered. The variable to be removed at this step (if any) is displayed. If no variable meets the criterion to be removed and the maximum number of steps as specified by the MAXSTEP= option has not been attained, then the procedure continues with another entry step.

Figure 83.3 Step 2: No Variable Is Removed; Variable Length2 Added

```
Fish Measurement Data

The STEPDISC Procedure
Stepwise Selection: Step 2

Statistics for Removal, DF = 6, 151

Variable R-Square F Value Pr > F

Height 0.7553 77.69 <.0001

No variables can be removed.
```

Figure 83.3 continued

	Statistics f	for Entry, DF	= 6, 150			
	Partial					
Variable	R-Square	F Value	Pr > F	Toleran	ce	
Weight	0.7388	70.71	<.0001	0.46	90	
Length1	0.9220	295.35	<.0001	0.60	83	
Length2	0.9229	299.31	<.0001	0.58	92	
Length3	0.9173	277.37	<.0001	0.50	56	
Width	0.8783	180.44	<.0001	0.36	99	
	Variable Ler	ngth2 will be	entered.			
	Variable(s)	That Have Be	en Entered	I		
	Le	ength2 Height				
	Multiva	ariate Statis	tics			
Statistic		Value	F Value	Num DF	Den DF	Pr > F
Wilks' Lambda		0.018861	157.04	12	300	<.0001
Pillai's Trace		1.554349	87.78	12	302	<.0001
Average Squared Canonic	al	0.259058				
Correlation						

The stepwise procedure terminates either when no variable can be removed and no variable can be entered or when the maximum number of steps as specified by the MAXSTEP= option has been attained. In this example at step 7 no variables can be either removed or entered (Figure 83.4). Steps 3 through 6 are not displayed in this document.

Figure 83.4 Step 7: No Variables Entered or Removed

	The STEPDISC	Procedure		
Si	cepwise Selec	tion: Step	7	
Statis	cics for Remo	val, DF = 6	, 146	
	Partial			
Variable	R-Square	F Value	Pr > F	
Weight	0.4521	20.08	<.0001	
Length1	0.2987	10.36	<.0001	
Length2	0.5250	26.89	<.0001	
Length3	0.7948	94.25	<.0001	
Height	0.7257	64.37	<.0001	
Width	0.5757	33.02	<.0001	
V-	variables ca	- <b>L</b>	a	

PROC STEPDISC ends by displaying a summary of the steps.

Figure 83.5 Step Summary

```
No further steps are possible.
                             Fish Measurement Data
                             The STEPDISC Procedure
                           Stepwise Selection Summary
                                                                 Average
                                                                 Squared
                         Partial
                                                 Wilks' Pr < Canonical
    Number
                                                                         Pr >
Step
      In Entered Removed R-Square F Value Pr > F
                                                                          ASCC
                                                Lambda Lambda Correlation
                         0.7553 77.69 <.0001 0.24466983 <.0001 0.12588836 <.0001
  1
        1 Height
        2 Length2
3 Length3
4 Width
  2
                         0.9229 299.31 <.0001 0.01886065 <.0001 0.25905822 <.0001
                         0.8826 186.77 <.0001 0.00221342 <.0001 0.38427100 <.0001
  4
                         0.5775 33.72 <.0001 0.00093510 <.0001 0.45200732 <.0001
  5
        5 Weight
                         0.4461 19.73 <.0001 0.00051794 <.0001 0.49488458 <.0001
        6 Length1
```

All the variables in the data set are found to have potential discriminatory power. These variables are used to develop discrimination models in both the CANDISC and DISCRIM procedure chapters.

# **Syntax: STEPDISC Procedure**

The following statements are available in PROC STEPDISC:

```
PROC STEPDISC < options>;
CLASS variable;
BY variables;
FREQ variable;
VAR variables;
WEIGHT variable;
```

The BY, CLASS, FREQ, VAR, and WEIGHT statements are described after the PROC STEPDISC statement.

# **PROC STEPDISC Statement**

#### PROC STEPDISC < options > ;

The PROC STEPDISC statement invokes the STEPDISC procedure. The options listed in Table 83.1 are available in the PROC STEPDISC statement.

Table 83.1 STEPDISC Procedure Options

Option	Description
Input Data Set	
DATA=	specifies input SAS data set
<b>Method Details</b>	
MAXMACRO=	specifies maximum macro variable lists
METHOD=	specifies method
SINGULAR=	specifies singularity
<b>Control Stepwis</b>	e Selection
SLENTRY=	specifies entry significance
SLSTAY=	specifies staying significance
PR2ENTRY=	specifies entry partial R square
PR2STAY=	specifies staying partial R square
INCLUDE=	forces inclusion of variables
MAXSTEP=	specifies maximum number of steps
START=	specifies variables to begin
STOP=	specifies number of variables in final model
<b>Control Display</b>	ed Output
ALL	displays all
BCORR	displays between correlations
BCOV	displays between covariances
BSSCP	displays between SSCPs
PCORR	displays pooled correlations
PCOV	displays pooled covariances
PSSCP	displays pooled SSCPs
SHORT	suppresses output
SIMPLE	displays descriptive statistics
STDMEAN	displays standardized class means
TCORR	displays total correlations
TCOV	displays total covariances
TSSCP	displays total SSCPs
WCORR	displays within correlations
WCOV	displays within covariances
WSSCP	displays within SSCPs

#### **ALL**

activates all of the display options.

#### **BCORR**

displays between-class correlations.

#### **BCOV**

displays between-class covariances. The between-class covariance matrix equals the between-class SSCP matrix divided by n(c-1)/c, where n is the number of observations and c is the number of classes. The between-class covariances should be interpreted in comparison with the total-sample and within-class covariances, not as formal estimates of population parameters.

#### **BSSCP**

displays the between-class SSCP matrix.

#### DATA=SAS-data-set

specifies the data set to be analyzed. The data set can be an ordinary SAS data set or one of several specially structured data sets created by statistical procedures available with SAS/STAT software. These specially structured data sets include TYPE=CORR, COV, CSSCP, and SSCP. If the DATA= option is omitted, the procedure uses the most recently created SAS data set.

#### INCLUDE=n

includes the first *n* variables in the VAR statement in every model. By default, INCLUDE=0.

#### MAXMACRO=n

specifies the maximum number of macro variables with independent variable lists to create. By default, MAXMACRO=100. PROC STEPDISC saves the list of selected variables in a macro variable, &\_StdVar. Suppose your input variable list consists of x1-x10; then &\_StdVar would be set to x1 x3 x4 x10 if, for example, the first, third, fourth, and tenth variables were selected for the model. This list can be used, for example, in a subsequent procedure's VAR statement as follows:

#### var &\_stdvar;

With BY processing, one macro variable is created for each BY group, and the macro variables are indexed by the BY-group number. The MAXMACRO= option can be used to either limit or increase the number of these macro variables in processing data sets with many BY groups. The macro variables are created as follows:

With no BY processing, PROC STEPDISC creates the following:

\_StdVar selected variables StdVar1 selected variables

\_StdNumBys number of BY groups (1)

\_StdNumMacroBys number of \_StdVari macro variables actually made (1)

#### With BY processing, PROC STEPDISC creates the following:

\_StdVar selected variables for BY group 1
\_StdVar1 selected variables for BY group 1
StdVar2 selected variables for BY group 2

•

.

\_StdVarm selected variables for BY group m, where a number is

substituted for m

\_StdNumBys n, the number of BY groups

\_StdNumMacroBys the number *m* of \_StdVar*i* macro variables actually made.

This value might be less than  $\_$ StdNumbys = n, and it is

less than or equal to the MAXMACRO= value.

#### MAXSTEP=n

specifies the maximum number of steps. By default, MAXSTEP= two times the number of variables in the VAR statement.

#### METHOD=BACKWARD | BW

#### METHOD=FORWARD | FW

#### METHOD=STEPWISE | SW

specifies the method used to select the variables in the model. The BACKWARD method specifies backward elimination, FORWARD specifies forward selection, and STEPWISE specifies stepwise selection. By default, METHOD=STEPWISE.

#### **PCORR**

displays pooled within-class correlations (partial correlations based on the pooled within-class covariances).

#### **PCOV**

displays pooled within-class covariances.

#### **PR2ENTRY**=*p*

#### PR2E=p

specifies the partial R square for adding variables in the forward selection mode, where  $p \le 1$ .

#### PR2STAY=p

#### PR2S=p

specifies the partial R square for retaining variables in the backward elimination mode, where  $p \le 1$ .

#### **PSSCP**

displays the pooled within-class corrected SSCP matrix.

#### SHORT

suppresses the displayed output from each step.

#### SIMPLE

displays simple descriptive statistics for the total sample and within each class.

#### SINGULAR=p

specifies the singularity criterion for entering variables, where 0 . PROC STEPDISC precludes the entry of a variable if the squared multiple correlation of the variable with the variables already in the model exceeds <math>1 - p. With more than one variable already in the model, PROC STEPDISC also excludes a variable if it would cause any of the variables already in the model to have a squared multiple correlation (with the entering variable and the other variables in the model) exceeding 1 - p. By default, SINGULAR= 1E-8.

#### **SLENTRY**=*p*

#### SLE=p

specifies the significance level for adding variables in the forward selection mode, where 0 . The default value is 0.15.

#### SLSTAY=p

#### SLS=p

specifies the significance level for retaining variables in the backward elimination mode, where  $0 \le p \le 1$ . The default value is 0.15.

#### START=n

specifies that the first *n* variables in the VAR statement be used to begin the selection process. When you specify METHOD=FORWARD or METHOD=STEPWISE, the default value is 0; when you specify METHOD=BACKWARD, the default value is the number of variables in the VAR statement.

#### **STDMEAN**

displays total-sample and pooled within-class standardized class means.

#### STOP=n

specifies the number of variables in the final model. The STEPDISC procedure stops the selection process when a model with *n* variables is found. This option applies only when you specify METHOD=FORWARD or METHOD=BACKWARD. When you specify METHOD=FORWARD, the default value is the number of variables in the VAR statement; when you specify METHOD=BACKWARD, the default value is 0.

#### **TCORR**

displays total-sample correlations.

#### **TCOV**

displays total-sample covariances.

#### **TSSCP**

displays the total-sample corrected SSCP matrix.

#### **WCORR**

displays within-class correlations for each class level.

#### **WCOV**

displays within-class covariances for each class level.

#### **WSSCP**

displays the within-class corrected SSCP matrix for each class level.

#### **BY Statement**

#### BY variables;

You can specify a BY statement with PROC STEPDISC to obtain separate analyses on observations in groups that are defined by the BY variables. When a BY statement appears, the procedure expects the input data set to be sorted in order of the BY variables. If you specify more than one BY statement, only the last one specified is used.

If your input data set is not sorted in ascending order, use one of the following alternatives:

- Sort the data by using the SORT procedure with a similar BY statement.
- Specify the NOTSORTED or DESCENDING option in the BY statement for the STEPDISC procedure. The NOTSORTED option does not mean that the data are unsorted but rather that the data are arranged in groups (according to values of the BY variables) and that these groups are not necessarily in alphabetical or increasing numeric order.
- Create an index on the BY variables by using the DATASETS procedure (in Base SAS software).

For more information about BY-group processing, see the discussion in SAS Language Reference: Concepts. For more information about the DATASETS procedure, see the discussion in the Base SAS Procedures Guide.

#### **CLASS Statement**

#### CLASS variable;

The values of the CLASS variable define the groups for analysis. Class levels are determined by the formatted values of the CLASS variable. The CLASS variable can be numeric or character. A CLASS statement is required.

#### **FREQ Statement**

#### FREQ variable;

If a variable in the data set represents the frequency of occurrence for the other values in the observation, include the name of the variable in a FREQ statement. The procedure then treats the data set as if each observation appears n times, where n is the value of the FREQ variable for the observation. The total number of observations is considered to be equal to the sum of the FREQ variable when the procedure determines degrees of freedom for significance probabilities.

If the value of the FREQ variable is missing or is less than one, the observation is not used in the analysis. If the value is not an integer, the value is truncated to an integer.

#### **VAR Statement**

#### VAR variables;

The VAR statement specifies the quantitative variables eligible for selection. The default is all numeric variables not listed in other statements.

#### **WEIGHT Statement**

#### **WEIGHT** variable;

To use relative weights for each observation in the input data set, place the weights in a variable in the data set and specify the name in a WEIGHT statement. This is often done when the variance associated with each observation is different and the values of the WEIGHT variable are proportional to the reciprocals of the variances. If the value of the WEIGHT variable is missing or is less than zero, then a value of zero for the weight is assumed.

The WEIGHT and FREQ statements have a similar effect except that the WEIGHT statement does not alter the degrees of freedom.

# **Details: STEPDISC Procedure**

## Missing Values

Observations containing missing values are omitted from the analysis.

#### **Input Data Sets**

The input data set can be an ordinary SAS data set or one of several specially structured data sets created by statistical procedures available with SAS/STAT software. For more information about these data sets, see Appendix A, "Special SAS Data Sets." The BY variable in these data sets becomes the CLASS variable in PROC STEPDISC. These specially structured data sets include the following:

- TYPE=CORR data sets created by PROC CORR by using a BY statement
- TYPE=COV data sets created by PROC PRINCOMP by using both the COV option and a BY statement
- TYPE=CSSCP data sets created by PROC CORR by using the CSSCP option and a BY statement, where the OUT= data set is assigned TYPE=CSSCP with the TYPE= data set option
- TYPE=SSCP data sets created by PROC REG by using both the OUTSSCP= option and a BY statement

When the input data set is TYPE=CORR, TYPE=COV, or TYPE=CSSCP, the STEPDISC procedure reads the number of observations for each class from the observations with \_TYPE\_='N' and the variable means in each class from the observations with \_TYPE\_='MEAN'. The procedure then reads the within-class correlations from the observations with \_TYPE\_='CORR', the standard deviations from the observations with \_TYPE\_='STD' (data set TYPE=CORR), the within-class covariances from the observations with \_TYPE\_='COV' (data set TYPE=COV), or the within-class corrected sums of squares and crossproducts from the observations with \_TYPE\_='CSSCP' (data set TYPE=CSSCP).

When the data set does not include any observations with \_TYPE\_='CORR' (data set TYPE=CORR), \_TYPE\_='COV' (data set TYPE=COV), or \_TYPE\_='CSSCP' (data set TYPE=CSSCP) for each class, PROC STEPDISC reads the pooled within-class information from the data set. In this case, the STEPDISC procedure reads the pooled within-class correlations from the observations with \_TYPE\_='PCORR', the pooled within-class standard deviations from the observations with \_TYPE\_='PSTD' (data set TYPE=CORR), the pooled within-class covariances from the observations with \_TYPE\_='PCOV' (data set TYPE=COV), or the pooled within-class corrected SSCP matrix from the observations with\_TYPE\_='PSSCP' (data set TYPE=CSSCP).

When the input data set is TYPE=SSCP, the STEPDISC procedure reads the number of observations for each class from the observations with \_TYPE\_='N', the sum of weights of observations from the variable INTERCEPT in observations with \_TYPE\_='SSCP' and \_NAME\_='INTERCEPT', the variable sums from the variable=*variablenames* in observations with \_TYPE\_='SSCP' and \_NAME\_='INTERCEPT', and the uncorrected sums of squares and crossproducts from the variable=*variablenames* in observations with \_TYPE\_='SSCP' and \_NAME\_=*variablenames*.

## **Computational Resources**

In the following discussion, let

n = number of observations

c = number of class levels

v = number of variables in the VAR list

l = length of the CLASS variable

t = v + c - 1

#### **Memory Requirements**

The amount of memory in bytes for temporary storage needed to process the data is

$$c(4v^2 + 28v + 3l + 4c + 72) + 16v^2 + 92v + 4t^2 + 20t + 4l$$

Additional temporary storage of 72 bytes at each step is also required to store the results.

#### **Time Requirements**

The following factors determine the time requirements of a stepwise discriminant analysis:

- The time needed for reading the data and computing covariance matrices is proportional to  $nv^2$ . The STEPDISC procedure must also look up each class level in the list. This is faster if the data are sorted by the CLASS variable. The time for looking up class levels is proportional to a value ranging from n to  $n \ln(c)$ .
- The time needed for stepwise discriminant analysis is proportional to the number of steps required to select the set of variables in the discrimination model. The number of steps required depends on the data set itself and the selection method and criterion used in the procedure. Each forward or backward step takes time proportional to  $(v + c)^2$ .

## **Displayed Output**

The displayed output from PROC STEPDISC includes the class level information table. For each level of the classification variable, the following information is provided: the output data set variable name, frequency sum, weight sum, and the proportion of the total sample.

The optional output from PROC STEPDISC includes the following:

The optional output includes the following:

- Within-class SSCP matrices for each group
- Pooled within-class SSCP matrix
- Between-class SSCP matrix
- Total-sample SSCP matrix
- Within-class covariance matrices for each group
- Pooled within-class covariance matrix
- Between-class covariance matrix, equal to the between-class SSCP matrix divided by n(c-1)/c, where n is the number of observations and c is the number of classes
- Total-sample covariance matrix
- Within-class correlation coefficients and Pr > |r| to test the hypothesis that the within-class population correlation coefficients are zero
- Pooled within-class correlation coefficients and Pr > |r| to test the hypothesis that the partial population correlation coefficients are zero
- Between-class correlation coefficients and Pr > |r| to test the hypothesis that the between-class population correlation coefficients are zero
- Total-sample correlation coefficients and Pr > |r| to test the hypothesis that the total population correlation coefficients are zero
- Simple statistics, including N (the number of observations), sum, mean, variance, and standard deviation for the total sample and within each class
- Total-sample standardized class means, obtained by subtracting the grand mean from each class mean and dividing by the total-sample standard deviation
- Pooled within-class standardized class means, obtained by subtracting the grand mean from each class mean and dividing by the pooled within-class standard deviation

At each step, the following statistics are displayed:

- for each variable considered for entry or removal: partial R-square, the squared (partial) correlation, the F statistic, and Pr > F, the probability level, from a one-way analysis of covariance
- the minimum tolerance for entering each variable. A variable is entered only if its tolerance and the tolerances for all variables already in the model are greater than the value specified in the SINGULAR= option. The tolerance for the entering variable is  $1 R^2$  from regressing the entering variable on the other variables already in the model. The tolerance for a variable already in the model is  $1 R^2$  from regressing that variable on the entering variable and the other variables already in the model. With m variables already in the model, for each entering variable, m + 1 multiple regressions are performed by using the entering variable and each of the m variables already in the model as a dependent variable. These m + 1 tolerances are computed for each entering variable, and the minimum tolerance is displayed for each.

The tolerance is computed by using the total-sample correlation matrix. It is customary to compute tolerance by using the pooled within-class correlation matrix (Jennrich 1977), but it is possible for a variable with excellent discriminatory power to have a high total-sample tolerance and a low pooled within-class tolerance. For example, PROC STEPDISC enters a variable that yields perfect discrimination (that is, produces a canonical correlation of one), but a program that uses pooled within-class tolerance does not.

- the variable label, if any
- the name of the variable chosen
- the variables already selected or removed
- Wilks' lambda and the associated F approximation with degrees of freedom and Pr < F, the associated probability level after the selected variable has been entered or removed. Wilks' lambda is the likelihood ratio statistic for testing the hypothesis that the means of the classes on the selected variables are equal in the population (see the section "Multivariate Tests" on page 100 in Chapter 4, "Introduction to Regression Procedures.") Lambda is close to zero if any two groups are well separated.</p>
- Pillai's trace and the associated *F* approximation with degrees of freedom and Pr > *F*, the associated probability level after the selected variable has been entered or removed. Pillai's trace is a multivariate statistic for testing the hypothesis that the means of the classes on the selected variables are equal in the population (see the section "Multivariate Tests" on page 100 in Chapter 4, "Introduction to Regression Procedures").
- Average squared canonical correlation (ASCC). The ASCC is Pillai's trace divided by the number of groups minus 1. The ASCC is close to 1 if all groups are well separated and if all or most directions in the discriminant space show good separation for at least two groups.
- Summary to give statistics associated with the variable chosen at each step. The summary includes the following:
  - Step number
  - Variable entered or removed

- Number in, the number of variables in the model
- Partial R-square
- the F value for entering or removing the variable
- Pr > F, the probability level for the F statistic
- Wilks' lambda
- Pr < Lambda based on the F approximation to Wilks' lambda
- Average squared canonical correlation
- Pr > ASCC based on the F approximation to Pillai's trace
- the variable label, if any

#### **ODS Table Names**

PROC STEPDISC assigns a name to each table it creates. You can use these names to reference the table when using the Output Delivery System (ODS) to select tables and create output data sets. These names are listed in Table 83.2 along with the PROC STEPDISC statement options needed to produce the table. For more information about ODS, see Chapter 20, "Using the Output Delivery System."

Table 83.2 ODS Tables Produced by PROC STEPDISC

ODS Table Name	Description	Option
BCorr	Between-class correlations	BCORR
BCov	Between-class covariances	BCOV
BSSCP	Between-class SSCP matrix	BSSCP
Counts	Number of observations, variables, classes, df	default
CovDF	Nonprinting table of df for covariance matrices	any *COV option
Levels	Class level information	default
Messages	Entry/removal messages	default
Multivariate	Multivariate statistics	default
NObs	Number of observations	default
PCorr	Pooled within-class correlations	PCORR
PCov	Pooled within-class covariances	PCOV
PSSCP	Pooled within-class SSCP matrix	PSSCP
PStdMeans	Pooled standardized class means	STDMEAN
SimpleStatistics	Simple statistics	SIMPLE
Steps	Stepwise selection entry/removal	default
Summary	Stepwise selection summary	default
TCorr	Total-sample correlations	TCORR
TCov	Total-sample covariances	TCOV
TSSCP	Total-sample SSCP matrix	TSSCP
TStdMeans	Total standardized class means	STDMEAN
Variables	Variable lists	default
WCorr	Within-class correlations	WCORR

Table 83.2 continued

<b>ODS Table Name</b>	Description	Option
WCov	Within-class covariances	WCOV
WSSCP	Within-class SSCP matrices	WSSCP

# **Example: STEPDISC Procedure**

## **Example 83.1: Performing a Stepwise Discriminant Analysis**

The iris data published by Fisher (1936) have been widely used for examples in discriminant analysis and cluster analysis. The sepal length, sepal width, petal length, and petal width are measured in millimeters on 50 iris specimens from each of three species: *Iris setosa*, *I. versicolor*, and *I. virginica*.

```
title 'Fisher (1936) Iris Data';
proc format;
   value specname
      1='Setosa
      2='Versicolor'
      3='Virginica ';
run;
data iris:
   input SepalLength SepalWidth PetalLength PetalWidth Species @@;
   format Species specname.;
   label SepalLength='Sepal Length in mm.'
         SepalWidth = 'Sepal Width in mm.'
         PetalLength='Petal Length in mm.'
         PetalWidth = 'Petal Width in mm.';
   datalines;
50 33 14 02 1 64 28 56 22 3 65 28 46 15 2 67 31 56 24 3
63 28 51 15 3 46 34 14 03 1 69 31 51 23 3 62 22 45 15 2
59 32 48 18 2 46 36 10 02 1 61 30 46 14 2 60 27 51 16 2
65 30 52 20 3 56 25 39 11 2 65 30 55 18 3 58 27 51 19 3
   ... more lines ...
63 33 60 25 3 53 37 15 02 1
```

A stepwise discriminant analysis is performed by using stepwise selection.

In the PROC STEPDISC statement, the BSSCP and TSSCP options display the between-class SSCP matrix and the total-sample corrected SSCP matrix. By default, the significance level of an F test from an analysis of covariance is used as the selection criterion. The variable under consideration

is the dependent variable, and the variables already chosen act as covariates. The following SAS statements produce Output 83.1.1 through Output 83.1.8:

```
%let _stdvar = ;
proc stepdisc data=iris bsscp tsscp;
  class Species;
  var SepalLength SepalWidth PetalLength PetalWidth;
run;
```

Output 83.1.1 Iris Data: Summary Information

	Fisher	(1936) Iris Da	ıta	
	The St	TEPDISC Procedu	ıre	
The	Method for Sele	ecting Variable	s is STEPWI	SE
Total Sample Siz	e 150	Variable(s	) in the An	alysis
Class Levels	3	Variable(s	;) Will Be I	ncluded
		Significan	ce Level to	Enter 0.
		Significan	ce Level to	Stay 0.
	umber of Observ		15 15	•
	Class I	Level Informati	.on	
	Variable			
Species	Variable Name	Frequency	Weight	Proportion
-		Frequency	Weight 50.0000	•
Setosa	Name		50.0000	0.333333

Output 83.1.2 Iris Data: Between-Class and Total-Sample SSCP Matrices

		Fisher (1936)	Iris Data		
		The STEPDISC	Procedure		
		Between-Class	SSCP Matrix		
Variable	Label	SepalLength	SepalWidth	PetalLength	PetalWidth
Sepal Length	Sepal Length in mm.	6321.21333	-1995.26667	16524.84000	7127.93333
SepalWidth	Sepal Width in mm.	-1995.26667	1134.49333	-5723.96000	-2293.26667
Petal Length	Petal Length in mm.	16524.84000	-5723.96000	43710.28000	18677.40000
PetalWidth	Petal Width in mm.	7127.93333	-2293.26667	18677.40000	8041.33333

#### Output 83.1.2 continued

Total-Sample SSCP Matrix							
Variable	Label	SepalLength	SepalWidth	PetalLength	PetalWidth		
Sepal Length	Sepal Length in mm.	10216.83333	-632.26667	18987.30000	7692.43333		
SepalWidth	Sepal Width in mm.	-632.26667	2830.69333	-4911.88000	-1812.42667		
Petal Length	Petal Length in mm.	18987.30000	-4911.88000	46432.54000	19304.58000		
_	Petal Width in mm.	7692.43333	-1812.42667	19304.58000	8656.99333		
PetalWidth		7692.43333	-1812.42667	19304.58000	8656.9933		

In step 1, the tolerance is 1.0 for each variable under consideration because no variables have yet entered the model. The variable PetalLength is selected because its F statistic, 1180.161, is the largest among all variables.

Output 83.1.3 Iris Data: Stepwise Selection Step 1

		Fisher (	1936) Iris D	ata			
		The STE	PDISC Proced	ure			
		Stepwise	Selection: S	tep 1			
		Statistics fo	r Entry, DF	= 2, 147			
Variable	Label		R-Square	F Value	Pr >	F To	lerance
SepalLength	Sepal	Length in mm.	0.6187	119.26	<.00	01	1.0000
SepalWidth	Sepal	Width in mm.	0.4008	49.16	<.00	01	1.0000
PetalLength	Petal	Length in mm.	0.9414	1180.16	<.00	01	1.0000
PetalWidth	Petal	Width in mm.	0.9289	960.01	<.00	01	1.0000
		Variable PetalL	ength will b	e entered			
		Variable(s) T	hat Have Bee	n Entered			
		Pe	talLength				
		Multivar	iate Statist	ics			
Statistic			Value	F Value	Num DF	Den DF	Pr > F
Wilks' Lambda			0.058628	1180.16	2	147	<.0001
Pillai's Trac	e		0.941372	1180.16	2	147	<.0001
Average Squar	ed Canor	nical	0.470686				
Correlation							

In step 2, with the variable PetalLength already in the model, PetalLength is tested for removal before a new variable is selected for entry. Since PetalLength meets the criterion to stay, it is used as a covariate in the analysis of covariance for variable selection. The variable SepalWidth is selected because its F statistic, 43.035, is the largest among all variables not in the model and because its associated tolerance, 0.8164, meets the criterion to enter. The process is repeated in steps 3 and 4. The variable PetalWidth is entered in step 3, and the variable SepalLength is entered in step 4.

Output 83.1.4 Iris Data: Stepwise Selection Step 2

Output 83.1.4 Ir	is Data:	Stepwise Selecti	on Step 2					
		Fisher	(1936) Iris D	ata				
		The ST	EPDISC Proced	lure				
		Stepwise	Selection: S	step 2				
		Statistics fo	r Removal, DF	= 2, 147				
Variable	e	Label	R-Sc	quare F	Value	Pr > F		
PetalLe	PetalLength Petal Length in mm. 0.9414 1180.16 <.0001							
	No variables can be removed.							
		Statistics f	or Entry, DF	= 2, 146				
	Partial							
Variable	Label		R-Square	F Value	Pr >	F To	lerance	
SepalLength	_	Length in mm.					0.2400	
SepalWidth	Sepal	Width in mm.			<.000	)1	0.8164	
PetalWidth	Petal	Width in mm.	0.2533	24.77	<.000	)1	0.0729	
		Variable Sepa	lWidth will b	e entered.				
		Variable(s)	That Have Bee	n Entered				
		SepalW	idth PetalLer	igth				
		Multiva	riate Statist	ics				
Statistic			Value	F Value	Num DF	Den DF	Pr > F	
Wilks' Lambda	Wilks' Lambda 0.036884 307.10 4 292 <.000						<.0001	
	Pillai's Trace			93.53	4	294	<.0001	
	Average Squared Canonical 0.559954							
Correlation								

Output 83.1.5 Iris Data: Stepwise Selection Step 3

Correlation

Fisher (1936) Iris Data

The STEPDISC Procedure
Stepwise Selection: Step 3

Statistics for Removal, DF = 2, 146

Partial

Variable Label R-Square F Value Pr > F SepalWidth Sepal Width in mm. 0.3709 + 43.04 < .0001 PetalLength Petal Length in mm. 0.9384 + 1112.95 < .0001

No variables can be removed.

Statistics for Entry, DF = 2, 145

Partial Variable Label R-Square F Value Pr > FTolerance Sepal Length in mm. 0.1447 12.27 <.0001 0.1323 SepalLength PetalWidth Petal Width in mm. 0.3229 34.57 <.0001 0.0662

Variable PetalWidth will be entered.

Variable(s) That Have Been Entered

SepalWidth PetalLength PetalWidth

Multivariate Statistics

Output 83.1.6 Iris Data: Stepwise Selection Step 4

Fisher (1936) Iris Data								
The STEPDISC Procedure								
		Selection: S	-					
	•		•					
Statistics for Removal, DF = 2, 145								
Partial								
Variable	Label	R-Sq	puare F	Value	Pr > F			
SepalWidth	Sepal Width in	mm. 0.	4295	54.58	<.0001			
•	Petal Length in							
PetalWidth			3229					
	No variabl	es can be re	emoved.					
	Statistics fo	r Entry, DF	= 2, 144					
		Partial						
Variable Label		R-Square	F Value	Pr >	F To	lerance		
SepalLength Sepal	Length in mm.	0.0615	4.72	0.01	03	0.0320		
	Variable SepalL	enath will b	e entered	L				
	All variable	s have been	entered.					
Multivariate Statistics								
Statistic		Value	F Value	Num DF	Den DF	Pr > F		
Wilks' Lambda		0.023439	199.15	8	288	<.0001		
Pillai's Trace 1.191899 53.47 8 290 <.0001								
Average Squared Cano	Average Squared Canonical 0.595949							
Correlation								

Since no more variables can be added to or removed from the model, the procedure stops at step 5 and displays a summary of the selection process.

Output 83.1.7 Iris Data: Stepwise Selection Step 5

Fisher (1936) Iris Data The STEPDISC Procedure Stepwise Selection: Step 5 Statistics for Removal, DF = 2, 144Partial Variable Label R-Square F Value Pr > FSepalLength Sepal Length in mm. 0.0615 0.0103 4.72 SepalWidth Sepal Width in mm. 0.2335 21.94 <.0001 PetalLength Petal Length in mm. 0.3308 35.59 <.0001 PetalWidth Petal Width in mm. 24.90 0.2570 <.0001 No variables can be removed.

Output 83.1.8 Iris Data: Stepwise Selection Summary

				No furthe	r steps are	possible.				
Fisher (1936) Iris Data										
				The S	TEPDISC Prod	cedure				
Stepwise Selection Summary										
	Number					Partial			Wilks'	Pr <
Step	In	Entered	Removed	l Label		R-Square	F Value	Pr > F	Lambda	Lambda
1	1	PetalLength		Petal	Length in	0.9414	1180.16	<.0001	0.05862828	<.0001
2	2	SepalWidth		Sepal mm.	Width in	0.3709	43.04	<.0001	0.03688411	<.0001
3	3	PetalWidth		Petal mm.	Width in	0.3229	34.57	<.0001	0.02497554	<.0001
4	4	SepalLength		Sepal	Length in	0.0615	4.72	0.0103	0.02343863	<.0001
						Ave	rage			
						Squa				
		<b>Q1</b>	Number			Canoni		Pr >		
		Step	In	Entered	Removed	Correlat	cion	ASCC		
		1	1	PetalLengt	h	0.47068	3586	<.0001		
		2	2	SepalWidth		0.55995	394	<.0001		
		3	3	PetalWidth		0.59495	5691 ·	<.0001		
		4	4	SepalLengt	h	0.59594	1941	<.0001		

PROC STEPDISC automatically creates a list of the selected variables and stores it in a macro variable. You can submit the following statement to see the list of selected variables:

```
* print the macro variable list;
%put &_stdvar;
```

The macro variable \_StdVar contains the following variable list:

```
SepalLength SepalWidth PetalLength PetalWidth
```

You could use this macro variable if you want to analyze these variables in subsequent steps as follows:

```
proc discrim data=iris;
  class Species;
  var &_stdvar;
run;
```

The results of this step are not shown.

# References

- Costanza, M. C. and Afifi, A. A. (1979), "Comparison of Stopping Rules in Forward Stepwise Discriminant Analysis," *Journal of the American Statistical Association*, 74, 777–785.
- Fisher, R. A. (1936), "The Use of Multiple Measurements in Taxonomic Problems," *Annals of Eugenics*, 7, 179–188.
- Jennrich, R. I. (1977), "Stepwise Discriminant Analysis," in K. Enslein, A. Ralston, and H. Wilf, eds., *Statistical Methods for Digital Computers*, New York: John Wiley & Sons.
- Klecka, W. R. (1980), *Discriminant Analysis*, Sage University Paper Series on Quantitative Applications in the Social Sciences, 07-019, Beverly Hills and London: Sage Publications.
- Puranen, J. (1917), "Fish Catch data set (1917)," Journal of Statistics Education Data Archive, last accessed May 22, 2009.

```
URL http://www.amstat.org/publications/jse/jse_data_archive.html
```

# Subject Index

```
discriminant analysis
    stepwise selection, 7021
STEPDISC procedure
     average squared canonical correlation, 7037
     computational resources, 7035
    input data sets, 7034
    introductory example, 7023
     memory requirements, 7035
     methods, 7021
     missing values, 7034
     ODS table names, 7038
    Pillai's trace, 7037
    stepwise selection, 7023
    time requirements, 7035
    tolerance, 7037
     Wilks' lambda, 7037
stepwise discriminant analysis, 7021
stepwise selection
     STEPDISC procedure, 7023
variable selection
     discriminant analysis, 7021
```

# Syntax Index

PROC STEPDISC statement, 7031

PROC STEPDISC statement, 7029 BCORR option PROC STEPDISC statement, 7029 BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, FREQ statement, 7033 STEPDISC procedure, FREQ statement, 7033 STEPDISC procedure, PROC STEPDISC statement STEPDISC procedure, 7033  BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029  MAXMACRO= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PRESETRY= option, 7031  SLENTRY= option, 7031  STEPDISC procedure, VAR statement, 7033	SLS BCORR option PROC STEPDISC statement, 7029 BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032 STE CLASS statement STEPDISC procedure, 7032 STE STEPDISC procedure, 7032 STE	ENTRY= option
BCORR option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7031 STEPDISC procedure, 7031 STEPDISC procedure, 7031 STEPDISC procedure, BY statement, 7032 STEPDISC procedure, BY statement, 7032 STEPDISC procedure, FREQ statement, 7033 STEPDISC procedure, PROC STEPDISC STEPDISC statement, 7029 BCOV option, 7030 BCOV option PROC STEPDISC statement, 7030 BCOV option, 7031 BCDIAL ARE option	SLS BCORR option PROC STEPDISC statement, 7029 BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032 STE CLASS statement STEPDISC procedure, 7032 STE STEPDISC procedure, 7032 STE	PROC STEPDISC statement, 7031
BCORR option PROC STEPDISC statement, 7029 BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, PROC STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  DATA= option PROC STEPDISC procedure, 7032  DATA= option PROC STEPDISC statement, 7033  STEPDISC procedure, PROC STEPDISC statement, 7033  STEPDISC procedure, PROC STEPDISC statement, 7029  ALL option, 7029 BCORR option, 7029 BCORR option, 7029 BSSCP option, 7029 BSSCP option, 7029 BSSCP option, 7029  MAXMACRO= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PCOR option PROC STEPDISC statement, 7030 PCOV option PROC STEPDISC statement, 7030	BCORR option PROC STEPDISC statement, 7029 BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032 STE CLASS statement STEPDISC procedure, 7032 STE STEPDISC procedure, 7032 STE STEPDISC procedure, 7032 STE	
PROC STEPDISC statement, 7029 BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, RFEQ statement, 7033 STEPDISC procedure, PROC STEPDISC statement, 7039 BCOR option, 7029 MAXMACRO= option, 7029 MAXMACRO= option, 7030 METHOD= option PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030	BCOV option PROC STEPDISC statement, 7029  BSSCP option PROC STEPDISC statement, 7029  STEPDISC procedure, 7032	
BCOV option PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  TSEPDISC procedure, PROC STEPDISC statement, 7031  STEPDISC procedure, PROC STEPDISC procedure, PROC STEPDISC procedure, PROC STEPDISC Statement, 7032  STEPDISC procedure, PROC STEPDISC Statement, 7033  STEPDISC procedure, PROC STEPDISC Statement, 7033  STEPDISC procedure, PROC STEPDISC Statement, 7033  STEPDISC procedure, PROC STEPDISC Statement, 7029  BCOR STEPDISC procedure, 7033  BCORR option, 7029 MAXMACRO= option PROC STEPDISC statement, 7029  MAXMACRO= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030	BCOV option PROC STEPDISC statement, 7029  BSSCP option PROC STEPDISC statement, 7029  STE BY statement STEPDISC procedure, 7032  STE CLASS statement STEPDISC procedure, 7032  STE STEPDISC procedure, 7032  STE	
PROC STEPDISC statement, 7029 BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, BY statement, 7032 STEPDISC procedure, FREQ statement, 7032 STEPDISC procedure, FREQ statement, 7033 STEPDISC procedure, PROC STEPDISC Statement, 7032 STEPDISC procedure, PROC STEPDISC Statement, 7033 STEPDISC procedure, PROC STEPDISC Statement, 7034 S	BSSCP option PROC STEPDISC statement, 7029 STE BY statement STEPDISC procedure, 7032 STE CLASS statement STEPDISC procedure, 7032 STE STEPDISC procedure, 7032 STE	*
BSSCP option PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, BY statement, 7032 STEPDISC procedure, PROC STEPDISC statement, 7032 STEPDISC procedure, PROC STEPDISC statement, 7033 STEPDISC procedure, PROC STEPDISC statement, 7033 STEPDISC procedure, PROC STEPDISC statement, 7029 BCORR option, 7029 BCORR option, 7029 BCOR option, 7029 BCOR STEPDISC statement, 7029 INCLUDE= option PROC STEPDISC statement, 7029 MAXMACRO= option PROC STEPDISC statement, 7029 MAXMACRO= option PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7031 STOP= option, 7031 TCON option, 7031 TCON option, 7031 TCON option, 7032 WCON option, 7032 WCON option, 7032 WSSCP option, 7032 STEPDISC procedure, WEIGHT statement, 7033 STEPDISC procedure, PROC STEPDISC STATEMENT, 7033 STEPDISC procedure, WEIGHT statement, 7033	BSSCP option PROC STEPDISC statement, 7029  BY statement STEPDISC procedure, 7032  STE CLASS statement STEPDISC procedure, 7032  STE STEPDISC procedure, 7032  STE	
PROC STEPDISC statement, 7029 BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, ERFQ statement, 7033 STEPDISC procedure, PROC STEPDISC statement, 7033 STEPDISC procedure, PROC STEPDISC statement, 7033 STEPDISC procedure, PROC STEPDISC statement, 7029  BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7029 BCORR option, 7030 MAXMACRO= option PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7031 PROC STEPDISC	BY statement STEPDISC procedure, 7032 STE CLASS statement STEPDISC procedure, 7032 STE STEPDISC procedure, 7032 STE	<u> </u>
BY statement STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, 7032  STEPDISC procedure, CLASS statement, 7032  STEPDISC procedure, PROC STEPDISC STEPDISC procedure, PROC STEPDISC  STEPDISC procedure, PROC STEPDISC  STEPDISC procedure, PROC STEPDISC  Statement, 7029  BCORR option, 7029  BCORR option, 7029  BCOV option, 7030  BCLUDE= option, 7029  MAXMACRO= option, 7029  MAXMACRO= option, 7030  PCOV option, 7030  PROC STEPDISC statement, 7030	SY statement STEPDISC procedure, 7032 STE CLASS statement STEPDISC procedure, 7032 STE	
STEPDISC procedure, 7032  CLASS statement STEPDISC procedure, CLASS statement, 7032  STEPDISC procedure, FREQ statement, 7033  STEPDISC procedure, FREQ statement, 7033  STEPDISC procedure, PROC STEPDISC  statement, 7028  ALL option, 7029  BCORR option, 7029  BSSCP option, 7029  BSSCP option, 7030  METHOD= option  PROC STEPDISC statement, 7030  METHOD= option  PROC STEPDISC statement, 7030  METHOD= option  PROC STEPDISC statement, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC STEPDISC STEPDIS	CLASS statement STE STEPDISC procedure, 7032 STE	<u>-</u>
CLASS statement STEPDISC procedure, CLASS statement, 7032 STEPDISC procedure, FREQ statement, 7033 STEPDISC procedure, FREQ statement, 7033 STEPDISC procedure, PROC STEPDISC Statement, 7029  BCOR option, 7029 BCOR option, 7029 BCOR option, 7029 BCOR option, 7029 BCOR option, 7029 BCOR option, 7029 BCOR option, 7029 DATA= option, 7029 DATA= option, 7029 DATA= option, 7029 DATA= option, 7029 MAXMACRO= option, 7029 MAXMACRO= option, 7029 MAXMACRO= option, 7030 METHOD= option PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7031	CLASS statement STE STEPDISC procedure, 7032 STE	
CLASS statement STEPDISC procedure, 7032 STEPDISC procedure, PROC STEPDISC statement, 7029 STEPDISC statement, 7029 FREQ statement STEPDISC procedure, 7033 STEPDISC procedure, PROC STEPDISC statement, 7029 BCORR option, 7029 MAXMACRO= option, 7029 MAXMACRO= option, 7030 METHOD= option PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030 PCORR option PROC STEPDISC statement, 7030 PCORR option PROC STEPDISC statement, 7030 PCOV option PROC STEPDISC statement, 7030 PROC STEPDISC	STEPDISC procedure, 7032 STE	
DATA= option PROC STEPDISC statement, 7029  FREQ statement STEPDISC procedure, 7033  INCLUDE= option PROC STEPDISC statement, 7029  INCLUDE= option PROC STEPDISC statement, 7029  INCLUDE= option PROC STEPDISC statement, 7029  MAXMACRO= option PROC STEPDISC statement, 7029  MAXMACRO= option PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PROC STEPDISC sta	STEPDISC procedure, 7032 STE	-
DATA= option PROC STEPDISC statement, 7029  FREQ statement STEPDISC procedure, 7033  FREQ statement STEPDISC procedure, 7033  BSSCP option, 7029  BSSCP option, 7029  BSSCP option, 7029  BSSCP option, 7029  DATA= option, 7029  INCLUDE= option PROC STEPDISC statement, 7029  MAXMACRO= option, 7029  MAXMACRO= option, 7030  MAXMACRO= option PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  STOP= option, 7031  TCORR option, 7031  WCORR option, 7032  WCOV option, 7032  WCOV option, 7032  WCOV option, 7032  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033		
PROC STEPDISC statement, 7029  FREQ statement STEPDISC procedure, 7033  BSSCP option, 7029  BCOR option, 7029  BSSCP option, 7029  INCLUDE= option PROC STEPDISC statement, 7029  MAXMACRO= option PROC STEPDISC statement, 7029  MAXMACRO= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 8ee STEPDISC procedure PSSCP option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	DATA= option	-
FROC STEPDISC statement, 7029  FREQ statement STEPDISC procedure, 7033  BCOR option, 7029  BCOV option, 7029  BSSCP option, 7029  DATA= option, 7029  INCLUDE= option PROC STEPDISC statement, 7029  MAXMACRO= option, 7030  MAXMACRO= option PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  STOP= option, 7031  TCOR option, 7031  TCOV option, 7032  WCOV option, 7032  WSSCP option, 7032  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	<u>*</u>	
FREQ statement STEPDISC procedure, 7033  STEPDISC procedure, 7033  BSSCP option, 7029  BSSCP option, 7029  DATA= option, 7029  INCLUDE= option PROC STEPDISC statement, 7029  MAXMACRO= option, 7029  MAXMACRO= option, 7030  MAXMACRO= option PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PCOV option PROC STEPDISC statement, 7030  STOP= option, 7031  TCORR option, 7032  WCOV option, 7032  WCOV option, 7032  WSSCP option, 7032  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	PROC STEPDISC statement, 7029	-
STEPDISC procedure, 7033  STEPDISC procedure, 7033  STEPDISC procedure, 7033  STEPDISC procedure, 7033  BSSCP option, 7029  DATA= option, 7029  INCLUDE= option, 7029  MAXMACRO= option, 7030  MAXMACRO= option  PROC STEPDISC statement, 7029  MAXMACRO= option, 7030  MAXMACRO= option  PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  PCORR option, 7030  PCOV option, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PRESTAY= option  PROC STEPDISC statement, 7030  PRESTAY= option  PROC STEPDISC statement, 7030  PRESTAY= option  PROC STEPDISC statement, 7030  STOP= option, 7031  TCON option, 7031  WCORR option, 7032  WCOV option, 7032  WSSCP option, 7032  WSSCP option, 7032  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	EDEO 444	•
DATA= option, 7029  INCLUDE= option PROC STEPDISC statement, 7029  MAXMACRO= option, 7029  MAXMACRO= option, 7030  MAXSTEP= option, 7030  PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  PROC STEPDISC statement, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  METHOD= option, 7030  PROC STEPDISC statement, 8ee STEPDISC procedure  PSSCP option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033		
INCLUDE= option PROC STEPDISC statement, 7029 MAXMACRO= option, 7029 MAXSTEP= option, 7030 MAXMACRO= option PROC STEPDISC statement, 7029 MAXSTEP= option, 7030 METHOD= option, 7030 PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030 METHOD= option PROC STEPDISC statement, 7030 PR2ENTRY= option, 7030 PSSCP option, 7030 SHORT option, 7031 SIMPLE option, 7031 SIMPLE option, 7031 SIMPLE option, 7031 SLENTRY= option, 7031 SLENTRY= option, 7031 START= option, 7031 START= option, 7031 STOP= option, 7031 TCOR option, 7031 TCOR option, 7031 TCOR option, 7031 TCOV option, 7031 SSCP option, 7032 WCOV option, 7032 WCOV option, 7032 STEPDISC procedure, WEIGHT statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	STEPDISC procedure, 7033	•
PROC STEPDISC statement, 7029  MAXMACRO= option, 7030  MAXMACRO= option, 7030  MAXMACRO= option, 7030  METHOD= option, 7030  METHOD= option, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  METHOD= option, 7030  PROC STEPDISC statement, 7030  METHOD= option, 7030  PROC STEPDISC statement, 8ee STEPDISC procedure  PSSCP option  PROC STEPDISC statement, 7030  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	NCLUDE- antion	*
MAXMACRO= option PROC STEPDISC statement, 7029  MAXSTEP= option, 7030  METHOD= option, 7030  PCOR option, 7030  PCOV option, 7030  PRESTAY= option, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PCOV option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PRESTAY= option PROC STEPDISC statement, 7030  PRESTAY= option PROC STEPDISC statement, 7030  PRESTAY= option PROC STEPDISC statement, 7030  STOP= option, 7031 TCORR option, 7031 TCOV option, 7032 WCOV option, 7032 TEPDISC procedure, VAR statement, 7033 TEPDISC procedure, WEIGHT statement, 7033 TEPDISC procedure, WEIGHT statement, 7033	1	*
MAXMACRO= option PROC STEPDISC statement, 7029  MAXSTEP= option PROC STEPDISC statement, 7030  METHOD= option, 7030 PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 8ee STEPDISC procedure PROC STEPDISC statement, 7030  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	FROC STEPDISC statement, 7029	
PROC STEPDISC statement, 7029  MAXSTEP= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PR2STAY= option, 7031  SIMPLE option, 7031  SIMPLE option, 7031  SIMPLE option, 7031  SLENTRY= option, 7031  SLENTRY= option, 7031  SLENTRY= option, 7031  START= option, 7031  START= option, 7031  STOP= option, 7031  TCORR option, 7031  TCORR option, 7031  TCOV option, 7031  WCORR option, 7032  WCOV option, 7032  WCOV option, 7032  WSSCP option, 7032  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	MAXMACRO= option	
MAXSTEP= option PROC STEPDISC statement, 7030 PROC STEPDISC statement, 8ee STEPDISC procedure PSSCP option PROC STEPDISC statement, 7030 SHORT option PROC STEPDISC statement, 7030 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033 STEPDISC procedure, WEIGHT statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	*	* '
PROC STEPDISC statement, 7030  METHOD= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 8ee STEPDISC procedure  PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033		*
METHOD= option PROC STEPDISC statement, 7030 PR2ENTRY= option PROC STEPDISC statement, 7030 PR2ENTRY= option PROC STEPDISC statement, 7030 PR2STAY= option PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7030 PROC STEPDISC statement, 8ee STEPDISC PROC STEPDISC statement, 8ee STEPDISC PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7030 PROC STEPDISC statement, 7030 SHORT option PROC STEPDISC statement, 7030 SHORT option PROC STEPDISC statement, 7031 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		
PROC STEPDISC statement, 7030  PCORR option PROC STEPDISC statement, 7030  PCOV option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC PROC STEPDISC statement, see STEPDISC PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033		<u> </u>
PCORR option PROC STEPDISC statement, 7030  PCOV option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure  PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7031  SHORT option, 7031 SLENTRY= option, 7031 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	<u> </u>	<u> </u>
PCORR option PROC STEPDISC statement, 7030  PCOV option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC Procedure  PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  SIMPLE option, 7031 SINGULAR= option, 7031 START= option, 7031 STOP= option, 7031 TCORR option, 7031 TCOV option, 7031 TCOV option, 7031 TCOV option, 7031 WCORR option, 7032 WCOV option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	THOS STEP BISS statement, 7000	•
PROC STEPDISC statement, 7030  PCOV option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  SINGULAR= option, 7031  SLSTAY= option, 7031  STOP= option, 7031  TCORR option, 7031  TCOV option, 7031  TCOV option, 7031  WCORR option, 7031  WCORR option, 7032  WCOV option, 7032  WSSCP option, 7032  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	PCORR option	
PCOV option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC Procedure PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  STEPDISC option, 7031 WCORR option, 7031 WCORR option, 7031 WCORR option, 7032 WCOV option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		
PROC STEPDISC statement, 7030  PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PSSCP option PROC STEPDISC statement, 7030  STEPDISC option, 7031 WCORR option, 7031 WCORR option, 7032 WCOV option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		*
PR2ENTRY= option PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PSSCP option PROC STEPDISC statement, 7030  STEPDISC statement, 7032 WCOV option, 7032 WSSCP option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	<u>-</u>	-
PROC STEPDISC statement, 7030  PR2STAY= option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure PSSCP option PROC STEPDISC statement, 7030  PROC STEPDISC statement, 7030  STEPDISC option, 7031 TCOV option, 7031 TCOV option, 7031 TSSCP option, 7031 WCORR option, 7032 WCOV option, 7032 WCOV option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		-
PR2STAY = option PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure  PSSCP option PROC STEPDISC statement, 7030  STOP= option, 7031 TCORR option, 7031 TCOV option, 7031 TSSCP option, 7031 WCORR option, 7032 WCOV option, 7032 WSCP option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		
PROC STEPDISC statement, 7030  PROC STEPDISC statement, see STEPDISC procedure  PROC STEPDISC statement, see STEPDISC procedure  PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7031  STEPDISC procedure  STOT = option, 7031 TCORR option, 7031 TCOV option, 7031 WCORR option, 7031 WCOV option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		
PROC STEPDISC statement, see STEPDISC procedure  PSSCP option PROC STEPDISC statement, 7030  SHORT option PROC STEPDISC statement, 7031  PROC STEPDISC statement, 7031  TCOV option, 7031 WCORR option, 7031 WCOV option, 7032 WSSCP option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	<u> •</u>	<u>.</u>
procedure  PSSCP option  PSSCP option  PROC STEPDISC statement, 7030  SHORT option  PROC STEPDISC statement, 7031  STEPDISC procedure, WEIGHT statement, 7033  STEPDISC procedure, WEIGHT statement, 7033		
PSSCP option PROC STEPDISC statement, 7030  WCORR option, 7032 WCOV option, 7032 WSSCP option, 7032 WSSCP option, 7032 STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033		
PROC STEPDISC statement, 7030  WCOV option, 7032  WSSCP option, 7032  WSSCP option, 7032  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	•	*
SHORT option PROC STEPDISC statement, 7031  STEPDISC procedure, VAR statement, 7033 STEPDISC procedure, WEIGHT statement, 7033	<u>*</u>	<u> -</u>
PROC STEPDISC statement, 7031  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	The Cararage sunction, 7000	
PROC STEPDISC statement, 7031  STEPDISC procedure, VAR statement, 7033  STEPDISC procedure, WEIGHT statement, 7033	SHORT option	
STEPLINE procedure Wellight statement ///33	PROC STEPDISC statement 7031	
SIMPLE OPHOLI	SIMPLE option 511	
PROC STEPDISC statement 7031 STOP= option	*	
PROCNIEPING Gratement (US)	SINGULAR= option	P= option

TCORR option

PROC STEPDISC statement, 7031

TCOV option

PROC STEPDISC statement, 7031

TSSCP option

PROC STEPDISC statement, 7031

VAR statement

STEPDISC procedure, 7033

WCORR option

PROC STEPDISC statement, 7032

WCOV option

PROC STEPDISC statement, 7032

WEIGHT statement

STEPDISC procedure, 7033

WSSCP option

PROC STEPDISC statement, 7032

# **Your Turn**

We welcome your feedback.

- If you have comments about this book, please send them to yourturn@sas.com. Include the full title and page numbers (if applicable).
- If you have comments about the software, please send them to suggest@sas.com.

# **SAS®** Publishing Delivers!

Whether you are new to the work force or an experienced professional, you need to distinguish yourself in this rapidly changing and competitive job market. SAS\* Publishing provides you with a wide range of resources to help you set yourself apart. Visit us online at support.sas.com/bookstore.

#### **SAS®** Press

Need to learn the basics? Struggling with a programming problem? You'll find the expert answers that you need in example-rich books from SAS Press. Written by experienced SAS professionals from around the world, SAS Press books deliver real-world insights on a broad range of topics for all skill levels.

support.sas.com/saspress

#### **SAS®** Documentation

To successfully implement applications using SAS software, companies in every industry and on every continent all turn to the one source for accurate, timely, and reliable information: SAS documentation. We currently produce the following types of reference documentation to improve your work experience:

- Online help that is built into the software.
- Tutorials that are integrated into the product.
- Reference documentation delivered in HTML and PDF free on the Web.
- Hard-copy books.

support.sas.com/publishing

#### **SAS® Publishing News**

Subscribe to SAS Publishing News to receive up-to-date information about all new SAS titles, author podcasts, and new Web site features via e-mail. Complete instructions on how to subscribe, as well as access to past issues, are available at our Web site.

support.sas.com/spn



Sas THE POWER TO KNOW